

JD Edwards EnterpriseOne

Applications Upgrade Guide

Applications Release 9.1 and Tools Release 9.1.x for IBMi with
DB2/400

E23322-17

August 2014

Copyright © 2011, 2014, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Contents

1 Understanding JD Edwards EnterpriseOne

1.1	Understanding This Guide	1-1
1.2	Understanding the Upgrade Process	1-2
1.2.1	What an Upgrade Preserves and Replaces	1-4
1.2.1.1	Interactive Application Rules	1-4
1.2.1.2	Report Rules	1-5
1.2.1.3	Application Text Changes	1-5
1.2.1.4	UBE Text Changes	1-5
1.2.1.5	Table Specification Rules	1-5
1.2.1.6	Control Table Rules	1-6
1.2.1.7	Business View Rules	1-6
1.2.1.8	Rules for Event Rules	1-6
1.2.1.9	Data Structure Rules	1-7
1.2.1.10	Business Function Rules	1-7
1.2.1.11	Versions	1-7
1.2.2	Understanding the Deployment Server Installation	1-7
1.2.3	Understanding the Platform Pack Installation.....	1-7
1.2.4	Understanding the Installation Planner	1-8
1.2.5	Understanding Installation Workbench.....	1-9
1.2.6	Understanding the Workstation Installation.....	1-9
1.3	Considering Additional Factors.....	1-10
1.3.1	Accessing Minimum Technical Requirements (Certifications).....	1-10
1.3.2	Understanding Machine Names.....	1-11
1.3.3	Accessing IBM i Performance Tuning and White Papers.....	1-11
1.3.4	Using JD Edwards EnterpriseOne Support	1-11
1.3.5	Understanding Documentation Conventions	1-11
1.3.5.1	Documentation Updates.....	1-12
1.3.5.2	Tips	1-12
1.3.5.3	Fonts and Type Styles	1-12
1.4	Working With the Customer Checklist	1-12
1.5	Environments Overview	1-13
1.5.1	Understanding Environments	1-13
1.5.2	Planner Environment (JDEPLAN)	1-14
1.5.2.1	Planner Pathcode	1-14
1.5.2.2	Planner Database	1-14
1.5.3	Pristine Environment (PS910)	1-15

1.5.4	Deployment Environment (DEP910)	1-15
1.5.5	Development Environment (DV910)	1-15
1.5.6	Prototype Environment (PY910).....	1-16
1.5.7	Production Environment (PD910).....	1-16
1.5.8	Additional Considerations	1-16
1.5.8.1	Cluster Software Options	1-16
1.5.8.2	Web-Based Options.....	1-16
1.5.9	Release History.....	1-16
1.6	Language Process Overview	1-16
1.6.1	Language Architecture	1-17
1.6.1.1	Base Language	1-17
1.6.1.2	Alternate Language Components	1-17
1.6.1.3	Language Preference Codes	1-18
1.6.2	Database Character Set and Code Page Considerations	1-18
1.6.2.1	Unicode	1-18
1.6.2.2	Code Page Settings	1-19
1.6.2.2.1	DB2\400 Code Page Settings.....	1-19
1.6.2.2.2	Workstations and Deployment Server	1-20
1.6.3	National Language Support	1-20
1.6.3.1	Single-Byte and Double-Byte Considerations	1-20
1.6.3.2	Font Considerations	1-21
1.6.3.3	User Display Preferences	1-21

2 Before You Begin the Upgrade

2.1	Preparing to Upgrade to Release 9.1 from Prior Releases	2-1
2.2	Preparing the Prototype Environment	2-2
2.3	Preparing the Development Environment	2-3
2.4	Preparing the DB2/400 Database for Table Conversions	2-4
2.5	Checking Modification and Merge Flags	2-5
2.6	Changing the Journal	2-6
2.7	Refreshing and Verifying Data	2-7
2.7.1	Refreshing the Business Data	2-7
2.7.2	Deleting SQL Packages	2-8
2.7.3	Refreshing the Control Tables	2-8
2.7.4	Verifying Custom Changes in Master Control Tables	2-9
2.7.5	Backing Up the Servers and Databases	2-10
2.7.5.1	Backing up the Deployment Server	2-10
2.7.5.2	Backing Up the Enterprise Server	2-10
2.7.5.3	Backing Up the Oracle Databases	2-10
2.7.6	Working with Purge Tables	2-10
2.7.7	Working with Accounts Payable Processing.....	2-11
2.8	Verifying Software and Hardware Requirements	2-11
2.8.1	Adding a New Entry to the QAQQINI File.....	2-11
2.8.2	Setting up Your IBM i.....	2-13
2.8.2.1	Setting Up AS\400 TCP\IP Services	2-13
2.8.2.2	Setting Up a Network Share for IBM i Root	2-15
2.8.2.3	Starting the EDRSQL Service.....	2-17

2.9	Verifying the Disk Space Requirements	2-18
2.10	Cleaning Up Disk Space on the Servers.....	2-19
2.11	Applying Microsoft Product Updates	2-19

3 Working with the Deployment Server

3.1	Using IXS (Integrated xSeries Server) for Deployment.....	3-1
3.2	Planning for IBM i Integration	3-4
3.3	Installing Microsoft Windows Visual Studio.....	3-8
3.4	Understanding the Deployment Server.....	3-8
3.5	Local Oracle Enterprise Edition (OEE) Considerations	3-9
3.5.1	32-Bit Oracle Database Client (Required for both 32-bit and 64-bit versions of OEE)	3-10
3.5.2	EnterpriseOne Application P96717	3-11
3.5.3	Best Practices for OEE Performance.....	3-12
3.5.4	Microsoft Windows Internet Protocol Version 4 (IPv4).....	3-12
3.6	Obtaining and Preparing the Deployment Server Install Image	3-13
3.7	Working with JDBC Drivers on the Deployment Server	3-14
3.7.1	Obtaining the JDBC Drivers.....	3-14
3.7.2	Copying the JDBC Drivers to the Deployment Server	3-15
3.8	Installing the Deployment Server.....	3-15
3.8.1	Prerequisites	3-17
3.8.2	Installation Process Flow	3-17
3.8.3	Before Launching the Deployment Server Installer	3-17
3.8.4	Understanding Destination Paths	3-18
3.8.5	Using InstallManager to Install a Local Database on the Deployment Server	3-18
3.8.5.1	Using InstallManager to Install a Local Database in the Default Location.....	3-19
3.8.5.2	Running OEESetup to Install a Local Database in a Directory Other Than the Default Location	3-20
3.8.6	Examine the Local Database Installer Logs	3-22
3.8.7	Understanding the JD Edwards EnterpriseOne Deployment Server Installer.....	3-23
3.8.7.1	Understanding EnterpriseOne Files Location.....	3-23
3.8.7.2	Running the JD Edwards EnterpriseOne Deployment Server Installer	3-25
3.9	Adding Additional Environments (Rerunning the Deployment Server Installer)	3-37
3.10	Downloading and Installing the Latest Software.....	3-37
3.10.1	Installing the Latest Tools Release and Latest Tools Release Patch to the Deployment Server	3-38
3.10.2	Installing the Latest Planner Update and Running the Special Instructions	3-38
3.11	Troubleshooting Deployment Server Installation.....	3-40
3.11.1	Verify Local Planner Tablespace are Not Attached	3-40
3.11.2	OEE Installer Logs	3-40
3.11.3	Configuration Files	3-41
3.11.4	Path Code Master (F98611).....	3-42
3.11.5	Oracle Enterprise Edition	3-42
3.11.5.1	File Locations.....	3-43
3.11.5.1.1	Oracle Installation Directory	3-43
3.11.5.1.2	OEE Logs	3-43
3.11.5.1.3	tnsnames.ora	3-43

3.11.5.2	Rebooting the Deployment Server	3-44
3.11.5.3	EnterpriseOne Access to the Local Oracle Database	3-44
3.11.5.4	Process Explorer	3-44
3.11.5.5	Verifying the Local Oracle Database Installation	3-46
3.11.5.6	Deployment Server Installation Problems	3-46
3.11.5.7	Runtime Problems	3-46
3.11.5.7.1	Jde.log shows ORA-12541: TNS:no listener.....	3-46
3.11.5.7.2	User gets a pop-up window prompting for E1Local DB user and password and Jde.log shows OCI0000141 - Error - ORA-01017: invalid username/password; logon denied 3-46	
3.11.5.7.3	tnsnames.ora	3-47
3.11.5.8	Administering the Local Oracle Database Using SQL Plus	3-47
3.11.5.9	Encrypting the Password of the Local Oracle Database	3-47
3.11.5.10	Decrypting the Password of the Local Oracle Database.....	3-48
3.11.5.11	Import and Export Tablespaces to the Local Oracle Database	3-49
3.11.5.11.1	Import Tablespace Script (attach_planner.bat)	3-49
3.11.5.11.2	Export Tablespace Script (detach_planner.bat)	3-49
3.11.5.12	Updating the InstallManager.htm File	3-50
3.11.5.13	Deployment.inf and <Package_name>.inf	3-51

4 Working with the Platform Pack on the IBM i

4.1	Understanding the Platform Pack	4-1
4.2	Platform Pack Process Flow	4-2
4.3	Configuring the Enterprise Server Prior to Installing the Platform Pack.....	4-2
4.3.1	Understanding the Prerequisites	4-3
4.3.2	Understanding Security for the Platform Pack Installer	4-3
4.3.3	Setting the System Values.....	4-3
4.3.4	Setting up the TCP\IP Protocol for Enterprise Server	4-4
4.3.5	Setting up IBM i Access on your Enterprise Server	4-5
4.3.6	Starting the Remote Database TCP\IP Service (Optional)	4-6
4.3.7	Optimizing Machine Resources.....	4-6
4.3.8	Cleaning Up From Prior Installations.....	4-7
4.3.9	Testing Long File Names on the IBM i	4-7
4.3.10	Checking for Co-existence Tables.....	4-7
4.3.11	Adding Entries to the System Reply List	4-8
4.3.12	Rebuilding Cross Reference Tables on the IBM i	4-8
4.4	Understanding the Platform Pack Installation on the IBM i	4-8
4.5	Running the JD Edwards EnterpriseOne Platform Pack Installer for the IBM i.....	4-9
4.6	Troubleshooting the IBM i Platform Pack Installation	4-23
4.6.1	Invalid User or Password	4-23
4.6.2	Abnormal Program Termination - jt400.jar and/or util.jar Missing.....	4-23
4.6.3	Business Data or Control Tables Already Exist.....	4-24
4.6.4	Business Data or Control Tables Do Not Exist.....	4-24
4.7	Rerunning the JD Edwards EnterpriseOne Platform Pack Installer	4-25
4.7.1	Enterprise Server.....	4-26
4.7.2	Database Server.....	4-26

4.8	Installing the Latest Tools Release and Latest Tools Release Patch to the Enterprise Server..	4-26
4.9	Working with Database Security	4-27

5 Working with the Installation Planner for an Upgrade

5.1	Understanding the Planner Process for Upgrades.....	5-1
5.1.1	Dropping SQL Packages	5-2
5.1.2	Defining the SQL Package Creation Location	5-2
5.1.3	Assumptions about Mandatory Pre-Upgrade Process.....	5-2
5.1.4	Mandatory Pre-Upgrade Process - Upgrading the Pristine Environment.....	5-3
5.1.5	Running Table Conversions Locally	5-3
5.1.6	Deferring Index Builds (Tools Release 9.1 Update 2).....	5-4
5.2	Working with JD Edwards EnterpriseOne Software Requirements	5-4
5.3	Reviewing Installation Planner Processing Options	5-4
5.3.1	Assumptions About Reviewing Installation Planner Processing Options.....	5-4
5.3.2	Accessing Processing Options	5-5
5.3.3	Choosing Processing Option Values	5-5
5.3.3.1	Specifying the Prompt Mode	5-5
5.3.3.2	Specifying the Process Mode	5-6
5.3.3.3	Specifying the Default Mode	5-7
5.3.3.4	Verifying Status Change Values Have Not Changed	5-9
5.3.3.5	Specifying Plan Completion Processes.....	5-9
5.3.3.6	Specifying Replication Options	5-10
5.4	Running the Installation Planner for an Upgrade.....	5-12
5.4.1	Starting Installation Planner.....	5-12
5.4.2	Entering a Plan Description	5-12
5.4.3	Entering Location Information	5-17
5.4.4	Entering Deployment Server Information	5-18
5.4.5	Entering Enterprise Server Information	5-21
5.4.6	Enter Data Source Information for Server Map	5-24
5.4.7	Entering HTML Web Server Information	5-25
5.4.8	Entering Data Server Information.....	5-28
5.4.9	Entering Shared Data Source Information.....	5-30
5.4.9.1	Specifying (Custom or Default) Shared Data Source setup information	5-30
5.4.9.2	Verifying the Data Source for Data Dictionary	5-30
5.4.9.3	Verifying the Object Librarian Data Source	5-31
5.4.9.4	Verifying the OWJRNL Data Source	5-32
5.4.9.5	Verifying the System Data Source	5-33
5.4.10	Setting Up Environments	5-34
5.4.10.1	Selecting an Environment	5-35
5.4.10.2	Specifying Environment Data Load Parameters	5-36
5.4.10.3	Verifying Advanced Parameters	5-37
5.4.10.4	Selecting Languages (optional).....	5-39
5.4.11	Setting Up Environment Data Sources	5-39
5.4.11.1	Selecting an Environment Data Source Setup Option	5-40
5.4.11.2	Setting Up the Data Source for Business Data	5-40
5.4.11.3	Setting Up the Data Source for Central Objects	5-42

5.4.11.4	Setting Up the Data Source for Control Tables	5-43
5.4.11.5	Verifying the Data Dictionary Data Source	5-44
5.4.11.6	Verifying the Data Source for Versions.....	5-45
5.4.12	Adding a Remote Location.....	5-45
5.4.13	Finalizing the Installation Plan	5-46
5.4.14	Concluding the Validation Planner Report	5-47
5.4.15	Resetting the jde.ini Prior to Running Table Conversions	5-47
5.4.16	Clearing SQL Packages from QRECOVERY.....	5-47
5.5	Deleting Machines from an Installation Plan.....	5-48
5.6	Verify and Configure Data Source for Previous Release	5-48

6 Working With Installation Workbench

6.1	Understanding Workbench Components	6-1
6.1.1	Verifying the Network Share on the Deployment Server.....	6-3
6.1.2	Loading Data (Demo Data and Production Data)	6-4
6.1.3	Creating the Job Queue.....	6-7
6.1.4	Deferring Indexes for Table Conversion Workbench (Tools Release 9.1 Update 2)..	6-9
6.2	Verifying OCM Mappings.....	6-9
6.3	Adding an Entry to the Remote Database Directory	6-9
6.4	Verifying the Language Code Character Set	6-10
6.5	Working with Unattended Workbench Mode.....	6-11
6.5.1	Selecting Attended or Unattended Workbench Mode	6-11
6.5.2	Setting a Task Break in Unattended Workbench Mode	6-11
6.6	Solution Explorer	6-12
6.7	Changing the Status of the Control Table Workbench Tasks.....	6-12
6.8	Verify and Update P98MOQUE Settings	6-13
6.9	Starting Installation Workbench	6-13
6.10	Working With Initial Tasks Workbench.....	6-15
6.10.1	Using Initial Tasks Workbench.....	6-15
6.10.2	Changing the Status of Initial Tasks Workbench.....	6-17
6.11	Configuring Your Locations.....	6-19
6.12	Configuring Your Data Sources.....	6-19
6.13	Configuring Your Environments.....	6-20
6.14	Using Machine Workbench	6-21
6.15	Understanding Control Table Merges	6-22
6.15.1	Language Installation.....	6-22
6.15.2	Configuring Control Tables	6-23
6.16	Understanding Table Conversions	6-24
6.16.1	Running Table Conversions	6-25
6.16.2	Table Conversion Workbench Architecture	6-27
6.16.3	Configuring Table Conversions to Run on the Enterprise Server	6-27
6.16.3.1	Table Conversion Schedule.....	6-28
6.16.3.2	Upgrade Plan Definition	6-29
6.16.3.3	Select Enterprise Server and Maximum Jobs On Select Environments - Advanced Exit	6-30
6.16.3.4	Configuring Queues.....	6-31
6.16.3.5	Starting Table Conversions	6-31

6.16.3.6	Monitoring Table Conversions.....	6-32
6.16.3.7	Working With Table Conversion Log Files	6-33
6.16.3.8	Stopping Table Conversions	6-35
6.16.3.9	Restarting Installation Workbench	6-35
6.16.3.10	Troubleshooting Table Conversions.....	6-35
6.16.3.10.1	Enabling the Print UBE Job Log	6-35
6.16.3.10.2	General Problems	6-36
6.16.4	Verifying the Table Conversion Process	6-40
6.16.4.1	Understanding Table Conversion Dependencies	6-40
6.16.4.2	Verifying Table Conversions	6-40
6.16.4.3	Understanding Table Format Verification.....	6-41
6.16.4.3.1	Verifying Table Formats.....	6-42
6.16.4.4	Rerunning Table Conversion Programs	6-43
6.16.5	Deferring Index Builds During Table Conversion Workbench (Tools Release 9.1 Update 2) 6-45	
6.17	Understanding Obsolete Tables.....	6-51
6.17.1	System Code 88 Obsolete Tables	6-51
6.17.2	System Code 89 Obsolete Tables.....	6-58
6.18	Understanding Specification Table Merges	6-60
6.18.1	Merging Specification Tables	6-60
6.18.2	Restarting the Specification Merge	6-61
6.19	Using the Package Workbench	6-62
6.20	Using Remote Location Workbench	6-62
6.20.1	Configuring Remote Locations	6-63
6.21	Finishing Installation Workbench	6-64

7 Working With the Enterprise Server

7.1	Verifying the Enterprise Server Installation Using PORTTEST.....	7-1
7.2	Starting Network Services on the Enterprise Server	7-2
7.3	Stopping Network Services on the Enterprise Server	7-2
7.4	Creating an Output Queue for the Default Printer.....	7-3
7.5	Creating the Job Queue	7-3
7.6	Working with OCM Generation	7-3
7.6.1	Understanding OCM Mappings.....	7-4
7.6.2	Understanding Data Source Setup	7-4
7.6.3	Understanding OCM Creation	7-4
7.6.3.1	Understanding Database Data Sources.....	7-4
7.6.3.2	Understanding Logic Data Sources	7-5
7.6.4	Understanding OCM Customization.....	7-5
7.6.4.1	Understanding Data Classes.....	7-5
7.6.4.2	Creating a New Data Class	7-6
7.6.4.3	Modifying the Data Source Template.....	7-6
7.6.4.4	Associating Table Data Classes	7-6
7.7	Setting Up a Printer on the Enterprise Server.....	7-7
7.7.1	Adding a New Printer.....	7-7
7.7.2	Defining a Default Printer	7-13
7.8	Enabling Multiple Concurrent Table Conversions	7-14

8 Installing the Development Clients for Developers and System Administrators

8.1	Understanding Development Client Installation	8-1
8.2	Preparing for Development Client Installation	8-1
8.3	Working With Development Client Installation	8-3
8.3.1	Creating a Desktop Shortcut	8-4
8.3.2	Using a Shared Drive	8-4
8.3.3	Understanding Third-Party Products.....	8-5
8.4	Understanding User Profiles and Languages.....	8-5

9 Performing Merges

9.1	Working with Control Table Merges	9-1
9.1.1	Working with Customer Base Merges.....	9-2
9.1.2	Working with Language-Specific Table Merges	9-2
9.1.3	Working with Data Dictionary Merge.....	9-2
9.1.4	Work with Solution Explorer Merge	9-3
9.1.5	Working with UDC Merge	9-4
9.1.6	Working with Favorites Merge.....	9-4
9.1.7	Working with Report Director Templates Merge.....	9-4
9.1.8	Working with Tips of the Day Merge.....	9-4
9.1.9	Working with Workflow Merge.....	9-5
9.2	Working with Specification Merges	9-5
9.3	Working with Object Librarian Merge	9-6
9.4	Working with Versions List Merge	9-7
9.5	Working with Central Objects Merge	9-7
9.6	Working with Update Language Text Merge.....	9-7

10 Understanding Media Object Queues

10.1	Overview	10-1
10.2	Modifying Media Object Queues	10-1
10.3	Specifying the Help Location Used by the Web Client and Development Client.....	10-3

11 Performing Post Upgrade Tasks

11.1	Setting Up Microsoft Windows Security on Release 9.1 Directories.....	11-1
11.1.1	Setting Security on the Pathcode Directory	11-2
11.1.2	Setting Security on the Database Directory	11-2
11.1.3	Setting Security on the Data Dictionary Directory	11-2
11.1.4	Setting Security on the Helps Directory	11-2
11.1.5	Setting Security on the Media Object Directory	11-3
11.1.6	Setting Security on the Planner Directory	11-3
11.1.7	Setting Security on the Print Queue Directory	11-3
11.1.8	Setting Security on the System Directory	11-3
11.2	Using the Adobe SVG Viewer on Web Clients.....	11-4
11.3	Setting Up Solution Explorer	11-4
11.3.1	Setting Up Solution Explorer HTML Documentation Path.....	11-4
11.3.2	Setting Up the Home Page for Solution Explorer	11-5

11.4	Configuring JD Edwards EnterpriseOne for Use with Vertex Quantum Tax Applications....	11-6
11.4.1	Adding Vertex Quantum Directory Information to the Microsoft Windows Server Path	11-7
11.4.2	Configuring the Release 9.1 Database Connections for Vertex Quantum Tax Applications	11-8
11.4.3	Mapping Objects to the Enterprise Server	11-10
11.4.4	Testing the Vertex Quantum Connection from Release 9.1.....	11-10
11.4.4.1	Adding an Entry for a Remote Database Directory for Vertex.....	11-11
11.5	Enabling CRM Functionality.....	11-11
11.5.1	Enabling CRM on the CRM Mobile Client.....	11-12
11.5.2	Enabling CRM on the Enterprise Server	11-12
11.6	Enabling Verity Enhanced Search Capability	11-12
11.7	Working with the Data Dictionary	11-13
11.7.1	Recreating Replicated Data Dictionary Files	11-13
11.8	Working with SETOWAUT	11-13
11.9	UBE Performance 'SQL Package Location	11-14

12 Working With Signon Security

12.1	Setting Up Signon Security	12-1
12.2	Enabling Server-Side Signon Security	12-5
12.3	Enabling Client-Side Signon Security	12-5
12.4	Setting Up JD Edwards EnterpriseOne Single Sign-on.....	12-5

13 Manual Table Conversions

13.1	Running Post Installation Tasks	13-1
13.2	Upgrading from XE \ ERP 8.0	13-2
13.3	Upgrading from 8.9 or Below.....	13-16
13.4	Upgrading from 8.10 or Below.....	13-17
13.5	Upgrading from 8.11 or Below.....	13-18
13.6	Upgrading from 8.11 SP1 or Below	13-23
13.7	Upgrading from 8.12 or Below.....	13-25
13.8	Upgrading from 9.0 or Below.....	13-28
13.9	Processing Options for R31P40039	13-30
13.10	Upgrading E1PAGE from Release 9.0 to Release 9.1	13-34
13.10.1	Upgrading E1PAGE Using R98E1UGC.....	13-34
13.10.1.1	Processing Options.....	13-34
13.10.1.2	Logic Flow	13-35
13.10.2	Upgrading F952400 Objects Using P98E1UGC	13-35
13.10.3	Working With Upgrade UGC Objects Using W98E1UGCA	13-35
13.10.4	Working With Detail Upgrade Using W98E1UGCB.....	13-36

14 Building and Testing Packages

14.1	Understanding Packages	14-1
14.2	Obtaining the JDK\JRE.....	14-2
14.3	Installing Application Fixes.....	14-2

14.4	Reviewing Pre-Package Build Issues	14-2
14.4.1	Verifying Available Space in DBMS	14-3
14.4.2	Verifying Specific UBEs are Mapped Locally	14-3
14.4.3	Verifying the Server-Side Settings.....	14-4
14.4.4	Configuring the Enterprise Server for Simultaneous Builds.....	14-4
14.4.5	Adding a Security Override for Running Package Build	14-4
14.4.6	Verifying UNICODE Settings When Upgrading From Xe	14-4
14.5	Reviewing Troubleshooting Tips	14-5
14.6	Building an Alternate Language Package	14-5
14.6.1	Package Build Considerations	14-5
14.6.2	Package Deployment Considerations	14-6
14.7	Assembling a Package that Contains Published Business Services.....	14-6
15	Upgrading the Production Environment	
15.1	Understanding the Upgrade of the Production Environment	15-1
15.2	General Checklist and Considerations.....	15-2
15.3	Running the Copy Environment Application (P989400)	15-3
15.4	Setting Up an Upgrade Plan for the Production Environment	15-13
15.5	Taking the Production Environment Offline	15-14
15.6	Running the Installation Plan for the Production Environment	15-14
15.7	Testing the Production Package	15-15
15.8	Bringing the Production Environment Online	15-15
16	Retrofitting Custom Modifications	
16.1	Overview	16-1
16.2	Retrofitting Custom Modifications.....	16-1
16.3	Using JD Edwards Compare and Merge Tools	16-2
16.3.1	Using the Application Configuration Analyzer (Release 9.1 Update 2).....	16-2
16.3.2	Using the Customization Object Analyzer (Release 9.1 Update 2)	16-3
16.3.3	JD Edwards Visual Compare for UDC Descriptions and Glossary Tool	16-3
16.3.4	JD Edwards EnterpriseOne FDA Compare	16-4
16.3.5	JD Edwards EnterpriseOne ER Compare.....	16-4
17	Troubleshooting	
17.1	Using the PORTTEST Checklist.....	17-1
17.2	Resolving Data Errors	17-3
17.3	Planner Update Special Instructions.....	17-3
17.4	Resolving Errors Due to Lack of *ALLOBJ and *JOBCTL Authority	17-3
18	Performing a Data-Only Upgrade	
18.1	Testing Long File Names	18-1
18.2	Pre-Upgrade Procedures	18-1
18.3	Installing the Deployment Server	18-2
18.4	Planning the Upgrade	18-2
18.5	Running Installation Workbench	18-3
18.6	Custom Modifications and Packages	18-3

18.7	Upgrading the Production Environment	18-4
19	Creating a Remote Installation Plan	
19.1	Understanding Remote Installation Plans	19-1
19.2	Starting Installation Planner	19-2
19.3	Entering Information in Installation Planner	19-3
19.4	Entering Plan Location Information.....	19-5
19.5	Entering Deployment Server Information	19-6
19.6	Entering Enterprise Server Information	19-8
19.7	Enter Data Source Information for Server Map.....	19-11
19.8	Entering HTML Web Server Information	19-12
19.9	Entering Data Server Information	19-16
19.10	Replicating Information to Remote Locations	19-16
19.11	Entering Shared Data Source Information	19-19
19.12	Setting Up Environments	19-20
19.13	Verifying Advanced Parameters	19-25
19.14	Setting Up Data Sources for Environment	19-26
19.15	Remote Location Packages	19-29
19.16	Finalizing the Installation Plan	19-32
19.17	Concluding the Planner Validation Report.....	19-32
20	Adding a Server to an Existing Configuration	
20.1	Assumptions about Adding a Server to an Existing Installation Plan.....	20-1
20.2	Starting Installation Planner	20-2
20.3	Entering a Plan Description	20-2
20.4	Entering a Plan Location	20-3
20.5	Selecting Additional Server Types	20-5
20.6	Entering Deployment Server Information	20-5
20.7	Specifying an Enterprise Server	20-7
20.7.1	Entering Enterprise Server Information	20-7
20.7.2	Entering Enterprise Server Data Source Information.....	20-9
20.7.2.1	Specifying Custom or Default Data Source Information	20-9
20.7.2.2	Verifying Custom Server Map Data Source Information	20-9
20.7.2.3	Adding another Enterprise Server	20-10
20.8	Entering HTML Web Server Information	20-11
20.9	Entering Data Server Information	20-13
20.10	Entering Shared Data Source Information	20-15
20.10.1	Specifying (Custom or Default) Shared Data Source Setup Information	20-15
20.10.2	Verifying the Data Source for Data Dictionary	20-15
20.10.3	Verifying the Object Librarian Data Source	20-16
20.10.4	Verifying the OWJRNL Data Source.....	20-17
20.10.5	Verifying the System Data Source	20-18
20.11	Setting Up Environments	20-19
20.11.1	Selecting an Environment.....	20-21
20.11.2	Specifying Environment Data Load Parameters	20-21
20.11.3	Verifying Advanced Parameters	20-22

20.11.4	Selecting Languages	20-24
20.12	Setting Up Environment Data Sources	20-25
20.12.1	Selecting an Environment Data Source Setup Option.....	20-25
20.12.2	Setting Up the Data Source for Business Data.....	20-25
20.12.3	Setting Up the Data Source for Central Objects	20-27
20.12.4	Setting Up the Data Source for Control Tables	20-28
20.12.5	Verifying the Data Source for Versions.....	20-29
20.13	Finalizing the Installation Plan	20-29
20.14	Concluding the Validation Planner Report	20-30
20.15	Configuring Additional Servers	20-30

21 Creating a Language-Only Installation Plan

21.1	Understanding Language-Only Installation Plans	21-1
21.2	Reviewing Requirements for a Language Installation	21-1
21.3	Installing Languages on the Deployment Server	21-2
21.4	Running Installation Planner	21-5
21.4.1	Accessing Installation Planner	21-5
21.4.2	Entering Information into Installation Planner	21-6
21.4.3	Selecting Custom or Default Parameters	21-6
21.4.4	Selecting an Environment	21-7
21.5	Selecting a Language	21-8
21.6	Running Installation Workbench	21-9
21.7	Verifying Enterprise Server Requirements	21-9
21.8	Verifying Workstation Requirements	21-10
21.9	Completing the Language Installation	21-10
21.10	Building and Deploying Alternate Language Packages	21-10

22 FTP on the IBM i

22.1	Setting up FTP on the IBM i	22-1
22.2	Starting the FTP Server	22-2
22.3	Copying assembly.dat to the IBM i IFS Directory (optional)	22-2

23 Understanding JD Edwards EnterpriseOne Directory Structures

23.1	Deployment Server Directory Structure	23-1
23.2	Language Directory Structure	23-12
23.3	IBM i Libraries	23-12
23.4	Workstation General Directory Structure	23-13

24 Major Technical Tables

25 Working with Reports

25.1	Installation Planner Validation Report (R9840B)	25-2
25.1.1	Setting Processing Options.....	25-2
25.1.2	How to Read the Report	25-2
25.2	Table and Index Creation (R98407)	25-3
25.3	Environment Database Creation Report (R98403)	25-3

25.3.1	Setting Processing Options.....	25-3
25.3.1.1	Version XJDE0001 for Installations and Upgrades.....	25-3
25.3.1.2	Version XJDE0004 for Updates.....	25-4
25.3.1.3	Version XJDE0024 for Running Pristine Data	25-5
25.3.1.4	How to Read the Report	25-6
25.3.1.5	Errors and How to Resolve Them.....	25-7
25.4	Data Dictionary Specification Merge Report and Data Dictionary Text Merge Report (R98722C and R98722T) 25-8	
25.4.1	Processing Options	25-9
25.4.2	Errors and How to Resolve Them	25-9
25.5	Object Librarian Modifications Report (R9840D).....	25-9
25.6	Async Launch (R98405A).....	25-9
25.7	Report on Table Conversions (R984052).....	25-10
25.7.1	How to Read the Report	25-10
25.8	Object Specification Merge Report (R98700).....	25-10
25.8.1	Processing Options	25-10
25.8.2	How to Read the Report	25-11
25.8.3	Errors and How to Resolve Them	25-13
25.8.3.1	Modifying the Merge Status of an Object	25-14
25.8.4	Compare Tables and Indexes Against Central Objects or TAM Specifications (R9698711) 25-14	
25.8.5	UDC Merge Report, Data Dictionary Merge Report, and Menu Merge Report ..	25-14
25.8.5.1	Setting Processing Options.....	25-15
25.8.5.1.1	UDC Merge and Exception Report and Data Dictionary Merge and Exception Report 25-15	
25.8.5.1.2	Menu Merge and Exception Report.....	25-15
25.8.5.2	How to Read the Report	25-15
25.8.5.3	Errors and How to Resolve Them.....	25-16
25.9	Index Recreation (R9698713)	25-16
25.10	Pathcode Copy (R9800942)	25-16

26 Understanding Data Source Charts

26.1	Business Data.....	26-1
26.2	Central Objects	26-2
26.3	Control Tables	26-3
26.4	Data Dictionary	26-4
26.5	Logic	26-4
26.6	Object Librarian.....	26-5
26.7	Language	26-6
26.8	Local	26-6
26.9	OWJRN.....	26-7
26.10	Server Map	26-8
26.11	System	26-8
26.12	Versions	26-9

27 Deinstalling the Software

27.1	Understanding the Deinstallation	27-1
------	--	------

27.2	Deinstalling the Software from the Workstations.....	27-2
27.3	Deinstalling the Local OEE from the Deployment Server	27-2
27.4	Manual Cleanup of a Deinstalled Oracle Database on the Deployment Server.....	27-2
27.5	Using the OUI Installer to Deinstall JD Edwards EnterpriseOne from the Deployment Server	27-4
27.6	Dropping DB2\400 Libraries	27-8
27.7	Deinstalling the Platform Pack	27-8

A Understanding IBM i Databases

Preface

Welcome to the JD Edwards EnterpriseOne Applications Release 9.1 Upgrade Guide.

Note: This Upgrade Guide has been updated for JD Edwards EnterpriseOne Tools Release 9.1 Update 2. For details on documentation updates, refer to the *JD Edwards EnterpriseOne Tools Net Change Guide*.

Audience

This guide is intended for system administrators and technical consultants who are responsible for installing, upgrading, and configuring JD Edwards EnterpriseOne.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Access to Oracle Support

Oracle customers have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Related Documents

You can access related documents from the JD Edwards EnterpriseOne Release Documentation Overview pages on My Oracle Support. Access the main documentation overview page by searching for the document ID of 876932.1.

To navigate to this page from the My Oracle Support home page, click the Knowledge tab, and then click the Tools and Training menu, JD Edwards EnterpriseOne, Welcome Center, Release Information Overview.

The most current versions of this guide and all other JD Edwards EnterpriseOne Tools and Installation/Upgrade documentation is available on the Oracle Technology Network:

<http://www.oracle.com/technetwork/documentation/jdedent-098169.html>

This guide contains references to server configuration settings that JD Edwards EnterpriseOne stores in configuration files (such as jde.ini, jas.ini, jdbj.ini,

jdelog.properties, and so on). Beginning with the JD Edwards EnterpriseOne Tools Release 8.97, it is highly recommended that you only access and manage these settings for the supported server types using the Server Manager program. For additional details, refer to the *Server Manager Guide*.

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

Understanding JD Edwards EnterpriseOne

This chapter discusses:

- [Section 1.1, "Understanding This Guide"](#)
- [Section 1.2, "Understanding the Upgrade Process"](#)
- [Section 1.3, "Considering Additional Factors"](#)
- [Section 1.4, "Working With the Customer Checklist"](#)
- [Section 1.5, "Environments Overview"](#)
- [Section 1.6, "Language Process Overview"](#)

1.1 Understanding This Guide

This guide is designed to direct you through a basic JD Edwards EnterpriseOne upgrade. It is not a substitute for the database administration manuals provided by your Relational Database Management System (RDBMS) vendor, the network administration manuals provided by your network vendor, or the installation and configuration manuals for third-party products used with JD Edwards EnterpriseOne.

Note: You should always check My Oracle Support for revisions to this guide subsequent to the initial release, which coincides with the General Availability of Release 9.1. Generally, this document is republished in its entirety only for the next major applications release of JD Edwards EnterpriseOne.

The book contains only the procedures required for a typical base upgrade with predefined typical environments and databases. However, the upgrade is flexible enough to enable you to:

- Select specific components to upgrade from multiple predefined environments and databases.
- Install the Platform Pack to either of these machine combinations:
 - Enterprise Server and Database Server on one machine and one drive - the Installer runs once.
 - Enterprise Server and Database Server on separate machines (or different drives in the same machine) - the Installer runs twice, once for each server.

This guide is designed for management information system (MIS) managers and installers. It outlines the procedures for upgrading to Release 9.1.

This guide also describes the procedures to migrate from existing JD Edwards World to Release 9.1.

To successfully upgrade to Release 9.1, you must understand:

- Hardware and software requirements
- Database setup and management
- Enterprise platforms and operating systems
- JD Edwards EnterpriseOne Tools Foundation Guide
- JD Edwards EnterpriseOne Configurable Network Computing Implementation Guide
- JD Edwards EnterpriseOne Tools System Administration Guide
- JD Edwards EnterpriseOne Tools Package Management Guide
- JD Edwards EnterpriseOne Tools Server and Workstation Administration Guide
- JD Edwards EnterpriseOne Tools Security Administration Guide

At a minimum, review these guides before beginning:

In addition, it is recommended to complete the database product courses that your database vendors provide.

1.2 Understanding the Upgrade Process

This documentation explains the process used to upgrade Release 9.1 software using the upgrade process, which consists of these steps:

- Install the Deployment Server (see [Concurrent Installation](#) below for concurrent operations)
- Install the Platform Pack (see [Concurrent Installation](#) below for concurrent operations)
- Set up the installation plan by running Installation Planner
- Run the Installation Workbench
- Install the HTML Web Server

Note: A JD Edwards EnterpriseOne HTML Web Server is mandatory to run web-enabled JD Edwards EnterpriseOne applications, which includes all end-user applications and selected tools applications. This guide only describes the definition of the HTML Web Server in regards to the Installation Planner and the Installation Workbench. The installation of the HTML Web Server itself is not covered by this guide. Separate guides describe the separate installation process for the HTML Web Server on the supported platforms using Server Manager. Topics relating to the HTML Web Server other than installation using Server Manager are covered in platform-specific reference guides. Such topics include the installation and configuration of the underlying application servers.

Refer to these Tools Release guides which are available on the JD Edwards EnterpriseOne Documentation library. This library is located on the Oracle Technology Network, which can be accessed at this link:

<http://www.oracle.com/technetwork/documentation/jdedent-098169.html>

- *Server Manager Guide*
 - *HTML Web Server Reference Guide for WebSphere on IBM i*
-

- Install the workstations for developers and system administrators

Concurrent Installation

You can concurrently install the Deployment Server, the Platform Pack, and the HTML Web Server assuming the installation programs are run on different machines (not recommended for VM environments). This can decrease the overall time it takes to complete the upgrade.

Recommended Configurations

You can set up your Release 9.1 configuration in many ways. You should follow the typical setup and naming conventions whenever possible, unless there is a strong business case that supports the need to change.

See Also

Typical Customer Configuration in the *JD Edwards EnterpriseOne Configurable Network Computing Implementation Guide* for more information about the typical customer configuration provided with Release 9.1.

Note: JD Edwards EnterpriseOne Release 9.1 does not support coexistence.

If you have ever had JD Edwards World installed, you will need to perform the steps in *JD Edwards EnterpriseOne Ending Coexistence Guide* before starting your Release 9.1 upgrade.

This section discusses:

- [Section 1.2.1, "What an Upgrade Preserves and Replaces"](#)
- [Section 1.2.2, "Understanding the Deployment Server Installation"](#)
- [Section 1.2.3, "Understanding the Platform Pack Installation"](#)

- [Section 1.2.4, "Understanding the Installation Planner"](#)
- [Section 1.2.5, "Understanding Installation Workbench"](#)
- [Section 1.2.6, "Understanding the Workstation Installation"](#)

1.2.1 What an Upgrade Preserves and Replaces

If custom modifications are required, follow the rules listed below to ensure a smooth and predictable upgrade. These rules describe which modifications the upgrade process preserves and which modifications the upgrade replaces.

Preserve means during an upgrade the custom modifications are not lost during the automatic and visual merges of the new applications shipped with the upgrade. If there is a direct conflict between your specifications and those in the upgrade, the upgrade process uses yours. When there is no direct conflict between the two, the upgrade process merges the two specifications.

Replace means the upgrade does not merge your custom modifications into the new release. Custom modifications must be redone after the upgrade is completed.

Customization Considerations

If possible, transfer all modifications to one pathcode. Do this only after testing and approving all modifications or if the modifications are only in development. Having only one environment to upgrade significantly shortens the process.

Refer to the *JD Edwards EnterpriseOne Tools Package Management Guide* for more information about custom modifications and how they are affected by the upgrade process.

1.2.1.1 Interactive Application Rules

Do not delete controls, grid columns, or hyperitems on existing software applications; instead, hide or disable them. JD Edwards EnterpriseOne might use these for calculations or as variables. Deleting them might disable major functionality. Modified JD Edwards EnterpriseOne applications are ignored by batch merge. All changes must be retrofit via Visual FDA\ER Merge.

An upgrade preserves custom changes to:

- New applications (batch merge).
- New objects on existing forms using Visual FDA Merge, including:
 - New hyperitems.
 - New controls.
 - New grid columns.
 - Any style changes, such as fonts and colors.
- Any code-generator overrides.
- Data dictionary overrides.
- Location and size changes for controls.
- Sequence changes for tabs or columns.

Custom forms on existing JD Edwards EnterpriseOne applications are not preserved. A set of visual merge tools have been provided to assist in retrofitting custom modifications.

Refer to the *JD Edwards EnterpriseOne Tools Development Tools: Form Design Aid Guide* for more information on Visual Merge Tools and FDA Compare.

1.2.1.2 Report Rules

These rules apply to report specifications that were created using Report Design Aid (all are batch merges).

An upgrade preserves these changes:

- New reports
- New elements to existing JD Edwards EnterpriseOne reports, including:
 - Constants.
 - Alpha variables.
 - Numeric variables.
 - Data variables.
 - Runtime variables.
 - Database variables.
 - Dictionary variables.
 - Any style changes, such as fonts and colors.
- Location and size changes for objects.
- Data dictionary overrides.

Custom sections in existing JD Edwards EnterpriseOne reports are not preserved.

1.2.1.3 Application Text Changes

An upgrade does **not** automatically preserve overrides done in Form Design Aid or Interactive Vocabulary Overrides. They must be retrofit using FDA Visual Merge.

1.2.1.4 UBE Text Changes

An upgrade automatically preserves overrides done in Report Design Aid or Batch Vocabulary Overrides.

1.2.1.5 Table Specification Rules

An upgrade merges your custom table specifications from one release level to the next.

An upgrade preserves these changes:

- New tables.
- New indexes on JD Edwards EnterpriseOne tables.

An upgrade replaces columns added or removed from existing JD Edwards EnterpriseOne tables, including changing field length, field type, and decimal position.

Instead of adding a new column to an existing table, use a tag file with product codes 55 through 59. For custom tag files, be aware of data item changes in the data dictionary. From one release to the next, JD Edwards EnterpriseOne might change certain data item attributes, such as data item size, which can affect data integrity and how data is stored in the database.

For this reason, use the Table Conversion tool to convert the custom tag file data to the new release level. For base files, the upgrade process takes care of the data dictionary changes by upgrading the previous database. An upgrade preserves custom indices over the custom tag files.

1.2.1.6 Control Table Rules

An upgrade merges your control table data, not JD Edwards EnterpriseOne tables, from one release level to the next using the Change Table process as the basis to do the data merge.

An upgrade preserves these changes:

- **Data dictionary custom changes.**

These include such as changes to row, column, and glossary text. The upgrade process uses your data dictionary as the base.

- **User-defined codes.**

The upgrade process merges any new hard-coded values. (These values are system 90 and above, and H90 and above.)

- **Solution Explorer Tasks.**

Consider these affects on the customization of Solution Explorer Tasks:

1. During an upgrade, your custom changes on any JD Edwards EnterpriseOne base task overrides any new changes from JD Edwards EnterpriseOne.
2. If any new custom task (TASKNM) has been added that conflicts with a new JD Edwards EnterpriseOne base task, the custom task will be replaced.

See Also

Chapter 9, "Performing Merges" for more information about merges.

1.2.1.7 Business View Rules

Do not remove columns from existing business views. Changing business views that applications use can cause unpredictable results when running the application. Hide columns at the application design level using either Form Design Aid or Report Design. Performance is not gained by deleting a few columns from a business view.

An upgrade preserves these changes:

- New custom business views.
- New columns or joins to the existing business views.

An upgrade replaces columns removed from business views.

1.2.1.8 Rules for Event Rules

An upgrade preserves these changes:

- For APPL, all retrofitting is done using the Visual FDA\ER Merge tools.
- Custom event rules on a new custom control field.
- For reports, tables, and business function events that do not have any event rules attached to the same event.
- An upgrade replaces modifications to applications, reports, tables, and business functions events that have existing event rules.

Use the Visual ER tools to restore custom event rules.

1.2.1.9 Data Structure Rules

An upgrade preserves all of these custom data structures:

- Forms
- Processing options
- Reports
- Business functions
- Generic text

An upgrade replaces all custom modifications to JD Edwards EnterpriseOne data structures. No changes to JD Edwards EnterpriseOne structures are preserved.

1.2.1.10 Business Function Rules

For any newly created custom business functions, create a new parent DLL directory to store them.

An upgrade preserves new custom business function objects, including custom BSSV objects.

An upgrade replaces modifications made to existing business functions and any business functions added to existing business function objects. Refer to the JD Edwards EnterpriseOne Tools Development Tools: APIs and Business Functions Guide.

1.2.1.11 Versions

For XJDE versions, nothing carries forward. The user JDE owns specifications and processing option data.

For ZJDE versions, specifications do not carry forward while processing option data changes do carry forward.

All other custom versions should have processing option data and specifications carried forward.

1.2.2 Understanding the Deployment Server Installation

The Deployment Server is the focus of the Release 9.1 upgrade process. The upgrade program for the Deployment Server copies the Release 9.1 software from the installation images to the Deployment Server. From the Deployment Server, the Release 9.1 software is distributed to one or more Enterprise Servers and workstations.

The Deployment Server installation program updates the Microsoft Windows registry with information about the Release 9.1 installation and languages, if applicable.

1.2.3 Understanding the Platform Pack Installation

Rather than transferring all the software from the Deployment Server, the Platform Pack installs the code and database directly to the Enterprise Server. This more direct installation method increases performance during this part of the process. It is especially beneficial in situations in which the Enterprise Server is connected to the Deployment Server using a wide area network (WAN). Since the Deployment Server and Platform Pack have separate Installers, they can be running concurrently which decreases the overall installation time (assuming the Installers are run on different machines).

1.2.4 Understanding the Installation Planner

Installation Planner is an application that runs as a stand-alone program on the Deployment Server. Installation Planner configures the environments for all machines within the enterprise. It also is a system administration tool that stores all information about the installation plan in a set of preloaded tables in the Planner data source. Installation Planner guides you through setting up the installation plan step-by-step based on options you choose.

Installation Planner manages these processes:

- Language setup
- Location setup
- Deployment Server setup
- Enterprise Server setup
- HTML Web Server
- Additional server setup

This includes setup to servers such as a Database Server.

- Data source setup

This includes setup for both Enterprise Server-specific and shared environment data sources.

Some data sources remain the same between releases:

- Business data
- Control tables

Other data sources are release specific:

- System and data dictionary
- Server map

The server map is machine-specific and release-specific if separate environments are maintained.

- Environment setup

This includes all environments for a typical customer configuration, and creation of a new environment, such as PD910. This process ensures that the Object Configuration Manager (OCM) mappings are correct and the new environments point to the correct path codes. This could include creating custom environments and path codes.

- Control table merges

The control table planner program offers these merges for customers upgrading to Release 9.1 from a previous release:

- Data Dictionary Merge (R989200P).
- User Defined Code Merge (R9600042).
- Solution Explorer Merge (R9690002).
- Favorites Merge (R96911002).
- Report Director Templates Merge (R96914002).
- Tips of the Day Merge (R96915002).

- Table conversions

You can convert all tables for which JD Edwards EnterpriseOne has made database changes, including technical, specification, and vertical tables.

- Specification table merges

You can use the upgrade process to merge custom modifications with JD Edwards EnterpriseOne applications. A single batch application merges changes to these objects:

- Tables
- Business views
- Data structures (only new are added)
- Interactive applications (no changes are merge, just new objects are added)
- Batch applications
- Business functions (only new are added)

See *Modifications Rules* in the *JD Edwards EnterpriseOne Tools Package Management Guide* for information about changes that merge or overlay former data.

- Package Workbench

You use Installation Planner to perform on environment-level operations that deal primarily with processing activity on the Enterprise Server platforms. You use it to set up user profiles and workstation installations after installing the Enterprise Server.

1.2.5 Understanding Installation Workbench

Installation Workbench runs the plan created during Installation Planner. It functions as a central point for all the processes required to install environments. Some of the processes that install environments might require procedures to be performed manually. However, Installation Workbench assures that procedures are performed in the proper order, and insulates you as much as possible from platform-specific environment setup.

1.2.6 Understanding the Workstation Installation

The JD Edwards EnterpriseOne Development Client (also known as a Web Development Client, "Fat" Client, Administrative Client, Windows client, or Workstation) contains components that run as standard Microsoft Windows applications (for example, Active Console, Forms Design Aid (FDA), and Report Design Aid (RDA)) and components that run in a web browser.

Note: This document uses the following terminology when discussing JD Edwards EnterpriseOne clients:

- Web Client

Components that run in a web browser.

- Development Client

Composed of standard Windows components and Web Client.

The Web Client part of the Development Client runs inside an Application Server. The supported Application Servers are:

- Oracle Application Server (OAS)
- IBM WebSphere Application Server (WAS) Express or WebSphere Application Server for Developers.

The Oracle Application Server is included as part of the JD Edwards EnterpriseOne system code and is automatically configured to work with the Web Client when you install the Web Client for OAS. This version of the Web Client is known by any of the following names:

- Oracle Containers for Java HTML for Applications,
- OC4J for H4A, or simply
- OH4A.

Although OAS is included with JD Edwards EnterpriseOne system code, you can choose to use WAS Express or WAS for Developers as the Application Server for the EnterpriseOne Web Client. Both products are similar; either one may be manually installed before installing the Web Client for WAS. Whereas WAS Express requires a licensing fee to IBM, WAS for Developers is free. The version of the Web Client that is installed on either WAS product is referred to by either of these names:

- HTML for Applications or
- H4Ax (where the "x" denotes the version of WAS Express or WAS for Developers; currently, the supported version is 7).

This guide describes how to install Web Clients for both Application Servers: OH4A and H4A7. In addition, it covers the installation of WAS 7 Express or WAS 7 for Developers.

The first time setup of the JD Edwards EnterpriseOne Development Client installer and installation package on an EnterpriseOne Deployment Server is described in a separate guide entitled: *JD Edwards EnterpriseOne Deployment Server Reference Guide*. This setup on the Deployment Server must be done before a user can install a JD Edwards EnterpriseOne Development Client on a workstation. The installation package specifies the components to install and may or may not include the Web Client.

1.3 Considering Additional Factors

This section discusses:

- [Section 1.3.1, "Accessing Minimum Technical Requirements \(Certifications\)"](#)
- [Section 1.3.2, "Understanding Machine Names"](#)
- [Section 1.3.3, "Accessing IBM i Performance Tuning and White Papers"](#)
- [Section 1.3.4, "Using JD Edwards EnterpriseOne Support"](#)
- [Section 1.3.5, "Understanding Documentation Conventions"](#)

1.3.1 Accessing Minimum Technical Requirements (Certifications)

Customers must conform to the supported platforms for the release as detailed in the JD Edwards EnterpriseOne Minimum Technical Requirements. In addition, JD Edwards EnterpriseOne may integrate, interface, or work in conjunction with other Oracle products. Refer to the following link for cross-reference material in the Program

Documentation for Program prerequisites and version cross-reference documents to assure compatibility of various Oracle products.

<http://www.oracle.com/corporate/contracts/index.html>

Access the current Minimum Technical Requirements (MTR) from My Oracle Support (<https://support.oracle.com>) by searching for this document:

745831.1 (JD Edwards EnterpriseOne Minimum Technical Requirements Reference)

<https://support.oracle.com/epmos/faces/DocumentDisplay?id=745831.1>

1.3.2 Understanding Machine Names

Due to underlying requirements in the machine name tables, you must ensure that all machines names in the JD Edwards EnterpriseOne environment conform to specific rules. Whenever you manually enter a machine name in JD Edwards EnterpriseOne, or whenever a machine name is programmatically determined, it is important to note that the machine name:

- Is case-sensitive
- Cannot exceed 15 characters
- Must be alphanumeric only and cannot contain any special characters, such as underscores or hyphens

Any machine whose name does not conform to these rules cannot be used in the JD Edwards EnterpriseOne environment.

1.3.3 Accessing IBM i Performance Tuning and White Papers

In order to optimize performance for JD Edwards EnterpriseOne customers running on IBM i, users should be aware of the IBM tuning guide (White Paper WP101777):

IBM Power Systems with IBM i Performance and Tuning Tips for Oracle's JD Edwards EnterpriseOne 9.0

<http://www-03.ibm.com/support/techdocs/atsmastr.nsf/WebIndex/WP101777>

On this IBM Techdocs (Technical Sales Library) web site, you can locate the above referenced White Paper and other documents by searching for "EnterpriseOne" and the EnterpriseOne release number (for example, 9.0 or 9.1):

<http://www-03.ibm.com/support/techdocs/atsmastr.nsf/Web/TechDocs>

1.3.4 Using JD Edwards EnterpriseOne Support

Use **My Oracle Support** to access customer support functions and information including issues, Software Action Requests (SARs), and to access the Oracle JD Edwards Update Center. Through the Update Center, you can research and download Service Packs, Electronic Software Updates (ESUs), view SARs and objects, and documentation.

If you need further assistance with Release 9.1 upgrade, contact Oracle customer support by phone, fax, or e-mail. For questions about operating systems, databases, and other software products, contact the appropriate vendor.

1.3.5 Understanding Documentation Conventions

This section explains these typographic and design conventions used throughout this documentation.

- [Section 1.3.5.1, "Documentation Updates"](#)
- [Section 1.3.5.2, "Tips"](#)
- [Section 1.3.5.3, "Fonts and Type Styles"](#)

1.3.5.1 Documentation Updates

The Oracle Technology Network for JD Edwards Documentation always contains the most recent documentation, which may include document updates and other information about installing and upgrade JD Edwards EnterpriseOne. You can use this link to access the Oracle Technology Network for JD Edwards Documentation:

<http://www.oracle.com/technetwork/documentation/jdedent-098169.html>

1.3.5.2 Tips

This documentation contains tips containing information that can make the JD Edwards EnterpriseOne setup process easier. Tips information is helpful but optional.

1.3.5.3 Fonts and Type Styles

Special fonts and type styles are used in this guide. Nearly all of the commands in this guide are case sensitive. Enter them exactly as written. In addition, all of the commands described illustrate the recommended directory structure. If your machine's directory structure is different, modify the commands to match your directory structure.

Italic type style designates variables used in the guide. For example, for the variable *deployment_server* in a command, substitute the actual name of your *Deployment Server*. Also, the names of other JD Edwards EnterpriseOne guides are in italic type style. For example, *JD Edwards EnterpriseOne Tools Package Management Guide*.

Courier font indicates explicit file names, commands, or other information that must be typed into the system. For example, a common file name used by JD Edwards EnterpriseOne is an initialization file called the `jde.ini`.

1.4 Working With the Customer Checklist

The Release 9.1 support structure consists of components such as databases, operating systems, and hardware. To upgrade Release 9.1 successfully, set up the support structure before starting the installation process.

The tasks in this section are designed to prepare the customer's system for the installation process. Some of the tasks, such as checking that the appropriate hardware and software are available, can take some time to complete. Other tasks are quick and easy.

This checklist helps to organize the required upgrade preparation:

- Review [Section 1.5, "Environments Overview"](#).
- If the installation involves a secondary language, review [Section 1.6, "Language Process Overview"](#) in this chapter.
- Assess the network.
- Back up the Deployment Server.
- Back up the existing language package directory (for language clients only).
- Back up the Enterprise Server.

- Back up the databases.
- Prepare the prototype environment.
- Prepare the development environment.
- Check media object queues.
- Check modification and merge flags.
- Prepare environments for upgrade.
- Refresh the business data (optional).
- Refresh the control tables.
- Verify custom changes in master control tables.
- Verify third-party hardware and software.
- Verify that the Deployment Server hardware and software meet minimum technical requirements.
- Verify that the Enterprise Server hardware and software meet minimum technical requirements.
- Verify that the workstation hardware and software meet minimum technical requirements.
- Verify that HTML Web Server hardware and software meet minimum technical requirements.
- Verify that the Deployment Server disk space meets minimum technical requirements.
- Verify that the Enterprise Server disk space meets minimum technical requirements.

1.5 Environments Overview

The HTML Web Server (J) environments have the same mappings as the regular environments with the exception of logic, all of which is mapped to run on the Enterprise Server.

Each environment shipped with Release 9.1 has a specific use. The following sections explain each environment in more detail.

- [Section 1.5.1, "Understanding Environments"](#)
- [Section 1.5.2, "Planner Environment \(JDEPLAN\)"](#)
- [Section 1.5.3, "Pristine Environment \(PS910\)"](#)
- [Section 1.5.4, "Deployment Environment \(DEP910\)"](#)
- [Section 1.5.5, "Development Environment \(DV910\)"](#)
- [Section 1.5.6, "Prototype Environment \(PY910\)"](#)
- [Section 1.5.7, "Production Environment \(PD910\)"](#)
- [Section 1.5.8, "Additional Considerations"](#)

1.5.1 Understanding Environments

The Release 9.1 software includes several environments that represent the typical customer configuration as defined in the *JD Edwards EnterpriseOne Configurable*

Network Computing Implementation Guide. These environments are preset to make the installation process as easy as possible. This section contains additional information about these environments and their role in the installation and upgrade process.

Follow the setup recommendations and naming standards described in this guide to minimize confusion when communicating with those outside of your implementation team. In addition, future upgrades are simpler if you use JD Edwards EnterpriseOne naming conventions. If you customize your configurations during the process, you should change only the descriptions provided with the typical setup.

JD Edwards EnterpriseOne provides the following preset environments:

- Deployment (DEP910)
- Planner (JDEPLAN)
- Prototype (PY910)
- Pristine (PS910)
- Development (DV910)
- Production (PD910)
- HTML Web Server (J)

1.5.2 Planner Environment (JDEPLAN)

The software installation and upgrade process includes a planning stage called the planner environment. Using this approach you can define the main components of your software configuration without affecting the production environment.

Every environment must have an associated pathcode and a set of OCM mappings. The planner environment uses a planner pathcode, which is shipped with the software, and a set of OCM mappings, which point to a planner database. All pathcodes share a complete set of runtime central objects on the Deployment Server.

1.5.2.1 Planner Pathcode

Release 9.1 provides a full set of runtime objects, which are used during the installation process. The software stores these objects on the Deployment Server in the planner directory. The planner pathcode contains the only complete set of runtime central objects on the Deployment Server, which are shared by all pathcodes.

The planner pathcode includes preloaded packages used during the update specification merge process. A package indicates the necessary objects for a workstation, a point-in-time snapshot of the central objects on the Deployment Server, and where the installation program finds them.

1.5.2.2 Planner Database

All information created and updated during the planning stage is saved in these Oracle tablespaces:

- JDEPlan910
- JDECTL910
- JDEDD910
- JDSYS910
- JDEVL910
- JDEOL910

- JDEData910

When using the planner environment to change your configuration:

- Planner database tables are updated with the change.
- A plan is defined and run to move the change to the production environment.

When using the deployment or production environment to change your configuration after finishing the process:

- Production environment tables in the System pathcode are updated in real-time.
- Planner database tables are not updated.

For the deployment and production environments, OCM and data source information comes from the planner database.

You should use the production environment system (technical) tables to make changes to environments, pathcodes, packages, and OCM.

1.5.3 Pristine Environment (PS910)

Use the pristine environment (PS910) to test pristine (un-customized) objects with JD Edwards EnterpriseOne demonstration data or for training classes. The pristine environment is also used to run Table Conversion processes during an upgrade. This environment is required to compare modified objects to pristine objects. When encountering a software problem that JD Edwards EnterpriseOne Global Support cannot duplicate, they will ask you to sign on to the pristine environment to duplicate the problem. Routinely, either monthly or quarterly, refresh the data for this environment from the JDEPLAN environment on the Deployment Server.

You should apply all software updates, ESUs, and Service Packs to the Pristine environment.

1.5.4 Deployment Environment (DEP910)

Use the deployment environment to run packages builds on the Deployment Server. The deployment environment uses the planner pathcode and has OCM mappings to the production environment system tables and local data. Only one deployment environment is required because all environments created by the installation process share common data sources.

The deployment environment uses system information, such as environments, packages, and user profiles. The OCM mappings and data source information are supplied by the planner database.

1.5.5 Development Environment (DV910)

The development environment is for development objects (DV910 pathcode). Log on to this environment to modify and test objects before transferring them to the prototype environment (PY910) pathcode. After transferring the objects into PY910, build and install a full or partial prototype package (for example, PY910FA or PY910PA), and then log on to the prototype environment for additional testing. The Development environment is delivered with JD Edwards EnterpriseOne Demonstration data.

1.5.6 Prototype Environment (PY910)

The prototype environment is the staging environment for production. Constants tables and master tables, such as company constants, fiscal date patterns, and item master are populated with production data during the prototype process. Copy the tables to the production environment before going live.

1.5.7 Production Environment (PD910)

Production users have a tested and released package on their system. Batch applications can run on the Enterprise Server.

1.5.8 Additional Considerations

Additional considerations include:

- [Section 1.5.8.1, "Cluster Software Options"](#)
- [Section 1.5.8.2, "Web-Based Options"](#)

1.5.8.1 Cluster Software Options

When using cluster software, additional issues exist that must be taken into consideration before installing Release 9.1.

1.5.8.2 Web-Based Options

The HTML Web Server installation enables the use of Web-enabled functions in Release 9.1.

See Also

HTML Web Server, Java Server, or JAS in the JD Edwards EnterpriseOne Tools HTML Web Server Installation Guide for more information about Web-based options.

1.5.9 Release History

This version of JD Edwards EnterpriseOne is Release 9.1. The following list shows the currently supported previous releases of JD Edwards EnterpriseOne:

- Release 9.0
- Release 8.12
- ERP8, 8.11, and 8.11 SP1 (8.11 and 8.11 SP1 are on extended support only)
- OneWorld Xe

1.6 Language Process Overview

Note: Languages are installed using the Installation Planner. The Language installation image is required to implement this functionality. If you install additional languages, you will perform the procedures after you have executed the initial installation described in this guide. For additional details, refer to the chapter [Chapter 21, "Creating a Language-Only Installation Plan"](#) in this guide.

This section is provided in this guide for references purposes. The language installation process automatically copies the text from a language database to the production Release 9.1 database and merges the alternate language text with the original English base. These automated processes are described throughout this guide. When installing language for the first time, a language-only plan may be chosen after completing the initial plan.

See Also

- Section 5.4, "Running the Installation Planner for an Upgrade"
- [Chapter 21, "Creating a Language-Only Installation Plan"](#) for the tasks that must be completed when choosing to install an alternate language after completing the base installation.

1.6.1 Language Architecture

The software language architecture incorporates multinational language functionality for international customers. The software specifies the language preference for forms and reports. For example, users who share the same environment may want to view the same text in multiple languages, such as French, Spanish, and English. All language text is stored in a central location and deployed to the individual workstation.

JD Edwards EnterpriseOne provides all software with a base language of English. The package build process enables the building of packages for multiple languages. Multiple languages can be installed using the processes outlined in this guide. Language text is accessed by the language preference code settings in the user profile associated with the alternate language installed.

1.6.1.1 Base Language

Release 9.1 language support works in conjunction with the English base language. The base release contains English and must be installed before creating custom modifications to include changes or additions to the translated text. All control files must also have an English record prior to adding an alternate language text record.

1.6.1.2 Alternate Language Components

An alternative language component is not included in this release; you must build the language package.

An alternate language includes major components whereby language text is stored in the Central Objects, System, Control Table, and Data Dictionary data sources. The data is loaded to the Deployment Server during the installation and copied to the Central Objects and the other data sources through the language installation process.

For Release 9.1, JD Edwards EnterpriseOne is shipped with 21 languages. Single-byte languages run on single-byte or double-byte operating systems, but double-byte languages must run on double-byte operating systems.

Instructions in this guide explain how to set up these features.

See Also

Package Build in the *JD Edwards EnterpriseOne Tools Package Management Guide* for more details on how to build a language package.

1.6.1.3 Language Preference Codes

The language preference codes are the standard language codes used throughout the software. The Language Preference Code field, located in the Release 9.1 user profile, determines which language is displayed on forms or reports. All users are assigned a language preference code within the user profile.

A blank language preference code specifies the base language of English. Alternate language records always have a value in the language preference code.

The alternate language text tables contain language preference codes. The tables contain several records for each item, such as a user defined code value as well as possible multiple records for a code value, with each code representing a different language.

If the language preference code does not have a corresponding translated language record, the base English record is the default record.

Certain database tables, such as the Business Unit Master, AAIs, Account Master, and Item Master, also contain the language preference code in an additional description table. This information is not translated in the JD Edwards EnterpriseOne demonstration data.

Release 9.1 applications support the use of languages. Refer to the individual applications to set up and use multiple languages.

1.6.2 Database Character Set and Code Page Considerations

Data within a database is defined by a set of parameters. Each character within the database is identified by a specific language preference code value. A collection of characters within a defined database is called a character set or code page. A character set or code page setting is a scheme for encoding character data. Every character is defined by a unique hexadecimal value. These values can change between databases and languages. Every language is represented by at least one character set. Some character sets may contain multiple languages.

For example, the Western European character set contains all characters common to the Western European languages (Aa - Zz) and all special characters unique to specific languages, such as ' , ' , ' , and ' . Asian character sets are specific to one language.

The software uses code page conversions to control the consistent or desired display of data. A code page conversion adjusts the hexadecimal values of different characters so that the appearance of text on the desktop is the same with different code pages.

When installing or upgrading the database, set up the code page for the language before loading your language specifics for Release 9.1.

See Also

[Section 1.6.3.1, "Single-Byte and Double-Byte Considerations"](#) to determine the LocalCodeSet and code page settings for your database machine environment.

1.6.2.1 Unicode

Unicode specifies that the data stored in the data source is in Unicode format. For installs, all data sources default to Unicode.

For DB2\400, the code page is stored at the table level. Therefore, the Unicode attribute must be consistent within a data source (that is, within a library).

Note that the code page still must be set to the correct value even though the data sources may all be Unicode. The Unicode flag only indicates what column type is used

to store character data in a Unicode database. For example, for DB2\400, it indicates GRAPHIC\VARGRAPHIC with CCSID 13488 is used. Refer to the following section for the code page settings.

See Also

JD Edwards EnterpriseOne Unicode Data Conversion Guide for information on how to convert data to Unicode.

JD Edwards EnterpriseOne Tools Development Standards for Business Function Programming Guide for information on how to convert Business Functions to support Unicode text strings.

JD Edwards EnterpriseOne Flat File Conversion Guide for information on how to convert Flat Files to Unicode.

1.6.2.2 Code Page Settings

You should use the code page settings in this guide. The correct code page should be set when the database is created.

1.6.2.2.1 DB2\400 Code Page Settings The DB2\400 character set (CCSID) for the database needs to be set correctly depending on the language used as listed in this table:

Tier	Language	DB2\400 for IBM i (CCSID)
1	English	37
1	French	37
1	German	37
1	Italian	37
1	Spanish	37
1	Portuguese	37
1	Japanese	939
2	Danish	37
2	Dutch	37
2	Finnish	37
2	Norwegian	37
2	Swedish	37
2	Korean	933
2	Traditional Chinese	937
2	Simplified Chinese	935
3	Arabic	N\A
3	Czech	870
3	Hungarian	870
3	Polish	870
3	Greek	875
3	Russian	1025

Tier	Language	DB2/400 for IBM i (CCSID)
3	Turkish	1026

1.6.2.2.2 Workstations and Deployment Server Code page settings for individual languages are specified in Microsoft Windows System locale. Verify that the Deployment Server code page is set correctly prior to upgrade.

1.6.3 National Language Support

National Language Support (NLS) is a set of common standards that enable data to be entered, displayed, stored, retrieved, and printed in multiple languages, in different databases, and on different platforms.

NLS is information that requires the set up of code pages and the `JDE.INI jde.ini` for the Enterprise Server and `JDE.INI` for the web development workstations. By using NLS standards, JD Edwards EnterpriseOne maintains consistent data within all databases and hardware platforms. The same database can store alternate language text, relying on NLS standards to manage the text storage and retrieval. JD Edwards EnterpriseOne uses NLS, on all supported platforms, to interact with any computer system (hardware and software) within your own environment.

For the workstation to reflect the language installed on the Deployment Server, perform the tasks for both the Enterprise Server and workstations to verify and modify the `JDE.INI jde.ini` settings. These procedures are described throughout this guide.

1.6.3.1 Single-Byte and Double-Byte Considerations

Many single-byte languages support either national code pages or multinational code pages. The double-byte languages support specific individual national code pages by language.

Single-byte character sets use a collection of phonetic characters that require one byte to create a single character. Conversely, the double-byte character sets use ideographic characters and require two bytes to create a single character.

Single-byte languages can generally be run on single-byte or double-byte systems. Double-byte languages, such as Japanese, Chinese, and Korean, must run on machines configured to support a double-byte system. For example, a double-byte SQL Server or Oracle database is required for Chinese and Japanese languages.

The software can perform a Query By Example (QBE) on any character. However, when using a double-byte language, this process may not necessarily use an understandable collating sequence, although it can still use QBE for any double-byte column.

The following table shows the languages that the software supports and the `LocalCodeSet` values set in the `JDE.INIjde.ini` for each platform:

Tier	Language	Language Code	LocalCodeSet Value
1	English	E	US_EBCDIC
1	French	F	US_EBCDIC
1	German	G	US_EBCDIC

Tier	Language	Language Code	LocalCodeSet Value
1	Italian	I	US_EBCDIC
1	Spanish	S	US_EBCDIC
1	Portuguese	P	US_EBCDIC
1	Japanese	J	JA_EBCDIC
2	Danish	DN	US_EBCDIC
2	Dutch	DU	US_EBCDIC
2	Finnish	FN	US_EBCDIC
2	Norwegian	NO	US_EBCDIC
2	Swedish	W	US_EBCDIC
2	Korean	KO	KO_EBCDIC
2	Traditional Chinese	CT	TC_EBCDIC
2	Simplified Chinese	CS	SC_EBCDIC
3	Arabic	AR	n\ a
3	Czech	C	EE_EBCDIC
3			
3	Hungarian	HU	EE_EBCDIC
3	Polish	PO	EE_EBCDIC
3	Greek	GR	GR_EBCDIC
3	Russian	RU	RS_EBCDIC
3	Turkish	TR	TK_EBCDIC

1.6.3.2 Font Considerations

JD Edwards EnterpriseOne includes standard language fonts in a separate file. Some languages (such as double-byte) require special fonts to display and print correctly. The software stores the font settings in files according to language. Individual users can choose fonts by language for forms, grids, and reports.

1.6.3.3 User Display Preferences

User display preferences are individually defined sets of Release 9.1 characteristics that are stored in the user profile. The software uses these preferences to determine how menus and forms are presented to individual users and where language is to be used in Release 9.1 for that user. After user display preferences are set up for a given user, the values remain the same on any workstation that the user accesses. Refer to the *JD Edwards EnterpriseOne Tools System Administration Guide* for information about modifying user profiles.

Before You Begin the Upgrade

You should complete the tasks in this chapter before you begin the actual upgrade process.

This chapter discusses:

- [Section 2.1, "Preparing to Upgrade to Release 9.1 from Prior Releases"](#)
- [Section 2.2, "Preparing the Prototype Environment"](#)
- [Section 2.3, "Preparing the Development Environment"](#)
- [Section 2.4, "Preparing the DB2/400 Database for Table Conversions"](#)
- [Section 2.5, "Checking Modification and Merge Flags"](#)
- [Section 2.6, "Changing the Journal"](#)
- [Section 2.7, "Refreshing and Verifying Data"](#)
- [Section 2.8, "Verifying Software and Hardware Requirements"](#)
- [Section 2.9, "Verifying the Disk Space Requirements"](#)
- [Section 2.10, "Cleaning Up Disk Space on the Servers"](#)

2.1 Preparing to Upgrade to Release 9.1 from Prior Releases

The Upgrade order should be:

1. Install the Deployment Server, which includes JD Edwards EnterpriseOne Tools Release 9.1.
2. Install the Platform Pack, which includes JD Edwards EnterpriseOne Applications Release 9.1.
3. Using Server Manager, install the latest update (service pack) to the JD Edwards EnterpriseOne Tools Release that is required to support JD Edwards EnterpriseOne Applications Release 9.1.

For example, if you are upgrading from JD Edwards EnterpriseOne 8.10 to JD Edwards EnterpriseOne Release 9.1, you should install the most current service pack or update for Tools Release 9.1 (where service packs and updates are cumulative and includes the base release).

4. Install the latest planner update.

For example, if you are upgrading from JD Edwards EnterpriseOne 8.9 to JD Edwards EnterpriseOne Release 9.1, you should install the most recent Release 9.1 planner update.

5. Run the Installation Planner.
6. Run the Installation Workbench.
7. Build packages.
8. Run post upgrade manual table conversions.
9. Apply all ESUs from the update center to get fix current.
10. Use Visual compare to retrofit custom objects.

By following this procedure, you are assured of saving time and avoiding extra work associated with retrofitting and retesting custom code in the future.

Before you begin the upgrade, you must prepare your current development, production, and prototype environments and back up your Deployment Server, Enterprise Servers, and databases.

You must complete these preparatory tasks before the upgrade team arrives.

Caution: It is important to turn off Table Auditing, if you are using it, before beginning the upgrade process. Failure to do so may cause the audited tables to be in inconsistent states, requiring the tables to be recovered. For more information on turning off the Table Audit function, refer to the *Auditing Administration Guide including 21 CFR Part 11*. Table Auditing may be turned on again after the upgrade has been completed.

2.2 Preparing the Prototype Environment

To make sure you retain all modifications from your prototype environment:

1. Make sure the network services JD Edwards EnterpriseOne network services are running on the Enterprise Server.

Note: The service names will be prefixed with JDE for releases prior to 8.9 and after 8.11, while the prefixed will be PSFT for releases 8.9, 8.10, and 8.11.

2. From the System Administration Tools menu (GH9011), select Batch Versions.
3. Transfer PD versions to prototype so the two environments are the same.
4. Run R9830512.
5. Select ZJDE0001 and click Copy.
6. Create a new version name and a new version title.
Leave security set at 0.
7. To select the new version on the version prompting form, check the Data Selection box.
8. Select the advanced options to bring up the Advanced version prompting form and select to Override Location.
9. Click Submit.
10. When prompted for the override location, select LOCAL.

11. Modify the data selection logic like this:

where BC Version History (F983051) is not equal to "XJDE0000-XJDE9999",
and BC Version History (F983051) is not equal to "XJDEAAAA - XJDEZZZZ"

12. When prompted to enter processing options, ensure that they are set at 1, A, 1, and 1, as shown on this screen:

Processing Options

Update Options

1. Enter a "0" for Proof Mode or a "1" for Update Mode.

2. Enter a "A" to only add new UBE Version records (no records will be replaced).

3. Enter a "1" to copy Processing Option Text.

4. Enter a "0" to copy version specs along with versions data (Upgrade) or a "1" to copy versions data only (Update)

13. Click OK on printer selection.

14. Click OK.

15. Build a prototype package. This package can be used later to verify that your custom versions were upgraded properly.

16. Deploy the prototype package to workstations. Run the release you are upgrading from, for example, B7333.

See Also

Transferring Objects and Package Build in the JD Edwards EnterpriseOne Tools Package Management Guide for more specific instructions about building and deploying packages.

2.3 Preparing the Development Environment

If you do not have a development environment, you can skip this procedure.

Caution: For your initial upgrade, do not select the DV910 environment as the target of the upgrade if you are upgrading a copy of your production data. The Development (DVxxx) environment defaults to loading demo data during the upgrade, so loading using the upgrade installer would result in a mixture of your data and the JD Edwards EnterpriseOne demo data in some of your tables.

To make sure you retain all modifications from the previous development environment:

1. Make sure that all work in progress is checked into the development pathcode.

Caution: From a development workstation, use Object Management Workbench, or your own query or report, to verify that objects are not checked out. Also, verify that no objects are checked out to individual workstations. Any modifications that are checked out will not be carried forward to the new release.

2. Build the development package in preparation for deployment to one or more workstations.
3. Deploy the development package to one or more workstations.

These workstations are used later to help verify that all custom modifications were carried forward to the new release.

Caution: You cannot make any modifications to the environment you are upgrading (except changes to custom business functions written in C language), and still carry them forward to the next release.

See Also

Transferring Objects and Package Build in the JD Edwards EnterpriseOne Tools Package Management Guide for more specific instructions about building and developing packages.

2.4 Preparing the DB2/400 Database for Table Conversions

The upgrade process requires specific database preparation to account for the various CPU-bound and data size requirements. It is important to note that during execution of the Table Conversion Workbench you will need sufficient disk space to accommodate two copies of tables being converted. To account for this disk space requirement, you should identify the four largest tables which you plan to convert, determine their current size, and multiple that by two.

For example, the following table shows a hypothetical environment where the largest tables are F0911, F42199, F42119, and F41021.

Largest Tables	Existing Size (see Note)	Existing Size Doubled
F0911	120 MB	240 MB

Largest Tables	Existing Size (see Note)	Existing Size Doubled
F42199	80 MB	160 MB
F42119	90 MB	180 MB
F41021	56 MB	112 MB
Total Amount of Space Required to Run Tables Conversions		692 MB

Note: This includes the size of the table and all unique indexes on that table.

That is, if N is the number of concurrent jobs in the TC Workbench, then the Temp disk space should be as large as the N largest tables combined, including all indexes.

Note: This includes the size of the table and all unique indexes on that table.

That is, if N is the number of concurrent jobs in the TC Workbench, then the data files and transaction log should be as large as the N largest tables combined, including all indexes.

For DB2\400 databases, ensure that:

- Your IBM i machine is running the supported OS version and latest database PTFs as detailed in the MTRs for JD Edwards EnterpriseOne. Refer to [Section 1.3.1, "Accessing Minimum Technical Requirements \(Certifications\)"](#).
- You do *not* enable journaling during the conversion.
- Your Deployment Server is running with the latest iSeries Access PTF.

2.5 Checking Modification and Merge Flags

This task ensures that your modifications are carried forward to the new release. Before you upgrade, perform the steps to review or set the modification flags on the Object Librarian records for all modified objects.

Caution: Do not run the Specification merges until you check the flags for all pathcodes containing modified objects.

To check modification and merge flags:

1. Logon to the workstation or to the deployment environment on the Deployment Server.
2. On the menu (GH9611), select Specification Merge Selection.

3. On the Specification Merge Selection form, complete these fields:
 - *Location*
Enter the name of the Deployment Server that is the check-in location for this pathcode.
 - *Path Code*
Enter the name of the associated pathcode (prototype or development).
4. On the QBE line, enter C in the Mod Flag field to list the changed objects, and then click Find.
5. Set the MrgOpt field to 1 for all objects except those you do not want to merge; use Enable to carry changed objects and use Disable to not carry changed objects.
6. When you finish reviewing or modifying the records, click Close.

Caution: To verify the accuracy of included modifications, additional queries are strongly recommended to avoid missing any modified objects. For example, verify that the system code of the objects is 55 to 59.

2.6 Changing the Journal

JD Edwards EnterpriseOne Release 9.1 uses LOB data in different native LOB data types - BLOB, CLOB, etc. The JRN and JRNRCV must have new attributes defined in them to handle the LOB data types, where JRN and JRNRCV in the previous release

cannot handle the LOB data types. The Platform Pack Installer changes the journal attributes using this command:

```
RCVSIZOPT(*MAXOPT2)
```

After the upgrade process completes, ensure the old STRJOURNAL *PGM object has been replaced with the new one in JD Edwards EnterpriseOne Release 9.1.

2.7 Refreshing and Verifying Data

Before running Installation Workbench, you have the option to refresh the business data for the environment being upgraded with a current set of Production data. Having a recent copy of the data makes testing table conversions and the new release more effective. For example, when you upgrade the development environment, refresh Business Data - TEST; and when you upgrade the PY environment, refresh Business Data - CRP.

The source can be any data set you choose, but you should use a current copy of your production data. When table conversions run during Installation Workbench, this data is converted to the new Release 9.1 formats, as required. By using a copy of your production data, you ensure a successful upgrade of your live production data later.

This section discusses:

- [Section 2.7.1, "Refreshing the Business Data"](#)
- [Section 2.7.2, "Deleting SQL Packages"](#)
- [Section 2.7.3, "Refreshing the Control Tables"](#)
- [Section 2.7.4, "Verifying Custom Changes in Master Control Tables"](#)
- [Section 2.7.5, "Backing Up the Servers and Databases"](#)
- [Section 2.7.6, "Working with Purge Tables"](#)
- [Section 2.7.7, "Working with Accounts Payable Processing"](#)

2.7.1 Refreshing the Business Data

To copy your business data, you must add a version of R98403 that is similar to XJDE0021 from a B73.3.x or B9 workstation, and then run it in proof mode to make sure the data selection and processing options are set correctly.

To refresh the business data:

1. From the System Administration Tools menu (GH9011), select Batch Versions.
2. In the Batch Application field, enter R98403.
3. Click Find.
4. Run your version (the one that is similar to XJDE0021).
5. On the Processing Options Environment tab, verify the processing options.
6. Click OK.
7. After running the batch application in proof mode, run in update mode to recreate the existing tables.

Because User-Defined Code (UDC) and menu merges are customer-based, copy them from the production environment to the PY environment. If upgrading the development environment, consider refreshing the development environment control tables from production environment to test the software.

Before running Installation Workbench to upgrade the prototype or development environment, copy the current production environment control tables (Control Tables - Production) to the Control Tables - Test or Control Tables - CRP data source, depending on the environment to upgrade. This makes sure that your master control tables are used when the upgrade merges run during Installation Workbench.

2.7.2 Deleting SQL Packages

On the IBM i, you must delete existing SQL packages. You must do this before signing onto the software on the Deployment Server. Use these steps to delete the existing SQL packages:

1. STRPDM
2. Choose Option 2 with this criteria:
 - Library: <data library>, for example CRPDTA
 - Name: *ALL
 - Type: *SQLPKG
3. Choose Option 4.
4. Press Enter

2.7.3 Refreshing the Control Tables

To refresh the control tables:

1. From the previous release's planner environment, you must map tables for the environment being upgraded as shown in the list below. For example, for DV733x, map these tables to the Control Tables - Test data source.

F0004
 F0004D
 F0005
 F0005D
 F0082
 F00821
 F0083
 F0084
 F9100
 F9101
 F9102
 F9105
 F9105D
 F9106
 F9106D
 F9050
 F9010
 F9020
 F9021
 F9022
 F9023
 F9025
 F9030
 F98840
 F91011

F91012
 F91013
 F91014
 F98810D
 F98811
 F98830
 F98845
 F98800
 F98800D
 F98800T
 F98810

2. From the System Administration Tools menu (GH9011), select Batch Versions.
3. In the Batch Application field, enter R98403.
4. Click Find.
5. Run version XJDE0022 locally.
6. On the Processing Options Environment tab, verify the processing options are set to 1, 1, A, and 1.
7. Click OK.
8. Deactivate the mappings you defined for the tables listed in Step 1.
9. Reactivate the original mappings.

You must verify that your master control tables for release level B73.3.x or B9 include all custom changes you want to carry forward to Release 9.1. Verify them for each environment you want to upgrade.

2.7.4 Verifying Custom Changes in Master Control Tables

To verify custom changes in master control tables:

1. Verify that the previous release's master control tables for the data dictionary reside in a relational database accessed by the Data Dictionary data source:
 - F9200
 - F9202
 - F9203
 - F9207
 - F9210
 - F9211
 - F9212
 - GT92002 (F00165)
2. Verify that the previous release's master control tables for menus reside in a relational database accessed by the Control Tables - Production data source (for production), Control Tables - CRP (for PY environments), or Control Tables - Test (for the development environment):
 - F9100
 - F9101
 - F9102

- F9105D
 - F9106D
3. Verify that the B73.3.x or B9 master control tables for user defined codes reside in a relational database accessed by the Control Tables - Production data source (for production), Control Tables - CRP (for PY environments), or Control Tables - Test (for the development environment).

2.7.5 Backing Up the Servers and Databases

This section discusses:

- [Section 2.7.5.1, "Backing up the Deployment Server"](#)
- [Section 2.7.5.2, "Backing Up the Enterprise Server"](#)
- [Section 2.7.5.3, "Backing Up the Oracle Databases"](#)

2.7.5.1 Backing up the Deployment Server

The Deployment Server must be completely backed up, because some JD Edwards EnterpriseOne objects exist in directories other than normal JD Edwards EnterpriseOne structures.

2.7.5.2 Backing Up the Enterprise Server

Prior to beginning the upgrade, you should back up the complete directory structure for the JD Edwards EnterpriseOne base installation.

To back up your IBM i-based Enterprise Server:

1. Save all data libraries that contain JD Edwards EnterpriseOne tables using the `SAVLIB` command.
2. Save all JD Edwards EnterpriseOne system libraries using the `SAVLIB` command.
3. Save the specifications for all pathcodes using the `SAV` command.

2.7.5.3 Backing Up the Oracle Databases

To back up your Oracle databases:

1. Fully export all instances (one at a time).
2. Perform a cold back up of the complete Oracle database.

2.7.6 Working with Purge Tables

These tables have changed format from Release 9.1:

- F3111S
- F3112S
- F31122S

The upgrade process will drop and recreate these tables. These are Purge tables, and the upgrade process does not preserve the data in purge tables.

2.7.7 Working with Accounts Payable Processing

If you are upgrading, you must use the Work with Payment Groups application (P04571) to reset or finish (write and update) all accounts payable processing. The Financials department or financials consultant can assist you with this task.

Note: Failure to accomplish this task causes data corruption in accounts payable processing files. To verify that no unfinished accounts payable processing records exist, tables F04571 and F04572 should both be empty.

2.8 Verifying Software and Hardware Requirements

Certain minimum hardware and software requirements must be met to run Release 9.1 on various operating systems and servers. Verify that the Deployment Server, Enterprise Servers, and workstations meet the hardware and software requirements.

Because the software and hardware requirements change rapidly as manufacturers constantly update their products, requirements are not provided in this documentation. Refer to [Section 1.3.1, "Accessing Minimum Technical Requirements \(Certifications\)"](#).

Note: Make sure that you have taken and installed the latest Planner Update ESU from the Oracle JD Edwards Update Center. Failing to do so may prevent proper installation of the software.

Additionally, a new compiler requirement is added for Release 9.1. Before you run the Deployment Server or Platform Pack installer, you should install a Microsoft Visual C++ compiler on any machine on which the installer will be run. The MTRs list supported C++ compilers on Microsoft Windows-based machines. Refer to [Section 1.3.1, "Accessing Minimum Technical Requirements \(Certifications\)"](#)

2.8.1 Adding a New Entry to the QAQQINI File

Once you have put the latest PTFs onto the IBM i, you need to enable the new LOB locator functionality. If you do not do this, Specifications Merge and Package Build will fail.


1. Open the QAQQINI file on the Enterprise Server using this command:

```
WRKOBJ QUSRSYS\QAQQINI *FILE
```

2. If the QAQQINI file does not exist, add it using this command:

```
CRTDUPOBJ QAQQINI QSYS *FILE QUSRSYS DATA(*YES)
```

3. Start IBM i Navigator.



4. Navigate the *Databases* node and then expand to show your machine name.
5. Right click on your machine name and select Run SQL Scripts.
6. Run these SQL commands:

```
SELECT * FROM QUSRSYS.QAQQINI
```

In the results, you should search for this entry:

```
LOB_LOCATOR_THRESHOLD
```

If the `LOB_LOCATOR_THRESHOLD` entry does not exist, you should insert it by running this command:

```
INSERT INTO QUSRSYS.QAQQINI VALUES ('LOB_LOCATOR_THRESHOLD', '10000',
default)
```

If the `LOB_LOCATOR_THRESHOLD` entry does exist, you should ensure that the value for `QQVAL` is set to 10000. If the `QQVAL` value is set to anything other than 10000 (for example, `*DEFAULT`), you must change it using this command:

Tip: If you have `STRSQL`, you can also run this command directly from that program.

```
UPDATE QUSRSYS.QAQQINI SET QQVAL='10000' WHERE QPPARM='LOB_LOCATOR_THRESHOLD'
```

7. Sign out of the IBM i Navigator and make sure the `QZDASOINIT` job is terminated. This is required because a new database connection must be started with the new values for `QZDASOINIT`.


2.8.2 Setting up Your IBM i

This section contains these tasks:


- [Setting Up AS/400 TCP/IP Services](#)
- [Setting Up a Network Share for IBM i Root](#)
- [Starting the EDRSQL Service](#)

2.8.2.1 Setting Up AS/400 TCP/IP Services


Use this procedure to set up the TCP/IP services on your IBM i.



1. In IBM i Navigator, open the node for your IBM i machine and drill down to Network | Servers | TCP/IP and right click on IBM i NetServer, and select Properties.



2. On IBM i NetServer File Share Properties - *<machine_name>*, click the Next Start button.




3. On IBM i NetServer General Next Start - *<machine_name>*, click to enable the checkbox for this setting:
Start when TCP\IP is started
4. Click OK to close the General Next Start dialog, and then click OK again to close the NetServer Properties dialog.


2.8.2.2 Setting Up a Network Share for IBM i Root

Use this procedure to set up a network share on your IBM i root.

1. Start IBM i Navigator
2. Expand your machine in the tree.
3. Drill down into the *Network* node.
4. Drill down into the *Servers* node.
5. Highlight *TCP\IP*.
6. In the right hand panel find IBM i NetServer.
If it has a status of Stopped, right click and start it.
7. Double click on the started IBM i NetServer.



8. Navigate from File | New | File and complete these fields:
 - *Share Name*
Enter this value: *ROOT*
 - *Description*
Enter the Root directory in IFS.
 - *Access*
Use the pulldown to choose Read\Write.
9. On IBM i NetServer - File Share Properties <machine_name>, click OK.



10. On IBM i NetServer File Share Properties, right click on Root and go to properties and make sure that Access is set to *Read\Write*.


Note: The default value is Read only.

11. Click OK to save the Read\Write setting.


2.8.2.3 Starting the EDRSQL Service

Tip: Alternatively, instead of using IBM i Navigator as detailed in this procedure, you can logon to a TN5250 session as QSECOFR and invoke this command:

```
STRTCPSVR SERVER(*EDRSQL)
```



1. On IBM i Navigator, while still on Network | Servers | TCP\IP, right click on EDRSQL, choose Properties.



2. On Setting Up AS\400 TCP\IP ServicesEDRSQL Properties, click in the checkbox to enable this setting:

Start when TCP\IP is started

2.9 Verifying the Disk Space Requirements

The amount of disk space you need for Release 9.1 software on the Deployment Server and Enterprise Server depends on many variables according to platform and database. For the Deployment Server, all disk space must be available on one drive *except* if you

use the Remote Share option. With the Remote Share option, there must be enough room on one remote share for all the path codes. For Enterprise Server installation, multiple foundations during the install are not supported. There must be enough space on one disk drive for all logic components.

During the install you *cannot* choose to have Printqueue and build areas installed onto another location. Additionally you must have sufficient disk space on either the Enterprise Server or a separate Database Server for the scripts and the database components.

After you have completed an installation, you can manually relocate some components of the Enterprise Server on different drives, such as printqueue location, build areas, package location, and BI-Publisher storage. Additionally, when using multiple foundations it is possible to use different drives for each set of JD Edwards EnterpriseOne pathcodes. However, it is important to note that for purposes of the initial installation, having the correct amount of space available, but not on a single drive, is not adequate. Up-to-date disk space requirements are listed in the Release 9.1 Minimum Technical Requirements. Refer to [Section 1.3.1, "Accessing Minimum Technical Requirements \(Certifications\)"](#).

Note: While the disk space tables accurately represent the disk space requirements, the actual requirements for an installation will be greater due to the requirement for temporary space.

2.10 Cleaning Up Disk Space on the Servers

Make sure you have enough disk space before starting the upgrade. You may delete some directories from previous releases to increase space on your system.

Note: Parallel Release Considerations

If you want to maintain the recommended parallel environments, and if you have sufficient disk space, you should keep your complete prior release directory structure intact, such as B733.x and B9. To run parallel, you must keep at least the CLIENT, PLANNER and DATA, PLANNER and SPEC, pathcode, and SYSTEM directory structures.

Path Code Considerations

If you use the JD733x pathcode, or any packages associated with it, do not delete the JD733x directory structure. However, if the directory is only a copy of the JD Edwards EnterpriseOne pristine objects for a previous release, you can delete it.

See Also

[Section 2.8, "Verifying Software and Hardware Requirements"](#)

[Section 2.9, "Verifying the Disk Space Requirements"](#)

2.11 Applying Microsoft Product Updates

You should apply all the critical updates for Microsoft on your Deployment Server including Visual C++.

Tip: If you already have the required components installed, you can install Microsoft .NET without prompting for the prerequisite installation image by entering this command line:

```
x:\setup\setup.exe /NO_BSLN_CHECK
```

where x: is the drive on which the .NET setup program resides.

Working with the Deployment Server

This chapter discusses:

- [Section 3.1, "Using IXS \(Integrated xSeries Server\) for Deployment"](#)
- [Section 3.2, "Planning for IBM i Integration"](#)
- [Section 3.3, "Installing Microsoft Windows Visual Studio"](#)
- [Section 3.4, "Understanding the Deployment Server"](#)
- [Section 3.5, "Local Oracle Enterprise Edition \(OEE\) Considerations"](#)
- [Section 3.6, "Obtaining and Preparing the Deployment Server Install Image"](#)
- [Section 3.7, "Working with JDBC Drivers on the Deployment Server"](#)
- [Section 3.8, "Installing the Deployment Server"](#)
- [Section 3.9, "Adding Additional Environments \(Rerunning the Deployment Server Installer\)"](#)
- [Section 3.10, "Downloading and Installing the Latest Software"](#)
- [Section 3.11, "Troubleshooting Deployment Server Installation"](#)

3.1 Using IXS (Integrated xSeries Server) for Deployment

This section describes the unique installation of the Microsoft Windows operating system if the Deployment Server is an integrated part of the IBM i. After verifying the hardware and software required for the Deployment Server on My Oracle Support (requirements are the same as for an external Deployment Server), use this section for an overview of the Integrated xSeries Server installation. The actual step by step instructions are found on the IBM IBM i Information Center web site (see below).

With this choice, the IBM i system arrives with the integrated Deployment Server in a non-configured state. The integrated server is one of these two types:

- Integrated xSeries Server for IBM i (IXS)

This server is essentially a Personal Computer (PC) on a card. It contains an Intel processor and memory but is diskless. With the IXS there is a PC card inside the IBM i system ready to become the Deployment Server.

- Integrated xSeries Adapter for IBM i (IXA)

This adapter consists of two parts:

1. An HSL bus adapter with cables ready to be plugged into a supported Netfinity or xSeries Server, and

2. One of the supported IBM Netfinity or xSeries Servers, separately ordered, without any disk. This integrated server will appear as an HSL attached expansion unit to the IBM i system.

Neither the internal IXS nor the external IXA contains disk drives; OS/400 disk storage will get allocated to either server type. The IBM i should have been ordered with enough disk to support the dedicated the Deployment Server.) The disk can be configured as one or more virtual drives called network storage spaces of varying capacities. These virtual drives are allocated within the OS/400 integrated file system. The Microsoft Windows software perceives them as physical hard drives. The IXS card is the usual choice for the Deployment Server because it meets the MTRs at a lower price than the IXA. The rest of this section, therefore, is based on the IXS.

There are three IBM redbooks that contain detailed installation and configuration information. Refer to this link:

<http://www.redbooks.ibm.com/>

- Consolidating Microsoft Windows 2000 Servers in IBM i: An Implementation Guide for the IBM Integrated xSeries Server for IBM i, SG24-6056, December, 2000
- Direct Attach xSeries for the IBM IBM i Server: A guide to Implementing xSeries Servers in IBM i, SG24-6222-00, December, 2001
- Microsoft Windows Server 2003 Integration with IBM i, SG24-6959-00, December, 2003

The Microsoft Windows Integration Home page offers additional information concerning OS/400, hardware specifications, etc.

The total disk used for the Release 9.1 Deployment Server is allocated across at least three Network Server Storage spaces associated with the Integrated xSeries Server:

1. Microsoft Windows system files represent the c: drive on the Microsoft Windows Server.

Note: Take these considerations into account when estimating the size of the c: drive on your Microsoft Windows Server:

- The more memory you have installed on the integrated server hardware, the larger you should make the c: drive. Microsoft Windows Server creates a virtual memory paging file (`pagefile.sys`) on the system drive. Microsoft Windows Server calculates the size of the paging file based on the amount of physical memory (RAM) installed on the server. It is generally recommended that you allocate at least 150% of the installed memory size as additional disk storage on the system drive to accommodate the paging file. For example, on an IXS Server with 512 MB of RAM, you should plan for a paging file size of 768 MB when considering how large to make the system drive.
 - When applications are installed on the server, many of them install some of their files on the system (c:) drive, so you should plan for this requirement.
 - When you install a Microsoft Windows Server service pack, you have the option of saving the files that are replaced, in case you need to uninstall the service pack. Therefore, if you choose the uninstall option, you may require up to 100 MB of additional free space on the system drive.
 - Future versions of Microsoft Windows Server may require additional free space on the c: drive to plan for an upgrade of the existing installation.
-

Tip: The recommended configuration is:

- **Microsoft Windows 2000 Server**
c: drive = 1,250 MB + (1.5 times installed memory) + Applications
(for example, Microsoft Visual C++, OEE, etc.)
- **Microsoft Windows Server 2003**
c: drive = 1,500 MB + (1.5 times installed memory) + Applications
(for example, Microsoft Visual C++, OEE, etc.)

2. Installation source files represent the d: drive on the Microsoft Windows Server. This drive also contains the files supplied by IBM as part of the integration for Microsoft Windows Server. The d: drive only needs to be large enough to accommodate the Microsoft Windows Server installation source files, client-side integration software, and any future updates to the integration software (provided by service packs).

Tip: The recommended configuration is:

- **Microsoft Windows 2000 Server**
d: drive = 500 MB
- **Microsoft Windows Server 2003**
d: drive = 800 MB

- Storage space is required for the Release 9.1 code, where the total space required depends on the JD Edwards EnterpriseOne files and on the number of pathcodes you install. See *Before You Begin the Installation or Upgrade* of this manual to calculate your Release 9.1 exact requirements for the size of the Deployment Server.

The first two disk drives, Microsoft Windows system and installation source spaces, get created and linked to the network server description during the INSWNTSVR command. The Release 9.1 drive will need to be created and linked to the network server description after the INSWNTSVR command and Microsoft Windows Server installation completes. Keep in mind that the total amount of disk allocated to these network storage spaces is instantly unavailable to the IBM i so you need to size correctly. Track % disk utilization for the network server storage spaces in WRKDSKSTS or IBM i Navigator both before and after the installation. See the redbooks mentioned for additional details on creating and linking storage spaces.

The instructions for setting up the operating environment for this Deployment Server (prior to installing Release 9.1) are in the IBM i Information Center.

Choose your region, OS/400 version and language. This web site provides the installation, configuration, operational and general use information for the IXS and IXA features. This topic is also available as a printable PDF file. Locate the documentation searching for *Windows Server*.

It is advisable to read through the entire Microsoft Windows server on IBM i topic, especially the Pre-installation Checklist, as you will need to be familiar with most of these points concerning the Integration software, hardware and set up process.

3.2 Planning for IBM i Integration

The steps in this section correspond to those in the topic *Plan for IBM i Integration* for Microsoft Windows Server installation for Microsoft Windows 2000 or Microsoft Windows 2003 Server. These are the main basis of the installation, with helpful hints highlighted.


- Microsoft Windows Server Installation Advisor.** This step consists of answering configuration questions either via the worksheet or on the web site using the interactive wizard. After you answer the questions to the Microsoft Windows Server installation advisor, it displays the Planning Worksheet which provides a summary of the values that were specified on the previous panels of the advisor. An example is shown below.

Field	Description
Network server description	<i>Name:</i> AS4IXS1 <i>Description:</i> Deployment, Microsoft Windows 2000, Lin06, 1.6 GHz, 1 GB memory
Hardware type	2892
Resource name	lin06
Microsoft Windows version	Microsoft Windows 2000
Language version	Primary national language of OS/400
Keyboard layout	Default keyboard layout
Microsoft Windows source directory	First optical device
System drive	8000 MB

Field	Description
NTFS	Convert system drive to NTFS.
Installation source drive	500 MB
Message logging	Do not log messages.
Event log	Log these messages: <ul style="list-style-type: none"> ■ System ■ Security ■ Application
Synchronization	Synchronize Microsoft Windows date and time with OS/400 date and time every 30 minutes.
Propagate domain users	Propagate domain users using this server.
Restricted device resources	Do not restrict tape or optical devices.
Client license type	Each computer has a client license.
Terminal Services	Do not install Terminal Services.
Domain role	Server.
Server domain name	Join this workgroup: workgroup
TCP/IP local domain name	Use the configured OS/400 local domain name.
Private LAN	For the private LAN between Microsoft Windows and OS/400, use the generated IP addresses.
TCP/IP port	Use these TCP/IP values for Port 1: IP address: 10.230.14.90 Subnet mask: 255.255.255.0 Gateway: 10.223.1.124
TCP/IP name server	Use the name servers that are configured for OS/400.
Clustering	Do not use clustering; it is not supported.

Using the wizard is preferred because the end result is the OS/400 command (INSWNTSVR) that can be pasted into your green screen and then executed in step 3.

2. Install IBM i Integration for Microsoft Windows Server - this step is unique to the IBM i and a pre-requisite to setting up the integrated Deployment Server via the installation command. It loads the Integrated Microsoft Windows software (5722-WSV) and any PTFs that are required on IBM i.
3. Install the Microsoft Windows server- this step loads the Microsoft Windows software using regular Microsoft Windows CDs similar to an external Deployment Server except the process is begun with the OS/400 command (INSWNTSVR) that invokes the Microsoft Windows installation. When you click on next in the wizard from step 1, the screen below summarizes the answers from the advisor onto a command line which can be copied and pasted onto your green screen.



Note: Before you hit Enter for the INSWNTSVR command, be sure to have your keyboard, mouse, and CRT attached to the IXS card. The reason is that the command continues by booting the IXS card and instructing you to continue at the Microsoft Windows server console; if the hardware is not attached in advance, you will have to vary off the IXS and repeat this step.

Copy the resulting command containing your choices onto your green screen, similar to this one:

```
INSWNTSVR NWSD(your server name) INSTYPE(*FULL) RSRNAME(your
communication line) DMNROLE(*SERVER) WNTVER(*WIN2000) TCPPOPCFG((1
'10.230.14.90' '255.255.255.0' '10.224.1.124')) EVTLOG(*ALL)
SVRSTGSIze(xxx yyyy) CVTNTFS(*YES) TOWRKGRP('workgroup')
RSTDDEVRSC(*NONE) TEXT('Deployment, Win2k, lin06, 1.6 GHz, 1 GB
memory')
```

where xxx is the size of your installation source drive and yyyy is the size of your Microsoft Windows C: drive. Be sure to put the first Microsoft Windows install CD into your IBM i CD-ROM drive, and hit Enter. This command loads Microsoft Windows and creates your C and D drives out of IBM i disk, a C drive for boot and Microsoft Windows system drive, and a D drive for Microsoft Windows installation source drive.

Note: The green screen will remain input inhibited until the completion indicator is shown and responded to at the Microsoft Windows server console. Now move to the Microsoft Windows screen.

4. Continue the Microsoft Windows 2000 or Microsoft Windows 2003 Server Installation from the Microsoft Windows server console. This step requires you to click Finish and restart the Integrated Microsoft Windows Server.

Note: Rebooting the IXS card does not affect the rest of the IBM i system. Restarting the IXS card can be accomplished from the Microsoft Windows screen using normal Microsoft Windows commands such as Shutdown or Control-Alt-Delete. (If the IXS card happens to be powered off at any time, then the IXS card will need to be varied on under WRKCFGSTS *NWS or under IBM i Navigator Network, Microsoft Windows Administration, Integrated xSeries Servers and right click on *name of your IXS server*.)

5. Complete Microsoft Windows 2000 or Microsoft Windows 2003 Server Installation. Refer to the [Section 1.3.1, "Accessing Minimum Technical Requirements \(Certifications\)"](#) for the recommended Microsoft Windows Service Pack level that you get from Microsoft. Apply it normally via Microsoft Windows. An IBM maintenance wizard is used to install the Microsoft Windows Integration software service pack of PTFs from IBM that get downloaded to Microsoft Windows from IBM i. This step also includes directions for setting your Microsoft Windows server to automatically vary on with TCP/IP (which includes at IPL time). Vary on to your Deployment Server and validate it.

Note: In this integrated environment, OS/400 and Microsoft Windows typically share the IBM i CD-ROM drive. In order for Microsoft Windows to use the drive, it must first be "locked". From Microsoft Windows via Start, Programs, IBM i, Integration for Microsoft Windows Server, *name of your IXS server*, IBM i devices, OPT01 (or your optical drive name), All Tasks, then right click and lock device. Be sure to unlock it after use, if the IBM i needs it next. Rebooting the Deployment Server always unlocks the optical device automatically so be sure to relock it if Deployment Server will use it again after a reboot.

After completing the above four steps of the Microsoft Windows installation, you will need to carve out at least one additional Network Server Storage space from IBM i disk to be used as dedicated Deployment Server disk for Release 9.1 with an assigned drive letter.

```
CRTNWSSTG NWSSTG(AS4IXS14) NWSSIZE(40000) TEXT('Release 9.1 G drive')
```

Once the storage spaces are created, you can vary the IXS off again in order to link the drives to the Microsoft Windows server. After the Release 9.1 drive is linked, you will vary the Deployment Server back on and you are ready to proceed with the normal set up of Microsoft Visual C++, TCP/IP, FTP, etc.

Note: It is a good idea to create a *SAVF, and back up your C drive in case you need to recover the Microsoft Windows operation system quickly:

```
CRTSAVF FILE(QGPL/IXS1CDRIVE)
```

Vary off the Deployment Server and then enter these commands:

```
SAV DEV(' /QSYS.LIB/QGPL.LIB/IXS1CDRIVE.FILE')
```

```
OBJ(' /QFPNWSSTG/AS4IXS1') DTACPR(*YES)
```

Note: It is a good idea to increase the size of your application event file on the Deployment Server, such as increasing from 512 KB to 2 MB, before beginning the deployment process to prevent it from filling up and halting the job.

3.3 Installing Microsoft Windows Visual Studio

Before running the Deployment Server Installation, install the Visual Studio 2008 SP1 RunTime. Refer to [Section 1.3.1, "Accessing Minimum Technical Requirements \(Certifications\)"](#) in this guide. The Visual Studio 2008 RunTime is available from the Microsoft Download Center. Download and install one of the following:

Microsoft Visual C++ 2008 SP1 Redistributable Package (x86) - 32-bit vcredist_x86.exe

Microsoft Visual C++ 2008 SP1 Redistributable Package (x64) - 64-bit vcredist_x64.exe

Note: Choose the 32-bit or the 64-bit installer that is appropriate for the Microsoft Windows platform on which the OUI Installation for Deployment Server will be run.

3.4 Understanding the Deployment Server

The Deployment Server for JD Edwards EnterpriseOne must reside on an Intel Pentium-based computer running Microsoft Windows. The JD Edwards EnterpriseOne software installation and upgrade programs enable you to create and maintain installation plans and deploy Release 9.1 to the Enterprise Servers and workstations.

Beginning with JD Edwards EnterpriseOne Applications Release 9.1, the Deployment Server installation program is based on the Oracle Universal Installer (OUI). You can use the OUI to:

- Install the JD Edwards EnterpriseOne Deployment Client on a local or remote Deployment Server

This installation includes attaching and importing the Planner and Workbench tables into the local database on the Deployment Server.

Also beginning with Release 9.1, only the Oracle Enterprise Edition (OEE) database is supported as the local database on the Deployment Server.

Note: The Oracle Universal Installer (OUI) requires the Microsoft Visual Studio 2008 VS2008SP1 Run Time. Refer to the section of this guide entitled: [Section 3.3, "Installing Microsoft Windows Visual Studio"](#).

A local OEE database must exist before you can run the OUI-based Deployment Server installer. The JD Edwards program called InstallManager is used to start the installation of the local OEE database.

No separate end-user licensing is required for installation of the local OEE database. It should be noted, however, that the installed OEE database is not fully functional relative to the commercial versions of the Oracle databases that are available.

For additional considerations, refer to [Section 3.5, "Local Oracle Enterprise Edition \(OEE\) Considerations"](#).

Caution: If you are upgrading to JD Edwards EnterpriseOne Applications Release 9.1, this is the order in which you should proceed:

1. Install the Deployment Server as described in [Section 3.8, "Installing the Deployment Server"](#).
 2. Install the latest Tools Release as described in [Section 3.10.1, "Installing the Latest Tools Release and Latest Tools Release Patch to the Deployment Server"](#).
 3. Install the latest Planner Update ESU on the deployment server and run special instructions as described in [Section 3.10.2, "Installing the Latest Planner Update and Running the Special Instructions"](#).
 4. Run the Workbench on Pristine environment as described in [Chapter 6, "Working With Installation Workbench"](#).
 5. Apply the Planner Update ESU to the Pristine environment.
 6. Build an Update Package as described in the *JD Edwards EnterpriseOne Package Management Guide*.
-

3.5 Local Oracle Enterprise Edition (OEE) Considerations

The Deployment Server installer includes the OEE database (version 11gR2) for local use by the Deployment Server. The installation includes GUI tools for database administration.

Caution: Because the Deployment Server installer must have access to a local OEE database, you must install the 32-bit database client prior to installing the Deployment Server.

This section discusses these topics:

- [Section 3.5.1, "32-Bit Oracle Database Client \(Required for both 32-bit and 64-bit versions of OEE\)"](#)
- [Section 3.5.2, "EnterpriseOne Application P96717"](#)
- [Section 3.5.3, "Best Practices for OEE Performance"](#)
- [Section 3.5.4, "Microsoft Windows Internet Protocol Version 4 \(IPv4\)"](#)

3.5.1 32-Bit Oracle Database Client (Required for both 32-bit and 64-bit versions of OEE)

If you installed OEE on a 64-bit version of Microsoft Windows, you must also install a 32-bit version of the Oracle database client and then copy your `tnsnames.ora` file to a subdirectory under the database client installation directory.

Caution: Because the Deployment Server installer must have access to a local OEE database, you must install the 32-bit database client prior to installing the Deployment Server.

To install a 32-bit Oracle database client:

1. Download the 32-bit Oracle 11g database client from the Oracle Software Delivery Cloud located at this link:

<http://edelivery.oracle.com>

2. Install the database client.

Caution: PATH environment variable. If you installed the 64-bit Oracle database, the installer placed the path to the database (for example, `c:\Oracle\E11local\bin`) at the start of the Windows PATH environment variable. Then when you installed the 32-bit Oracle database client, the installer placed the path to the database client (for example, `c:\Oracle\product\11.2.0\client_1\bin`) at the start of the Windows PATH environment variable.

When EnterpriseOne runs, it looks for database drivers in each directory from start to finish in the PATH. The first occurrence of a driver DLL that EnterpriseOne finds will be loaded. This means that the path to the 32-bit Oracle database client must come **BEFORE** the path to the 64-bit Oracle database.

If you installed the 64-bit database and 32-bit database client in that order, the order in the PATH should be correct. However, if you installed them in the opposite order, you need to correct the order in the PATH.

To reverse the order of the 64-bit database and 32-bit database client paths in the Windows PATH, follow these steps:

1. From the Start button, select Control Panel and then System.
 2. On the left side of the window that comes up, click Advanced system settings.
 3. Click the Advanced tab.
 4. Click Environment Variables....
 5. In the "System variables" box, highlight the variable Path and click Edit...
 6. In the "Variable value" field, cut the 32-bit database client's path and the following semicolon (for example, `c:\Oracle\product\11.2.0\client_1\bin;`).
 7. Paste the client's path and semicolon at the start of the Path value.
 8. Click OK.
 9. Click OK to exit from the Environment Variables window.
 10. Click OK to exit from the System Properties window.
 11. Close the Control Panel's System window.
-

3. After you install the Deployment Server, you can copy this `tnsnames.ora` file that the installation delivered:

From:

`\\<deployment server name>\<release>\client`

To:

`<32-bit Oracle Client Install Dir>\network\admin`

3.5.2 EnterpriseOne Application P96717

Best practices in JD Edwards EnterpriseOne environments are to never directly modify an EnterpriseOne database outside of EnterpriseOne. You should always use the JD Edwards EnterpriseOne application P96717 to perform the following Oracle database actions:

- Import Tablespace

- Export Tablespace
- Create Tablespace
- Drop Tablespace

3.5.3 Best Practices for OEE Performance

You should always verify that your Deployment Server machine meets the MTRs (refer to [Section 1.3.1, "Accessing Minimum Technical Requirements \(Certifications\)"](#)). The local Oracle database performs best on hard drives that are not fragmented or full. Additionally, the following table lists some guidelines for minimum configurations.

Specification	Recommendation
RAM	2 GB minimum
Page File Size	Minimum setting should be two times the amount of memory
Disk Space Usage	Oracle database engine requires approximately 1.7 GB of disk space JD Edwards EnterpriseOne specifications require approximately 1.7 GB of disk space When fully loaded, best performance is obtained if the hard drive on the Deployment Server machine has at least 20% free space.
Local Database Name	Ensure that any reference in data sources and .ini files refer to the local database name in the <i>exact</i> mixed case, which is: E1Local Failure to use the exact mixed case will lead to decreased performance of JD Edwards EnterpriseOne on the Deployment Server.

3.5.4 Microsoft Windows Internet Protocol Version 4 (IPv4)

The JD Edwards EnterpriseOne Deployment Server requires Microsoft Windows Internet Protocol Version 4 (IPv4) for connectivity. It cannot function using IPv6.

If your Deployment Server is not working as expected, use this procedure to determine if the problem is due to your Windows machine using IPv6 and if so, to remedy:

1. After installing the local Oracle database, use a text editor to open the `log.xml` file which is typically located in this directory

```
C:\Oracle\diag\tnslsnr\[MACHINE NAME]\listener>alert\.
```

2. Examine the contents of the `log.xml` file for indicators that the machine is using IPv6 addresses.

IPv6 addresses can be distinguished by alphanumeric digits separated by colons, rather than periods as in IPv4 addresses.

One example is if you see `host_addr='::1'>`. This indicates an IPv6 address, which in this case is the machine's local loopback address, whose equivalent IPv4 address is 127.0.0.1.

Another example that indicates the use of IPv6 is if this string exists:

```
host_addr='fe80::7045:1aba:cb6d:1b50%13'
```

3. If you see references to IPv6 addresses in the logs after installing the Oracle local database, then you may need to deinstall the Deployment Server and Oracle database as described in the chapter of this guide entitled: [Chapter 27.3](#),

["Deinstalling the Local OEE from the Deployment Server,"](#).

Also, you may possibly need to perform additional cleanup for the Oracle Database as described in the section of this guide entitled: [Section 27.4, "Manual Cleanup of a Deinstalled Oracle Database on the Deployment Server"](#).

4. After the deinstall and cleanup is complete, you must apply a software patch from Microsoft to disable IPv6 before reinstalling the Oracle local database and EnterpriseOne Standalone or Web Development Client. The Microsoft patch for disabling IPv6 is at the following link:

How to disable IPv6 or its components in Windows

<http://support.microsoft.com/kb/929852>

On the above Microsoft web page, click the link labelled **Disable IPv6** (Microsoft Fix it 50409).

5. After you apply the Microsoft patch to disable IPv6, you can reinstall the Oracle database and EnterpriseOne Standalone Client using the procedures in this guide.

MICROSOFT DISCLAIMER ON DISABLING IPV6

Important: Internet Protocol version 6 (IPv6) is a mandatory part of Windows Vista and later versions. We do not recommend that you disable IPv6 or its components, or some Windows components may not function. For more information, see the "What are Microsoft's recommendations about disabling IPv6?" question in IPv6 for Microsoft Windows: Frequently Asked Questions at this link:

<http://technet.microsoft.com/en-us/network/cc987595.aspx>

3.6 Obtaining and Preparing the Deployment Server Install Image

You install the Deployment Server Install image from DVD images obtained from the Oracle e-delivery web site:

<http://edelivery.oracle.com>

To install from images downloaded from the Oracle e-delivery web site:

1. Create a parent download directory on a disk with at least 15 GB free space. For example:
`c:\DepSvr\Disk1`
2. Download the source DVD images for the JD Edwards EnterpriseOne Deployment Server into the directory you created in Step 1.
3. You must use either the 7-Zip or WinZip program to unzip each of the DVD images into the directory you created in Step 1 (to verify successful extraction see **Caution** below).

Note: During the extraction if you receive a message indicating that `.. \META-INF\MANIFEST\MF` already exists, at the prompt you can choose either Ignore or Replace.

Caution: You cannot use the built-in Microsoft Windows Explorer functionality to extract the zip files otherwise the result is an incomplete install image. You **must** use WinZip or 7Zip.

To verify a successful extraction, check the file size of SPEC_MASTER.DBF. This file should be 1.8 GB.

After unzipping all DVDs, you should have a structure that looks like this:

```
c:\DepSvr\Disk1\
    DeploymentServer\
    Install\
    META-INF\
    Misc\
    stage\
    InstallManager.exe
    InstallManager.htm
    InstallManager.ico
    ONEWORLD.ICO
    OracleLogo.gif
    README.TXT
```

Caution: The directories contained on the Disk2, Disk3, Disk4, Disk5, and Disk6 images are all at the same hierarchal level as the \Disk1\DeploymentServer directory.

When your unzip operation is complete, all the files must be in the same structure as the \Disk1\DeploymentServer directory.

You should not have either a Disk2, Disk3, Disk4, Disk5, or Disk6 directory.

3.7 Working with JDBC Drivers on the Deployment Server

The Deployment Server requires database-specific JDBC drivers for several purposes as described below. This section describes:

- [Section 3.7.1, "Obtaining the JDBC Drivers"](#)
- [Section 3.7.2, "Copying the JDBC Drivers to the Deployment Server"](#)

3.7.1 Obtaining the JDBC Drivers

Based on the database being used on your JD Edwards EnterpriseOne Enterprise Server, you should obtain the required java-based JDBC driver files from your database vendor. Access the current Minimum Technical Requirement (MTR) listing from My Oracle Support for the proper JDBC driver files to obtain. For help with locating MTRs, refer to [Section 1.3.1, "Accessing Minimum Technical Requirements \(Certifications\)"](#). Place the driver files in the location specified in the section of this guide entitled: [Section 3.7.2, "Copying the JDBC Drivers to the Deployment Server"](#).

In addition, for JD Edwards EnterpriseOne Release 9.1, all installations of OEE on the Deployment Server require a driver for local database connectivity on the Deployment Server (required to build and deploy ESUs) and to perform installations of the Web Development Client (workstation). You can locate the Oracle database driver in these locations:

- Oracle Enterprise Edition Database (on your JD Edwards EnterpriseOne Enterprise or Database Server)

Your installation of an Oracle 11gR2 database product includes the Oracle JDBC driver(s). Typically the driver is located in this directory of your Oracle 11gR2 installation:

`\jdbc\lib`

- Oracle Technology Network (OTN)

<http://www.oracle.com/technetwork/indexes/downloads/index.html>

You cannot have multiple Oracle JDBC driver files (such as `ojdbc5.jar` and `classes12.jar`) in the same folder (`\misc`) or else the drivers will conflict, which will cause access failure to the Oracle database on your Enterprise Server. The Oracle JDBC driver (for example, `ojdbc5.jar`) is added to the `\misc` folder by the Deployment Server installer.

Note: You must manually copy the driver files from the installed location to the location specified in the section of this guide entitled: [Section 3.7.2, "Copying the JDBC Drivers to the Deployment Server"](#).

3.7.2 Copying the JDBC Drivers to the Deployment Server

Caution: This step must be done before starting the installer, as one of its first steps the installer attempts to load all jar files needed for the process.

After you have obtained the JDBC driver(s) from the database vendor(s), you should copy the driver file(s) (and, if applicable, any associated license files) in this directory on the Deployment Server:

`x:\DepSvr\Disk1\Misc`

where "x" is a drive name, and

where `DepSvr\Disk1\Misc` is the Deployment Server install image.

You must supply this directory location and name when you run the Deployment Server Installer.

3.8 Installing the Deployment Server

Caution: Microsoft Windows 2008. If you are running the JD Edwards EnterpriseOne Deployment Server on a Microsoft Windows 2008 platform, you must be signed onto the machine as administrator. Additionally you must run all JD Edwards EnterpriseOne installers and processes 'as Administrator'.

Due to the security model on Microsoft Windows 2008, failure to run the JD Edwards EnterpriseOne processes 'as Administrator' will likely result in random and unpredictable failures in the processes at run time.

Caution: Remote Desktop. If you are using Remote Desktop to connect to the Deployment Server, you must use the `/admin` argument to launch Remote Desktop. For example:

```
C:\WINDOWS\system32\mstsc.exe /F /admin
```

If you do not run Remote Desktop with the `/admin` argument, Microsoft Windows blocks several important installer functions although Microsoft Windows reports success to the installer. For example, some registry entries will be missing and the Share for the Deployment Server will not be correctly created.

The Oracle Universal Installer (OUI) process creates temporary files during the install. By default these are placed on the c: drive of your Windows-based Deployment Server. You may need a sizable amount of free space on your c: drive in order to complete the installation successfully.

Microsoft Windows 2008

For Microsoft Windows 2008, pay special attention to the various Cautions in the steps in this chapter.

This table lists the mandatory and optional components of the Deployment Server installation.

Server	Mandatory Component	Optional Components
Deployment Server	Deployment Client	Development environment
	EnterpriseOne Files	Prototype environment
		Pristine environment
		Production environment

The installation process for the Deployment Server performs these functions:

- Installs the objects from the CDs.
- Creates the path code directory structures (such as PS910 and PD910) based on your selections.
- Updates the Microsoft Windows Registry.

Note: You can run the Deployment Server and the Platform Pack installation concurrently (assuming the installation programs are run on different machines).

After verifying the support structure as shown in the section of this guide entitled: [Section 3.6, "Obtaining and Preparing the Deployment Server Install Image"](#), you can install the Deployment Server. This process installs the Deployment Server from CDs.

Note: You must install the Deployment Server locally; you cannot install the Deployment Server from a remote machine. However, you can choose to install JD Edwards EnterpriseOne files and environments on a remote machine using a mapped drive. Prior to installing to a remote machine, you must have already setup the drive with network mapping.

This section describes these topics:


- [Section 3.8.1, "Prerequisites"](#)
- [Section 3.8.2, "Installation Process Flow"](#)
- [Section 3.8.3, "Before Launching the Deployment Server Installer"](#)
- [Section 3.8.4, "Understanding Destination Paths"](#)
- [Section 3.8.5, "Using InstallManager to Install a Local Database on the Deployment Server"](#)
- [Section 3.8.6, "Examine the Local Database Installer Logs"](#)
- [Section 3.8.7, "Understanding the JD Edwards EnterpriseOne Deployment Server Installer"](#)

3.8.1 Prerequisites

Before you run the installation program, shut down all programs running on the Deployment Server that could cause DLL conflicts (such as Microsoft SQL Services, Internet Explorer, Microsoft Word, or Adobe Acrobat). You can restart these programs after you finish installing the Deployment Server.

3.8.2 Installation Process Flow

The diagram below illustrates the process flow and the various installation paths.



3.8.3 Before Launching the Deployment Server Installer

Before you launch the Deployment Server installer, you should obtain the JDBC drivers for the Enterprise Server database and also for your local database, which is Oracle Enterprise Edition (OEE). You can place the JDBC drivers in the CD images directory on your Deployment Server either before or after running OUI to install the Deployment Server; however, it is preferable that you copy the drivers before running OUI. For instructions on obtaining and placing the requisite JDBC drivers, refer to the section [Section 3.7, "Working with JDBC Drivers on the Deployment Server"](#).

Note: The Deployment Server OUI installer delivers the requisite JDK/JVM.

Tip: Installation Methods

You can install the Deployment Server using any of these methods:

- Directly from the Deployment Server installation DVD.
- From a copy of the Deployment Server installation DVD that exists on a hard disk drive.
- From a downloaded and unzipped image of the installation DVD that was obtained from the Oracle E-Delivery web site.

3.8.4 Understanding Destination Paths

Each Oracle product that is installed on a machine has what is termed an **Oracle Home** directory or path. This is a directory that contains all the files associated with the product. This path has a name as well. You can specify a name that is intuitive so you do not have to remember the path.

When you install the JD Edwards EnterpriseOne Deployment Server, you specify an **Oracle Home** and name for that installation as well. For example, you may enter C:\JDEdwards\E910 as the Oracle Home path and **JDE DEP910_HOME** as the Oracle Home name. Following the this example, your **Oracle Home** on the Deployment Server would be:

Oracle Home Path	Oracle Home Name	Comment
C:\JDEdwards\E910	JDE_DEP910_HOME	This is the Oracle Home of the Deployment Server

3.8.5 Using InstallManager to Install a Local Database on the Deployment Server

If you have not already installed the database engine and a database called E1Local does not exist on your Deployment Server, use the procedures in this section to install these requisite components before installing the JD Edwards EnterpriseOne Deployment Server. If the local database engine is already installed and an E1Local database exists, do not reinstall the database engine; go to the section entitled: [Section 3.8.7, "Understanding the JD Edwards EnterpriseOne Deployment Server Installer"](#).

If you want to install the local database under the default location (that is, c:\Oracle), you can run InstallManager to do so. If you want to install into another directory, you must run the database installation program OEESetup.exe from a command prompt and provide one or more arguments.

This section discusses these topics:

- [Section 3.8.5.1, "Using InstallManager to Install a Local Database in the Default Location"](#)
- [Running OEESetup to Install a Local Database in a Directory Other Than the Default Location](#)

3.8.5.1 Using InstallManager to Install a Local Database in the Default Location

1. Obtain the appropriate disk images from Oracle Software Delivery Cloud for the local database you wish to install on your Deployment Server.
2. Log on to the Deployment Server as a user with Administrator rights.

Caution: Ensure that the Administrator account name that you use does not contain any special characters.

3. If you have not already done so, expand all disk images to be under a common directory called Disk1 on your Deployment Server.

Tip: Refer to the preceding [Tip: Installation Methods](#) for a list of various installation methods.

Caution: Microsoft Windows 2008. For Windows/2008, if you are using a physical DVD and the installation starts automatically, you must cancel this process and start the installation manually.

Caution: Microsoft Windows 2008. On the Microsoft Windows 2008 platform, you must right-click on the executable and select **Run as Administrator** from the drop-down.


4. From the Disk1 image, execute the InstallManager.exe file from the root folder.

\Disk1\InstallManager.exe

Caution: Microsoft Windows 2008. On the Microsoft Windows 2008 platform, you must right-click on the executable and select **Run as Administrator** from the drop-down.



5. On JD Edwards Install Manager, select this link to install the local OEE database:
[EnterpriseOne Database Engine](#)



6. Click the **Run** button to launch the OEESetup.exe installer.



7. If you receive an Install Manager - Security warning dialog with the message "The publisher could not be verified", click the **Run** button to begin the installation of the local database. This installation process can take quite some time. Upon completion a local database called **E1Local** will exist.

Caution: You must reboot your machine before continuing with the installation of the JD Edwards EnterpriseOne Deployment Server as described in the next section in this guide entitled: [Section 3.8.7, "Understanding the JD Edwards EnterpriseOne Deployment Server Installer"](#).

3.8.5.2 Running OEESetup to Install a Local Database in a Directory Other Than the Default Location

1. Obtain the appropriate disk images from Oracle Software Delivery Cloud for the local database you wish to install on your Deployment Server.

2. Log on to the Deployment Server as a user with Administrator rights.

Caution: Ensure that the Administrator account name that you use does not contain any special characters.

3. If you have not already done so, expand all disk images to be under a common directory called Disk1 on your Deployment Server.

Tip: Refer to the preceding [Tip: Installation Methods](#) for a list of various installation methods.

Caution: Microsoft Windows 2008. On the Microsoft Windows 2008 platform, if you are using a physical DVD and the installation starts automatically, you must cancel this process and start the installation manually.

Caution: Microsoft Windows 2008. On the Microsoft Windows 2008 platform, you must right-click on the executable and select **Run as Administrator** from the drop-down.

4. Open a command prompt window.

Caution: Microsoft Windows 2008. On the Microsoft Windows 2008 platform, you must right-click on the command prompt's executable (cmd.exe) and select **Run as Administrator** from the drop-down.

5. From within the command prompt window, change directory (cd) to directory that contains the extracted contents of the Disk1 image. For example:

```
DeploymentServer\OneWorld Client Install\ThirdParty\ORACLE
```

6. Run the following command:

```
OEESetup.exe -i installation_directory
```

where

the **-i** switch tells OEESetup.exe where to install the local database **E1Local**. If both this switch and the `installation_directory` argument are omitted, the local database will be installed under the default location `c:\Oracle`. If the default location is used, the database will then reside in this directory (instead of a user-specific directory):

```
c:\Oracle\E1Local
```

The argument `installation_directory` is optional; it represents the path where the local database will be installed. Do not include `E1Local` as part of this path. If this argument is not provided, you will be prompted for the path as shown below:



7. If you specified the `-i` switch but did not provide the `installation_directory` argument, you will see the above screen. On the screen entitled Oracle Base Directory, in the Path field, enter or browse to the directory into which you want to install the local Oracle database. For example:

`c:\Oracle`

Note: This installation process can take quite some time. Upon completion a local database called **E1Local** will exist in the specified directory. Using the example above, the database would be installed in this directory

`c:\Oracle\E1Local`

Caution: You must reboot your machine before continuing with the installation of the JD Edwards EnterpriseOne Deployment Server as described in the next section in this guide entitled: [Section 3.8.7, "Understanding the JD Edwards EnterpriseOne Deployment Server Installer"](#).

3.8.6 Examine the Local Database Installer Logs

Even though the screen indicates that the installation was successful, you should perform the following checks to verify that the database truly installed correctly:

1. **Examine the log file**

- The log file is in this folder:

`C:\Program Files\Oracle\Inventory\logs`

- The log file name is named:

`installActionsyyyy-mm-dd_hh-mm-ssAM|PM.log`

where the syntax is:

- yyyy is the year

- mm is the month
- dd is the day of the month
- hh is the hour
- mm is the minutes
- ss is the seconds
- AM|PM is either AM or PM
- For additional details on log file names and location, refer to the section of this chapter entitled: [Section 3.11.2, "OEE Installer Logs"](#).

2. Verify that the OEE services exist and are running

- a. From the Microsoft Windows Control Panel, navigate to Administrative Tools > Services.
- b. In the list of Services, look for these services:
OracleE1LocalTNSListener
OracleServiceE1LOCAL
- c. If either of the above services is missing, it indicates that there was a problem in completing all the installation and configuration steps. You should examine the logs specified in the table in the section of this guide entitled: [Section 3.11.2, "OEE Installer Logs"](#).

To remedy you will probably need to deinstall the database engine using the steps in the section of this guide entitled: [Section 27.5, "Using the OUI Installer to Deinstall JD Edwards EnterpriseOne from the Deployment Server"](#), reboot the Deployment Server machine, and then reinstall the OEE database.

3.8.7 Understanding the JD Edwards EnterpriseOne Deployment Server Installer

A local OEE database engine and a database called E1Local must already exist on this machine. If not, use the procedures in the preceding section entitled: [Section 3.8.5, "Using InstallManager to Install a Local Database on the Deployment Server"](#).

This section describes:

- [Section 3.8.7.1, "Understanding EnterpriseOne Files Location"](#)
- [Section 3.8.7.2, "Running the JD Edwards EnterpriseOne Deployment Server Installer"](#)

3.8.7.1 Understanding EnterpriseOne Files Location

The software component called *EnterpriseOne Files* is a pre-defined grouping of files that can be installed on your local machine or a mapped network drive. It includes EnterpriseOne system files and pathcodes for these four (4) environments:

- Development
- Prototype
- Pristine
- Production

By default the installer assumes the local machine is the Deployment Server. As such it provides a default value for your *Oracle Home* path.

You cannot change this local path value after the installation is complete; it must remain whatever value you specified at the time of installation.

Optionally you can choose to install EnterpriseOne (E1) Files to a remote machine as the Deployment Server. If you do so, the installer creates a unique "planner client" on the local machine that contains only the Planner pathcode. You should only set up one "planner client" machine to do the Deployment Server jobs such as applying software updates, running installation plan, and so on.

Using a Remote Machine as the Deployment Server

If you intend to use a remote machine as the Deployment Server, prior to running the Deployment Server installer you must first map a network drive using this procedure:


1. On the remote Deployment Server, create a folder as the target location in which the installer will place the EnterpriseOne (E1) files. For example:

E:\JDEdwards\E910

2. Using the example above, share the target folder E910 with full permissions.


Caution: Because the Deployment Server installer must be run as an Administrator, you must also map a network drive as an Administrator.

Start a Command Prompt as Administrator and map a network drive on the local machine to the remote Deployment Server machine. For example, map Z:\ to \\Remote_Deployment_Server_Machine_name\E910



Tip: You can verify that the drive is being mapped as an Administrator by confirming that "Administrator:" is displayed in the title bar of the Command Prompt window.

The below screen shows a sample of a properly mapped network drive for the remote Deployment Server:



Note: In a later separate process described in [Section 3.8.7.2, "Running the JD Edwards EnterpriseOne Deployment Server Installer"](#), when you are prompted by the installer for the location of the remote Deployment Server, in the location field you can browse to or enter the mapped drive including the drive letter designation. Using the above example in Step 1, the value would be the Z: drive. Using the above screen shot as an example, the value would be the L: drive.

The same installer validates the location that you enter for the remote location. If the mapping to the remote location is not valid or the directory specified in Step 1 above does not exist on the remote machine, the installer will not continue.

Note: The installer validates the location. If the mapping to the remote location is not valid the installer cannot continue. Likewise the directory specified in Step 1 must exist on the remote machine or else the installer cannot continue.

3.8.7.2 Running the JD Edwards EnterpriseOne Deployment Server Installer

Use the procedure in this section to install the JD Edwards EnterpriseOne Deployment Server.

1. Log on to the Deployment Server as a user with Administrator rights.

Caution: Ensure that the Administrator account name that you use does not contain any special characters such as ampersands, asterisks, or underscores.

2. Locate the disk 1, which is either a physical disc or disc image directory, for the Deployment Server installation DVD.

Tip: Refer to the preceding [Tip: Installation Methods](#) for a list of various installation methods.


Caution: Microsoft Windows 2008. For Windows/2008, if you are using a physical DVD and the installation starts automatically, you must cancel this process and start the installation manually.

Caution: Microsoft Windows 2008. On the Microsoft Windows 2008 platform, you must right-click on the executable and select *Run as Administrator* from the drop-down.


You must right-click on the executable and select **Run as Administrator** from the drop-down.

3. From disk1, execute the InstallManager.exe file from the root folder. For example:


\Disk1\InstallManager.exe



4. On JD Edwards Install Manager, select this link:
EnterpriseOne E910 Deployment Server




5. If you get the above prompt, click the **Run** button to execute the Deployment Server OUI installer, which is called by the `setup.exe` program. This process opens a Microsoft Windows command window as shown in the below example.

A screenshot of a Windows command window titled "Oracle Universal Installer". The text inside shows the progress of the installer: "Starting Oracle Universal Installer...", "Checking swap space: must be greater than 500 MB . Actual 6805 MB Passed", "Checking monitor: must be configured to display at least 256 colors Higher than 256 . Actual 65536 Passed", and "Preparing to launch Oracle Universal Installer from C:\Users\lcmadmin\AppData\Local\Temp\OraInstall12011-08-05_10-34-56AM. Please wait ... _".


```
Oracle Universal Installer
Starting Oracle Universal Installer...

Checking swap space: must be greater than 500 MB . Actual 6805 MB Passed
Checking monitor: must be configured to display at least 256 colors Higher than
256 . Actual 65536 Passed
Preparing to launch Oracle Universal Installer from C:\Users\lcmadmin\AppData\Local\Temp\OraInstall12011-08-05_10-34-56AM. Please wait ... _
```

After the OUI installer is launched, the command window is closed and the Welcome screen is displayed.



6. On Welcome, select the **Next** button.



7. On **Select Installation Type**, select the appropriate radio button for these installation types:


- **Typical**

The **Typical** selection installs environments for Deployment Client (Planner), prototype, pristine and also installs JD Edwards EnterpriseOne files on the local machine. This selection is recommended for the general user.

- **Custom**

The **Custom** selection lets you choose the specific environments you want to install on the deployment server. The deployment client (Planner) is always installed on the local machine. You may choose to install JD Edwards EnterpriseOne Files and environments on a remote machine. In that case, first you need to setup a mapped drive as described in the section of this guide entitled: [Section 3.8.7.1, "Understanding EnterpriseOne Files Location"](#). This selection is only recommended for an expert user.

8. After you have selected an installation type, select the **Next** button.



9. On **Specify Home Details**, you must specify an Oracle Home path and a name for that path.

Tip: For more information about Oracle Homes and recommendations for naming the Oracle Homes for the JD Edwards EnterpriseOne Deployment Server, see the section in this guide entitled: [Section 3.8.4, "Understanding Destination Paths"](#).

Each Oracle product that is installed on a machine has what is termed an **Oracle Home** path. This path contains all the files for each Oracle product. This path has a user-specified name as well.


On Specify Home Details, complete these fields:

Field	Description
<i>Name</i>	Enter a name for the Oracle Home for the JD Edwards EnterpriseOne Deployment Server. For example: JDE_DEP910_HOME
<i>Path</i>	The path you enter here is for the Oracle Home path where the E1 Deployment Server will be installed. For example, the path might be: C:\JDEdwards\E910 Do not specify the same <i>Oracle Home</i> name or path into which you installed the local database; however, you can specify a path that is a subdirectory of the database's Parent Oracle Home . For local installation, you must use the default value. For remote installation, this value must be the letter designation of the mapped drive. For additional details, refer to the section of this chapter entitled: Section 3.8.4, "Understanding Destination Paths" .

10. Select the **Next** button.

Tip: If you chose **Typical** installation on the preceding screen (Select Installation Type), you can skip directly to Step 16 located later in this task to complete the Deployment Server installation.

If you chose **Custom** installation on the preceding screen (Select Installation Type), proceed with the following steps.




Note: The Available Product Components screen and subsequent screens until the Summary are displayed if you chose **Custom** installation on Select Installation Type in Step 7.

11. On Available Product Components, EnterpriseOne Deployment Server, enable the checkboxes to select these features components you want to install:
 - **EnterpriseOne Deployment Client**

The selection for EnterpriseOne Deployment Client is mandatory in order to select other components. If you do not select this component, you cannot select any other components. This installs the planner pathcode and databases on the local machine. You will be given an option to install other components on a remote share.
 - **EnterpriseOne Files**

The selection for EnterpriseOne Files includes mandatory system files. If you do not select this component you cannot select any other environment components. Likewise, if you re-run the JD Edwards EnterpriseOne Deployment Server Installer to add an environment it will check to ensure that these files are already installed and you will not be given an option to install the environment on a machine, drive, or directory that is different from that which contains the JD Edwards EnterpriseOne files.
 - **Development Environment**
 - **Prototype Environment**
 - **Pristine Environment**
 - **Production Environment**

Tip: You can use the **Select All** button to select all components.



12. On Specify EnterpriseOne Files Location, you can accept the default local value or enter a mapped network drive.

The installer provides a default value which is your *Oracle Home* path. For example:

C:\JDEdwards\E910

If you prefer to install JD EnterpriseOne Files to a remote Deployment Server, you can specify a mapped drive. For example:

Z:\

For more on the proper use of mapped drives and network drives, refer to the following **Caution**.

Caution: You *cannot* enter a network path such as:

\\machine_name\network_share

If you enter a network path instead of a mapped drive, the installer will give an error.

When you click Browse to select the drive, if the mapped remote drive is not listed, perform these steps:

1. Start a Command Prompt session by right clicking and selecting **Run as Administrator**.


This command prompt opens on the Microsoft 2008 Server with **Administrator:cmd** in the header.

2. In the command window, type this command:

```
net use z: \\<MachineName>\<SharedPath>
```

where z: is the drive on which you mapped drive exists.

13. Select the **Next** button.




14. On Choose E1Local User Password, you can specify a secure password to be used for the E1Local Database Users on the Deployment Server. This unique password will be used for all database accounts created by the Deployment Server installer.

The default password is the same as the user name of the database account. For example, if the user name of the local database account is JDE, the default password is JDE.


If you do not specify a E1Local user password, by default the installer will use this value: **DEFAULT**. You cannot leave this field blank.

15. Select the **Next** button.

Sample Summary Screen for Typical Installation




Sample Summary Screen for Custom Installation



16. On Summary, verify the list of items to be installed is correct.

If there is insufficient disk space to complete the installation is available on the Deployment Server target machine, an error message is displayed.

17. Click the **Install** button.



The JD Edwards EnterpriseOne Deployment Server Installer displays a panel showing the ongoing status of the installation.



18. When the installation of the database finishes, the **End of Installation** screen is displayed.

Caution: *Examine the Installer Logs.* Even though the screen indicates that the installation was successful, you should always check the logs before you attempt to run the Deployment Server. The file is named log.txt and is located in the Deployment Server installation directory. For example:

```
C:\Program Files (x86)\Oracle\Inventory\logs\InstallActions\installActionsyyyy-mm-dd_hh-mm-ssPM.log
```

For additional details on log file names and location, refer to the section of this chapter entitled: [Section 3.11.2, "OEE Installer Logs"](#).

19. On End of Installation, select the **Exit** button.

3.9 Adding Additional Environments (Rerunning the Deployment Server Installer)

Caution: If you want to add an additional environment that you did not install when you first ran the Deployment Server Installer, you must re-run the installer from the **original disk image**. You cannot re-run the installer using the OUI-based installer.

You can only use the installer located accessed by Start > All Programs > Oracle - JDE_DEP910_HOME > Oracle Installation Products > Universal Installer for deinstalling the Deployment Server.

To rerun the Deployment Server Installer, follow the instructions in the preceding section of this chapter entitled: [Section 3.8, "Installing the Deployment Server"](#)

3.10 Downloading and Installing the Latest Software

Caution: You must start Change Assistant **as Administrator**. Right-click on the shortcut and select '**Run as Administrator**' from the drop-down.

Before continuing with the upgrade, download and install the latest Tools Release, Tools Release Patch, and Planner Update ESU from the JD Edwards EnterpriseOne Update Center.

Note: The order in which the following Tools Release and updates are applied is very important. Do not deviate from the order described in these procedures.

This section discusses:

- [Section 3.10.1, "Installing the Latest Tools Release and Latest Tools Release Patch to the Deployment Server"](#)

- [Section 3.10.2, "Installing the Latest Planner Update and Running the Special Instructions"](#)

3.10.1 Installing the Latest Tools Release and Latest Tools Release Patch to the Deployment Server

To install the latest tools release and latest tools release patch:

1. From the JD Edwards EnterpriseOne Update Center home page, download the latest Tools Release Patch (for example, 9.1.1.0) and Tools Release documentation.
2. Using the Tools Release documentation, install the Tools Release Patch to the Deployment Server.

Caution: You must right-click on the executable and select **Run as Administrator** from the drop-down.

Note: If you have ever used the Drag and Drop method of moving between Tools Releases for service packs, it is necessary to run the ReconfigureMSDE utility to encrypt the "system" database user's password. Refer to the section of this guide entitled: [Section 3.11.5.9, "Encrypting the Password of the Local Oracle Database"](#).

3.10.2 Installing the Latest Planner Update and Running the Special Instructions


Caution: As part of the local database installation, which is bundled with the Deployment Server Installer, the password for the system user on the E1Local database is encrypted. If you re-set this password, several JD Edwards EnterpriseOne functions will fail. If you should inadvertently reset the password, you can encrypt it again to the expected default password. Refer to the section of this guide entitled: [Section 3.11.5.9, "Encrypting the Password of the Local Oracle Database"](#).

To install the latest planner update:

1. From My Oracle Support, download the latest planner update for your Tools Release to the Deployment Server.
2. Run the self-extracting executable and follow the on-screen instructions to install the planner update on the Deployment Server.

Caution: You **must** apply the Planner Update ESU to the Pristine environment in order to get the latest Table Conversion changes, among other important changes.

You must right-click on the executable and select **Run as Administrator** from the drop-down.



3. You must enter a valid JD Edwards EnterpriseOne user and password to initialize the Planner.

The shipped values are JDE for the user and JDE for the password.

Note: The above login screen is displayed so the Planner Update can update the metadata specifications on the Deployment Server.

4. When the installation finishes, view the JD Edwards EnterpriseOne Deployment Server Setup form to confirm that the installation was successful.

Tip: If the folder into which you expanded the Planner Update is empty, you should run the self-extracting executable (JMnnnnn.exe) again. When the Welcome screen comes up, click on Cancel to quit.

5. Follow the steps in the Special Instructions, which are contained within an HTML file that is shipped with the Planner Update. The special instructions file is in this directory with this file name:

x:\download_directory\planner_update_id\E910SpecialInstructions.htm

where download_directory is the directory where you downloaded the Planner Update.

Caution: Every time you apply a new Planner Update you must run both of these:

- SpecialInstrs.bat
 - R98403XB XJDE0002
-

3.11 Troubleshooting Deployment Server Installation

This section discusses:

- [Section 3.11.2, "OEE Installer Logs"](#)
- [Section 3.11.3, "Configuration Files"](#)
- [Section 3.11.4, "Path Code Master \(F98611\)"](#)
- [Section 3.11.5, "Oracle Enterprise Edition"](#)

3.11.1 Verify Local Planner Tablespaces are Not Attached

If you are re-installing your Deployment Server, you must ensure that the local Planner tablespaces (OEE) are not attached. To detach the tablespaces, run these batch files:

```
jd Edwards\e910\planner\data\detach_planner.bat
```

```
jd Edwards\e910\planner\data\detach_metadata.bat
```

3.11.2 OEE Installer Logs

This section lists the log files for installations on the Deployment Server:

- x:\jdedebug.log

Note: The location is defined by this jde.ini setting:

```
[DEBUG]
DebugFile=d:\jdedebug.log
```

- x:\jde.log

Note: The location is defined by this jde.ini setting:

```
[DEBUG]
JobFile=D:\jde.log
```

- C:\ReconfigureMSDE.log
- \InstallLogs\attach_plannerdata.log
- \InstallLogs\attach_plannerspec.log
- \InstallLogs\Configurexxxspec.log

Where xxx denotes that there are several of these logs, which contain logging for predefined package specs. For example:

```
ConfigureDV910FAspec.log
```

- X:\JDEdwards\E910\Detachxxx.log

Where xxx denotes that there are several of these logs, which contain logging for predefined package specs. For example:

```
DetachDV910FAspec.log
```

See Also

For OEE-specific logs, refer to [Section 3.11.5.1.2, "OEE Logs"](#) in this chapter.

3.11.3 Configuration Files

Note: This section is provided for reference. You are not required to manually configure these files because the Deployment Server installer configures the .ini files appropriately for the OEE local database.

The data source definitions for OEE are defined in these configuration files:

- jde.ini
- jdbj.ini

The following lists some of the settings within the various configuration files that are related to the local database.

- jde.ini

```
[DB SYSTEM SETTINGS]
Type=E
LOBFlag=Y

[DB SYSTEM SETTINGS ' SECONDARY]
Type=E
LOBFlag=Y
```

- jdbj.ini

The jdbj.ini file specifies location of the tnsnames.ora file.

The jdbj.ini file also specifies the JDBC driver for Oracle as ojdbc5.jar, which replaces the version (classes12.jar) used in prior releases of JD Edwards EnterpriseOne.

```
[JDBj-BOOTSTRAP DATA SOURCE]
databaseType=E
lob=true

[JDBj-SPEC DATA SOURCE]
databaseType=E
lob=true

[JDBj-JDBC DRIVERS]
ORACLE=oracle.jdbc.driver.OracleDriver
```

Caution: The shipped `jdbj.ini` file in the following folder contains specifications for each database type:

System\OC4J\j2ee\home\applications\
webclient.ear\webclient\WEB-INF\classes

You must manually comment out (with a semicolon) every database driver that you are not using. For example, if you are connecting to only Oracle databases, your file would look like this:

```
[JDBj-JDBC DRIVERS]
ORACLE=oracle.jdbc.driver.OracleDriver
;AS400=com.ibm.as400.access.AS400JDBCdriver
;SQLSERVER=com.microsoft.sqlserver.jdbc.SQLServerDriver
;UDB=COM.ibm.db2.jdbc.app.DB2Driver
```

3.11.4 Path Code Master (F98611)

The Path Code Master (F98611) contains changes to support OEE. It contains values for use of EMDBSY column to indicate type of specs and type of local database. These values are used by JDB, JDBj, and Package Build.

EMDBSY Value	Spec Type	Local DB Type
0	TAM	MSDE
1	XML	MSDE
2	TAM	SSE
3	XML	SSE
5	XML	Oracle

3.11.5 Oracle Enterprise Edition

This section discusses these topics:

- [Section 3.11.5.1, "File Locations"](#)
- [Section 3.11.5.2, "Rebooting the Deployment Server"](#)
- [Section 3.11.5.3, "EnterpriseOne Access to the Local Oracle Database"](#)
- [Section 3.11.5.4, "Process Explorer"](#)
- [Section 3.11.5.5, "Verifying the Local Oracle Database Installation"](#)
- [Section 3.11.5.6, "Deployment Server Installation Problems"](#)
- [Section 3.11.5.7, "Runtime Problems"](#)
- [Section 3.11.5.8, "Administering the Local Oracle Database Using SQL Plus"](#)
- [Section 3.11.5.9, "Encrypting the Password of the Local Oracle Database"](#)
- [Section 3.11.5.10, "Decrypting the Password of the Local Oracle Database"](#)
- [Section 3.11.5.11, "Import and Export Tablespaces to the Local Oracle Database"](#)
- [Section 3.11.5.12, "Updating the InstallManager.htm File"](#)
- [Section 3.11.5.13, "Deployment.inf and <Package_name>.inf"](#)

3.11.5.1 File Locations

This section discusses the location for these critical files:

- [Section 3.11.5.1.1, "Oracle Installation Directory"](#)
- [Section 3.11.5.1.2, "OEE Logs"](#)
- [Section 3.11.5.1.3, "tnsnames.ora"](#)

3.11.5.1.1 Oracle Installation Directory Deployment Server. The default installation location of the local Oracle database on the Deployment Server is:

C:\Oracle\E1Local

Note: This location can be changed at installation time.

Client. The default installation location of the local Oracle database on the Web Development Client (also called the Administration client or fat client or workstation) is:

C:\Oracle\E1Local

Note: This location can be changed at installation time.

3.11.5.1.2 OEE Logs The following table lists the locations of the various log files.

Log File	Location
Import for Planner databases	<E1_install_dir>\planner\Data\Imp*.log
Import for Planner specs	<E1_install_dir>\planner\spec\Imp*.log
Oracle import log for package specifications (created during Install and also during Package Workbench)	<E1_install_dir>\<pathcode>\package\<pkg_name>\Spec\imp*.log and Imp*.log
Oracle export log for specifications (created during Install and also during Package Workbench)	<E1_install_dir>\<pathcode>\package\<pkg_name>\Spec\exp*.log and Exp*.log
Local Oracle database runtime	C:\Oracle\diag\rdbms\e1local\e1local>alert\
Local Oracle database listener	C:\Oracle\diag\tnlsnr\<this_machine>\listener>alert\
Log for ReconfigureMSDE.exe	C:\ReconfigureMSDE.log
Local Oracle database install logs	c:\Program Files\Oracle\Inventory\logs
Log for OEESetup.exe	c:\OEEInstall.log

3.11.5.1.3 tnsnames.ora The tnsnames.ora file is located in these directories:

..\Oracle\E1Local\NETWORK\ADMIN

..\System\OC4J\j2ee\home\applications\webclient.ear\webclient\WEB-INF\classes

3.11.5.2 Rebooting the Deployment Server

You must reboot the Deployment Server after installing or deinstalling the local Oracle database.

3.11.5.3 EnterpriseOne Access to the Local Oracle Database

The Deployment Server Installation Workbench generates and encrypts a password and then changes the local Oracle database "system" and "sys" accounts' passwords to that password. During the rest of the Installation Workbench and at runtime of the Deployment Server, the local Oracle database is accessed via the "system" account and this generated and encrypted password.

This table lists the relationship between the local Oracle database accounts and the password.

Local Oracle Database	
Account	Default Password
System	Generated and encrypted by the Deployment Server installer.
Sys	Generated and encrypted by the Deployment Server installer.
JDE	JDE Note: The default password may be changed by DBA but if Security Server is not used, it must match the password of EnterpriseOne user JDE.
<tablespace_name>	<tablespace_name>
For example:	For example:
■ JDESY910	■ JDESY910
■ JDEOL910	■ JDEOL910
	Note: The default password may be changed by DBA. This value does not affect the runtime operation of JD Edwards EnterpriseOne because it does not access the local Oracle database in this manner.


3.11.5.4 Process Explorer

If you cannot delete the directory for the *E1Local* Oracle Home because a process has it locked, you can use Process Explorer to determine which process has it locked, and subsequently kill that process.


To obtain Process Explorer, you can download and install a free version at this link:

<http://technet.microsoft.com/en-us/sysinternals>

To use Process Explorer:



1. Navigate to Find > Find Handle or DLL....



2. In the **Handle or type** field, enter the full name of the directory that cannot be deleted. For example:
c:\oracle\ellocal
3. Click the Search button.
4. On the search results screen, note the PID(s) (Process IDs) that are associated with the specified directory.
5. Cancel the Process Explorer Search window to return to Process Explorer.
6. Use Process Explorer to kill the identified process(es).

Note: If one or more of the processes is Windows Explorer (explorer.exe), killing it may cause the computer to lock up. If that happens, you will need to reboot the Deployment Server machine.

The process Oracle.exe is the local Oracle database engine. If it has a file locked, you can stop the service **OracleServiceE1LOCAL**.

7. If one or more of the processes locks a file in the directory you are trying to delete even after rebooting, you may have to determine which service is automatically starting that process and change the service to manual startup. Then reboot the Deployment Server machine and delete the directory.

3.11.5.5 Verifying the Local Oracle Database Installation

To verify that the installation of the local Oracle database was successful:

1. Inspect the latest logs in these directories:

<E1_install_dir>\InstallLogs

C:\Program Files\Oracle\Inventory\logs

2. Resolve any issues that are identified in the logs.

3.11.5.6 Deployment Server Installation Problems

You cannot reinstall the local Oracle database using the Deployment Server installer if there are indications that the local Oracle database already exists. The Deployment Server installer will skip the installation of the local Oracle database if either of these conditions is true:

- The local Oracle database service **OracleServiceE1LOCAL** is running.
- This registry key exists:
 \HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\ORACLE\KEY_
 E1Local

3.11.5.7 Runtime Problems

This section discusses:

- [Section 3.11.5.7.1, "Jde.log shows ORA-12541: TNS:no listener"](#)
- [Section 3.11.5.7.2, "User gets a pop-up window prompting for E1Local DB user and password and Jde.log shows OCI0000141 - Error - ORA-01017: invalid username/password; logon denied"](#)
- [Section 3.11.5.7.3, "tnsnames.ora"](#)

3.11.5.7.1 Jde.log shows ORA-12541: TNS:no listener Verify that the Oracle listener service **OracleE1LocalTNSListener** is running. It is possible that the service may not have started due to slow bootup of the machine.

3.11.5.7.2 User gets a pop-up window prompting for E1Local DB user and password and Jde.log shows OCI0000141 - Error - ORA-01017: invalid username/password; logon denied Verify that the E1Local database system account password is valid. If the following command executes successfully, it means that the password is not encrypted. If so, you must encrypt the password in order to enable database access.

```
SQLPlus.exe system/admin@E1Local
```

where "admin" is the password. This password may have been set to "admin" by one of the EnterpriseOne database scripts, or it may be a plain-text word that someone set by running ReconfigureMSDE.

If the password was decrypted with ReconfigureMSDE, you should re-encrypt it using ReconfigureMSDE.exe. Refer to the section of this guide entitled: [Section 3.11.5.9, "Encrypting the Password of the Local Oracle Database"](#).

3.11.5.7.3 tnsnames.ora When the Deployment Server installer installs the local Oracle database (E1Local), the \bin directory is added to the start of the Windows PATH. If you have both the local Oracle database and the Oracle client installed (for example, if you are connecting to an Oracle database on a machine other than the Deployment Server), the local Oracle database version of the executables and tnsnames.ora are used. In order to maintain functionality of the Oracle client, you should add the remote database server tnsnames entries into the tnsnames.ora used by E1Local, which is located in this directory:

```
<OEE_installation_path>\network\admin
```

By default, the <OEE_installation_path> is C:\Oracle\E1Local, but the actual value is specified during OEE installation.

3.11.5.8 Administering the Local Oracle Database Using SQL Plus

The command-prompt program SQLPlus.exe and GUI program SQL Developer are provided with the installation of the local Oracle database using the Deployment Server installer. You can use either tool to access the local Oracle database where both the user and default password are the same as the tablespace name. If using SQLPlus, the command to sign into a database is:

```
SQLPlus.exe <user>/<password>@E1Local
```

For example, if the tablespace JDESY910 exists in the E1Local database, use the following to sign in:

```
SQLPlus.exe JDESY910/JDESY910@E1Local
```

3.11.5.9 Encrypting the Password of the Local Oracle Database

JD Edwards EnterpriseOne connects to the local Oracle database (E1Local) through the **system** account using an encrypted password. Some of the administrative database scripts on the Deployment Server decrypt this password before submitting database commands. Upon exit, such programs subsequently then re-encrypt the password. If one of these scripts fails to complete (for example, it is killed or it otherwise dies) before it can encrypt the password again, EnterpriseOne will not be able to connect to the database. You can determine if this is the case by attempting to sign into the local Oracle database using this command:

```
SQLPlus.exe system/admin@E1Local
```

where "admin" is the default password that the scripts use.

If you can sign in, the password must still be decrypted. You must re-encrypt the system account password using the following steps for EnterpriseOne to operate correctly:

1. Locate this program:

```
<E1_install_dir>\system\bin32\ReconfigureMSDE.exe
```

2. Right click on ReconfigureMSDE.exe and select **Run as administrator**.

Tip: Do not let the "MSDE" part of the program name mislead you. This program was originally created when EnterpriseOne supported Microsoft's MSDE database. It was not renamed when support for OEE was added.

3. Be sure the **E1Local** database is selected.
4. Enter the "system" user's old password (in this case, enter "admin" without the quotes) in the field "Change from password...."
5. Under "To password", click on "Encrypted E1 Password."
6. Click OK.
7. Click OK.
8. Watch the status bar at the bottom of the dialog for informational messages.
9. If changing the password fails, attempt to stop and restart the database services **OracleServiceE1LOCAL** and **OracleE1LocalTNSListener** and then retry `ReconfigureMSDE.exe`.

3.11.5.10 Decrypting the Password of the Local Oracle Database

To decrypt the **system** account password:

1. Locate this program:
`<E1_install_dir>\system\bin32\ReconfigureMSDE.exe`
2. Right click on `ReconfigureMSDE.exe` and select **Run as administrator**.

Tip: Do not let the "MSDE" part of the program name mislead you. This program was originally created when EnterpriseOne supported Microsoft's MSDE database. It was not renamed when support for OEE was added.

3. Be sure the **E1Local** database is selected.
4. Under "Change from password...", click on "Encrypted E1 Password."
5. Enter the "system" user's new password in the field "To password."
6. Reenter the new password and click OK.
7. Click OK.
8. Watch the status bar at the bottom of the dialog for informational messages.
9. If changing the password fails, attempt to stop and restart the database services **OracleServiceE1LOCAL** and **OracleE1LocalTNSListener** and then retry `ReconfigureMSDE.exe`.

Caution: If you manually decrypt the **system** account password, ensure that you re-encrypt the password before attempting to run JD Edwards EnterpriseOne. If the password is not encrypted, JD Edwards EnterpriseOne will fail because it cannot access the local Oracle database.

3.11.5.11 Import and Export Tablespaces to the Local Oracle Database

You can use the JD Edwards EnterpriseOne application P96717 to import and export tablespaces *except* the Planner. To import or export the Planner tablespaces, you must use scripts that are delivered with the installation of the Deployment Server. The scripts are located in this directory:

For Planner Databases:

<E1_install_dir>\planner\data

For local metadata repository database (for example, specs and serialized objects):

<E1_install_dir>\planner\spec

This section discusses:

- [Section 3.11.5.11.1, "Import Tablespace Script \(attach_planner.bat\)"](#)
- [Section 3.11.5.11.2, "Export Tablespace Script \(detach_planner.bat\)"](#)

3.11.5.11.1 Import Tablespace Script (attach_planner.bat) To use the import tablespace script:

1. Navigate to the directory JDEdwards\E910\planner\data and run this script:

```
TestPlannerDBs.bat
```

2. Edit the attach_planner.bat file such that any tablespaces that you do not intend to import are commented out. These lines start with:

```
call %DATA_PATH%\IMPORT_TABLESPACE.BAT
```

3. Open a command prompt window by right-clicking on a Command Prompt shortcut and selecting **Run as administrator**.
4. Change directory to the location of the batch files.
5. Run the batch file to import the tablespace using this syntax:

```
attach_planner.bat <Oracle_dir> <E1_install_dir>
```

where <Oracle_dir> is the parent of the **E1Local** directory.

For example:

```
attach_planner.bat c:\Oracle c:\JDEdwards\E910
```

Note: This import batch file for the local metadata repository is in the spec directory:

```
attach_metadata.bat
```

3.11.5.11.2 Export Tablespace Script (detach_planner.bat) To use the export tablespace script:

1. Edit the jdedwards\E910\planner\data\detach_planner.bat file such that any tablespaces that you do not intend to import are commented out. These lines start with:

```
call %DATA_PATH%\EXPORT_TABLESPACE.BAT
```

2. Open a command prompt window by right-clicking on a Command Prompt shortcut and selecting **Run as administrator**.
3. Change directory to the location of the batch files.

4. Run the batch file to import the tablespace using this syntax:

```
detach_planner.bat <Oracle_dir> <E1_install_dir>
```

where <Oracle_dir> is the parent of the **E1Local** directory.

For example:

```
detach_planner.bat c:\Oracle c:\JDEdwards\E910
```

Note: This export batch file for the local metadata repository is in the spec directory:

```
detach_metadata.bat
```

3.11.5.12 Updating the InstallManager.htm File

To install a database or the Development Client onto a Development Client machine, the user runs this program:

```
\\<deployment server name>\<release>\OneWorld Client  
Install\InstallManager.exe
```

This program displays a Graphical User Interface that provides several options for the user to perform. The options that InstallManager.exe displays are read from the file InstallManager.htm that resides in the same directory as InstallManager.exe.

The JD Edwards EnterpriseOne administrator can edit this file to rename the options or to add new options. Instructions are inside the file.

Caution: Although InstallManager.htm is in HTML format, it is a restricted HTML that the InstallManager.exe can read. Some text file editing programs add extraneous HTML tags that InstallManager.exe cannot recognize.

The Microsoft Windows program Notepad.exe is an example of a program that is known to not add these extra tags, making it safe to use. Before you make any changes to the file, it is good practice to save a copy in case any changes that you make are not recognized by InstallManager.exe when it reads it.

Note that the installation path of the Development Client's installer (setup.exe) changed with Tools Release 9.1. This means that you will need to change the path of the Development Client's installer in the InstallManager.htm when you first install Tools Release 9.1 onto a Deployment Server that has a tools release prior to 9.1 installed.

The following is an example of a line in a pre-9.1 InstallManager.htm that creates the link to install the Development Client (this should be on a single line):

```
<a class="sectionItem" id="LaunchLink" link="setup.exe"  
href="InstallManager.htm">EnterpriseOne Client</a>
```

The Development Client's installer prior to Tools Release 9.1 is called setup.exe. It should be in the same directory as InstallManager.exe and InstallManager.htm. The value of the link in the above line should be a path and executable for the installer. If a relative path is used (for example, the path starts with neither a drive letter followed by a colon nor a backslash), the path is relative to the location of InstallManager.exe. If no path is given, Setup.exe and InstallManager.exe are in the same directory.

Here is an example of a similar line for Tools Release 9.1 (this should be on a single line):

```
<a class="sectionItem" id="LaunchLink" link="install\setup.exe"
href="InstallManager.htm">EnterpriseOne Client</a>
```

Note the addition of this relative path: `install`. With Tools Release 9.1, the Development Client's installer (which, is also called `setup.exe`) is now located in a subdirectory called `install` under the path where `InstallManager.exe` resides.

3.11.5.13 Deployment.inf and <Package_name>.inf

The following lists specific settings within the `Deployment.inf` and `<Package_name>.inf` for OEE.

- `Deployment.inf`

```
[ThirdPartyApps]
ORACLE=ThirdParty\ORACLE\OEESetup.exe,
```
- `<Package_name>.inf` (example from a DV910FA.inf file)

```
[Oracle Databases]
JDELocal_DV910=ORACLE
SPEC_DV910FA=ORACLE

[JDELocal_DV910]
SourceTableSpace=JDELocal
Server=127.0.0.1
UserID=SYSTEM
DataFileDestDir=$DDV910DATA\JDELocal_DV910.dbf
DumpFileDestDir=$DDV910DATA\JDELocal_DV910.dmp

[SPEC_DV910FA]
SourceTableSpace=SPEC_DV910FA
Server=127.0.0.1
UserID=SYSTEM
DataFileDestDir=$DDV910\Spec\SPEC_DV910FA.dbf
LogFileDestDir=$DDV910\Spec\SPEC_DV910FA.dmp
```

Working with the Platform Pack on the IBM i

This chapter discusses:

- [Section 4.1, "Understanding the Platform Pack"](#)
- [Section 4.2, "Platform Pack Process Flow"](#)
- [Section 4.3, "Configuring the Enterprise Server Prior to Installing the Platform Pack"](#)
- [Section 4.4, "Understanding the Platform Pack Installation on the IBM i"](#)
- [Section 4.5, "Running the JD Edwards EnterpriseOne Platform Pack Installer for the IBM i"](#)
- [Section 4.6, "Troubleshooting the IBM i Platform Pack Installation"](#)
- [Section 4.7, "Rerunning the JD Edwards EnterpriseOne Platform Pack Installer"](#)
- [Section 4.8, "Installing the Latest Tools Release and Latest Tools Release Patch to the Enterprise Server"](#)
- [Section 4.9, "Working with Database Security"](#)

4.1 Understanding the Platform Pack

The Platform Pack installs these major components:

- JD Edwards EnterpriseOne Server code
- JD Edwards EnterpriseOne database tables

Note: To reinstall any Enterprise Server components, refer to [Section 4.7, "Rerunning the JD Edwards EnterpriseOne Platform Pack Installer"](#).

This table lists the mandatory and optional components of the Platform Pack installation:


Server	Mandatory Component	Optional Components
Enterprise Server	JD Edwards EnterpriseOne Foundation	ES Production ES Prototype ES Development ES Pristine

Server	Mandatory Component	Optional Components
Database Server	System Database	Production Databases Prototype Databases Development Databases Pristine Databases

4.2 Platform Pack Process Flow

The Platform Pack installation process upgrades Release 9.1 system and path code files.

The diagram below illustrates the process flow for the Oracle Universal Installer for the JD Edwards EnterpriseOne Platform Pack.



4.3 Configuring the Enterprise Server Prior to Installing the Platform Pack

Install any IBM i server upgrades that are required to support Release 9.1.

Before you install Release 9.1 software on the Microsoft Windows Enterprise Server, you must create the Release 9.1 administrator user, verify disk space, and set up and verify the hosts file.

This section discusses:

- [Section 4.3.1, "Understanding the Prerequisites"](#)
- [Section 4.3.2, "Understanding Security for the Platform Pack Installer"](#)
- [Section 4.3.3, "Setting the System Values"](#)

- [Section 4.3.4, "Setting up the TCP/IP Protocol for Enterprise Server"](#)
- [Section 4.3.5, "Setting up IBM i Access on your Enterprise Server"](#)
- [Section 4.3.6, "Starting the Remote Database TCP/IP Service \(Optional\)"](#)
- [Section 4.3.7, "Optimizing Machine Resources"](#)
- [Section 4.3.8, "Cleaning Up From Prior Installations"](#)
- [Section 4.3.9, "Testing Long File Names on the IBM i"](#)
- [Section 4.3.10, "Checking for Co-existence Tables"](#)
- [Section 4.3.11, "Adding Entries to the System Reply List"](#)
- [Section 4.3.12, "Rebuilding Cross Reference Tables on the IBM i"](#)

4.3.1 Understanding the Prerequisites

Verify this list of prerequisites is met prior to installing the JD Edwards EnterpriseOne Platform Pack on your IBM i-based Enterprise Server:

- Refer to the [Language Process Overview](#) for the National Language Support tables and other information related to multilingual installations.
- Install the requisite IBM i upgrades.
- Verify that you have met the hardware and software requirements for the Release 9.1 release you are installing. See *Release 9.1 Hardware and Software Requirements*.
- If you prefer to perform the configuration tasks in this chapter (set up TCP/IP and IBM i Access) in a language other than the language for which the IBM i is currently configured, change the value for the code character set ID. For example, to perform these configuration tasks in English, set the code character set ID to 37. After completing these configuration tasks, reset the code character set ID to its original value.

4.3.2 Understanding Security for the Platform Pack Installer

The following is a list of security actions performed by the JD Edwards EnterpriseOne Installer:

1. Recreates the ONEWORLD job description.
2. Creates the user profiles for JDE and ONEWORLD, each with user class *PGMR.
3. Grants the JDE user rights to the ONEWORLD user profile.
4. Grant rights to QRECOVERY library for users JDE and ONEWORLD so that they can create SQL Packages in there for UBEs and CALLOBJ kernels.
5. If the PSFT user profile exists, for each environment that you are upgrading, uses GRTOBJAUT to grant authority for all tables in business data and control tables for JDE.

4.3.3 Setting the System Values

Because the JD Edwards EnterpriseOne Platform Pack Installer cannot run with the default QJOBMSGQFL system value, you may need to change it.

To verify the existing QJOBMSGQFL system value, and change if necessary:

1. Enter this command:

```
WRKSYSVAL QJOBMSGQFL
```

2. Enter option 5.

If the value displayed is *NOWRAP, you must change it to *WRAP or *PRTWRAP. Be sure to note the existing value so you can reset it after you complete the JD Edwards EnterpriseOne Platform Pack installation.

To allow the JD Edwards EnterpriseOne services to run, you must change the value for QUSEADPAUT to *NONE before installing the Enterprise Services. Then once the JD Edwards EnterpriseOne Platform Pack installation is complete, you can change this value back to its original setting.

To set the system values:

1. Enter this command:

```
WRKSYSVAL QUSEADPAUT
```

2. Enter option 5.

If the value displayed is anything other than *NONE, you must change from that value to *NONE. Be sure and note the existing value so you can reset it after you complete the installation of the JD Edwards EnterpriseOne Platform Pack.

4.3.4 Setting up the TCP/IP Protocol for Enterprise Server

Note: Set up the TCP/IP service to start automatically each time you IPL the IBM i. For more information about setting it up, contact your system administrator or see the appropriate IBM documentation.

To set up the TCP/IP protocol for your IBM i Enterprise Server:

1. Log on to the Enterprise Server as QSECOFR (or as any user who can access the Configure TCP/IP menu).
2. On Current OneWorld Versions, choose the version of the software for which you are setting up the TCP/IP protocol.
3. To access the Configure TCP/IP menu, enter CFGTCP.
4. Select Work With TCP/IP Host Table Entries.
5. On Work With TCP/IP Host Table Entries, find the network (Internet) address for the Enterprise Server.

A single machine could have more than one entry for the same network address. Verify that an entry exists for the Enterprise Server network address and that it matches the format that follows. Search for the Enterprise Server network address by entering the Enterprise Server name only (for example, SYS1). If one does not exist, you must add one by choosing Add.

In the Host Name field, your Enterprise Server (machine) name should appear in this format:

```
hostname.domainname
```

where `hostname` is the name of your machine and `domainname` is the local domain of the machine on the network. For example, `SYS1.MFG.ABC.COM`, in which `SYS1` is the Enterprise Server name and `MFG.ABC.COM` is the domain name. The combined

Enterprise Server name and local domain name represent the location of the Enterprise Server on the network.

Note: *Network Considerations.* To avoid problems when applications running on separate machines need to communicate with applications running on other machines on the same network, make sure that each machine name (host name) has a single unique dot decimal address. For example, SYS1 could have a dot decimal address of, for instance, 140.252.13.33, but you could not assign any other address to it.

6. To verify that the local domain and Enterprise Server names represent the correct location of the IBM i, choose Change Local Domain and Host Names from the Work With TCP/IP Host Table Entries form.

Verify that the Local Domain Name and Local Host Name fields match the combined `hostname.domainname` network address.

Following the example in this task, the local domain name would be `MFG.ABC.COM` and the local host name would be `SYS1`.

4.3.5 Setting up IBM i Access on your Enterprise Server

The IBM i Access terminal emulation program enables workstations to communicate with IBM i servers. This task describes the procedure to set up the component of IBM i Access that runs on the IBM i server.

To set up IBM i Access on your JD Edwards EnterpriseOne Enterprise Server:

1. To determine the number of prestart jobs that are available and have been submitted for program QZDASOINIT, enter this command:

```
DSPACTPJ QUSRWRK QSYS\QZDASOINIT
```

Information about the number of your system's prestart jobs, prestart jobs submitted, and program start requests appears.

The number of prestart jobs depends on the number of concurrent and active ODBC user connections. This change is iterative as users or applications are added or removed. If you do not have enough prestart jobs, your system could be slow to make connections. If connections fail, they could be successful with the second attempt. If too many prestart jobs are waiting, the system will end some of them automatically. Also, the system initiates prestart jobs as additional ones are submitted.

Note: *Troubleshooting.* To determine the number of prestart jobs you should set up, be aware that each OneWorld user typically uses three to five ODBC connections. Each ODBC connection uses one QZDASOINIT program. Therefore, the initial value for QZDASOINIT could be set to four times the number of expected concurrent connected users.

The current maximum number of prestart jobs is 9,999. If more jobs are needed, they will be created as necessary.

2. To see the current settings, enter this command:

```
DSPSBSD QUSRWRK
```

3. Choose option 10, and then choose option 5 for program QSYS\QZDASOINIT.
4. To access the form on which you can change the number of prestart jobs, enter this command and press F4 to prompt:
`CHGPJE`
5. Change the number of prestart jobs as needed, and then press Enter.
6. Restart the QUSRWRK subsystem for your changes to take effect.

4.3.6 Starting the Remote Database TCP/IP Service (Optional)

If your installation will have separate IBM i machines for the Enterprise Server and the Data Server, you will need to start the remote database TCP/IP service on the Enterprise Server.

To start the remote database TCP/IP service:

1. Enter this command:
`STRTCPSVR SERVER(*EDRSQL)`
2. In order to change the attribute of this server to autostart when TCP/IP starts, you will need to use IBM i Navigator from a Microsoft Windows client:
 1. Open the node for your IBM i machine.
 2. Open the Network node.
 3. Open the Servers node.
 4. Double click on TCP/IP.
A list of TCP/IP servers is displayed in the right hand pane.
 5. Right click on EDRSQL, select Properties, and enable the option *Start when TCP/IP Starts*.

Tip: You can also start and stop this server from this screen.

4.3.7 Optimizing Machine Resources

Ideally you should run the Platform Pack Installer when the machine is not busy. However, if there are other processes running on the same IBM i as the Installer, their performance will be impacted by the Platform Pack installation.

The Platform pack install uses a prestart job in the QUSRWRK subsystem (program QZRCSRVS) which does Restores. This job runs at priority 20. In order to reduce the performance impact of this job, you can change its run priority during the install.

To change the run priority of the install job running in the QUSRWRK subsystem and optimize machine resources:

1. Enter this command:
`WRKACTJOB SBS(QUSRWRK)`
2. Look for the job running program QZRCSRVS, type option 5 next to it, and press Enter.

If there is more than one job running QZRCSRVS, the one using the most machine resources is most likely the one running the Platform Pack Installer. You can also check the job logs to find jobs unique to the Platform Pack Installer. Examples of such jobs are restores and CHGOBJOWN.

3. For the job you selected in the previous step, enter option 40 (change job) press Enter.
4. Enter 51 as the Run Priority and press Enter.

4.3.8 Cleaning Up From Prior Installations

If you have previously run the Platform Pack installer on your IBM i machine, prior to re-running it you must ensure that all QACX ' files are cleared from this folder:

\tmp\

4.3.9 Testing Long File Names on the IBM i

Before running Installation Workbench, you may need to rebuild the cross-reference table. This table enables tables of long (more than 10 characters) file names to be created on the IBM i. Rebuilding the table causes your system to be in a restrictive state. Coordinate this activity with the system administrator.

To test long file names on the IBM i:

1. Log on to the IBM i as QSECOFR.
2. On the command line, enter STRSQL.

This command will start a SQL session on the IBM i.

3. To test a long file name, enter this SQL statement:

```
CREATE TABLE QGPL\LONGFILENAME (FIELD CHAR(10))
```

where *LONGFILENAME* is the name of your file.

Your system is ready if the file is created in the QGPL library. You can ignore the journal setting.

4. To remove the file that you just created in the QGPL library, enter the following SQL statement:

```
DROP TABLE QGPL\LONGFILENAME
```

Note: If you are unable to create the table with a long name, likely your system cross reference tables are corrupt. You must rebuild them before proceeding. Refer to [Rebuilding Cross Reference Tables on the IBM i](#).

4.3.10 Checking for Co-existence Tables

Before running the Table Conversion Workbench, you must check whether any of your tables are in Co-Existence (DDS) format. If you run Table Conversions against DDS format tables it will lead to data corruption and cause TCs to fail.

Use this procedure to check for co-existence tables:

1. Log on to the IBM i as QSECOFR.
2. On the command line, start a SQL session by entering this command:

```
STRSQL
```

3. Run the following SQL statement, substituting in your Control Tables and Business Data library names

```
SELECT TABLE_SCHEMA, TABLE_NAME, TABLE_TYPE FROM SYSTABLES WHERE TABLE_SCHEMA
```

```
IN ('PRODCCTL','PRODDTA') AND TABLE_TYPE = 'P'
```

where

TABLE_TYPE='P' is DDS (World-created) tables

TABLE_TYPE='T' is SQL (EnterpriseOne created) tables

If there are DDS created tables in these libraries, you must follow the additional procedures in the Co-Existence Upgrade Guide (Doc ID: 702770.1), which is located on My Oracle Support at this link:

<https://support.us.oracle.com/oip/faces/secure/km/DocumentDisplay.jspx?id=702770.1>

4.3.11 Adding Entries to the System Reply List

To add entries to the System Reply List:

1. Verify the existing entries in the Reply List with this command:

```
WRKRPYLE
```

2. Verify that this entry does not exist and that the sequence number 3283 has not been used:

```
ADDRPYLE SEQNBR(3283) MSGID(CPA32B2) RPY('I')
```

3. If the above entry does not exist, you can add it using this command:

```
ADDRPYLE SEQNBR(3283) MSGID(CPA32B2) RPY('I')
```

4.3.12 Rebuilding Cross Reference Tables on the IBM i

To rebuild cross reference tables on the IBM i:

1. Stop all subsystems using this command:

```
ENDSBS *ALL *IMMED
```

2. After the jobs have successfully stopped, run the following command:

```
RCLSTG SELECT(*DBXREF)
```

Note that this command may run for as much as several hours.

3. Restart all subsystems using this command:

```
STRSBS QCTL
```

The cross-reference table is now rebuilt and ready for use.

4.4 Understanding the Platform Pack Installation on the IBM i

The Platform Pack installation process installs Release 9.1 system and database files on the IBM i. The Platform Pack installer does not run on the IBM i machine; it can only run on a Microsoft Windows machine. Oracle recommends that you run the installer from the JD Edwards EnterpriseOne Deployment Server so that the Oracle Inventory and install history will be preserved. As a prerequisite to running the installer, IBM i Access for Windows must be installed on the Deployment Server.

Caution: In some cases the JDEOW library may not be properly updated with the new JD Edwards EnterpriseOne programs as expected during the JD Edwards EnterpriseOne Upgrade process. To ensure the new JD Edwards EnterpriseOne programs are properly installed, rename your existing JDEOW library prior to running the JD Edwards EnterpriseOne Platform Pack Installer.

To rename JDEOW, run the following command while signed onto your IBM i JD Edwards EnterpriseOne server:

```
RNMOBJ OBJ(QSYS\JDEOW) OBJTYPE(*LIB) NEWOBJ(JDEOW_SAVE)
```

Note: If you are installing any JD Edwards EnterpriseOne component on multiple IBM i machines (for example, if you are installing multiple logic servers), you must run the Platform Pack installer from a different Microsoft Windows machine for each separate machine you install. Otherwise, the installer detects that some components (for example Foundation for a logic server) have already been installed, and by design ignores subsequent requests to install the same component, regardless of whether the installation is intended for a different target machine.

4.5 Running the JD Edwards EnterpriseOne Platform Pack Installer for the IBM i

The user profile you specify during the Platform Pack install must not be limited by network security. Most of the Platform Pack install is done through commands and JAVA code that uses TCP/IP to send work between various OS/400 service jobs. To find out whether there are network security limitations in place:

1. Enter the WRKREGINF command.
2. Page down to the QIBM_QZ* entries which are for the IBM i Access Host Servers.
3. Use Option 8 on any of these to see if an exit program is in place.

In addition, a Platform Pack installer failure can occur if any of the RSTxxx commands have been changed from the IBM defaults relative to the environments in which they can run.

To run the JD Edwards EnterpriseOne Platform Pack Installer for the IBM i Enterprise Server:

1. Log on to the Microsoft Windows machine where you will be running the Platform Pack installer for IBM i. If you follow the recommendation, this will be the JD Edwards EnterpriseOne Deployment Server.

Caution: Ensure that the Administrator account name that you use does not contain any special characters.

2. Create a folder into which you will copy the two .zip files that comprise the Platform Pack image. For example, the folder might be named:


```
c:\IBMPPack
```

3. Extract the two zip files within the root of the folder created above. Using the example in this guide, a **correctly** extracted structure is:





4. Locate the `jt400.jar` and `util400.jar` from the location where you installed IBM i Access for Windows. For example, the location might be:
`c:\Program Files\IBM\Client Access\jt400\lib`
5. Copy these two `.jar` files to this structure in your install image:
`..\stage\ext\jlib`
6. In the above extracted structure, locate the `setup.exe` file under the `\install` subdirectory, right-click on it, and select **Run as Administrator**.

Note: The Oracle Universal Installer takes a few minutes to start up.



7. On Welcome, click the **Next** button.





8. On Select Installation Type, choose your installation type:

- *Typical*

Choose this setup type if you wish to complete the Platform Pack installation with no further specifications. This installation option is recommended for most users and includes the required JD Edwards EnterpriseOne files for the Prototype and Pristine environments.

- *Custom*

This mode is recommended for experienced users, choose this setup type if you wish to complete the Platform Pack installation by specifying the installation of a subset of pre-defined environments.

- *Custom*

In most cases this is the mode you should choose for Upgrades.

This mode is recommended for experienced users, choose this setup type if you wish to complete the Platform Pack installation by specifying the installation of a subset of pre-defined environments.

Tip: If you choose Custom installation, continue with the steps below in this task which immediately follow.

- *Typical*

Choose this setup type if you wish to complete the Platform Pack installation with no further specifications. This installation option includes the required JD Edwards EnterpriseOne files for the Prototype and Pristine environments.

- Click the **Next** button.

9. On Specify Home Details, complete these fields:

- *Name*

Enter a unique name for the JD Edwards EnterpriseOne Platform Pack installation. For example:

JDE_PPack910_HOME

By default, the installer populates the values on this screen with _1 suffix. The _1 suffix can be removed, if desired. The actual value between Name and Path need not be consistent. It is only used by the Oracle Universal Installer.

If desired, change the install location from the c: drive. During the installation process itself, only a small amount of disk space is required on the Microsoft Windows machine for the Oracle Inventory for this install and a few temporary text files like jde.ini.

- *Path*


Enter the drive and directory where you want the files installed on your Enterprise Server. For example:

Z:\JDEdwardsPPack\E910


10. Click the **Next** button.

If you chose the **Typical** installation type, the Available Products screen will **not** display; you can skip to the Step 12.

If you chose the **Custom** installation type, the Oracle Universal Installer displays a list of available JD Edwards EnterpriseOne product components, as shown in the example below:



Tip: Use the scroll bar to on the right hand side of the screen to view the complete list of available components. This is shown in the following screen sample.



On Available Product Components, select from these choices:

JD Edwards EnterpriseOne Database Server

- System Database

Note: This selection includes mandatory system files. If you do not select this box, the JD Edwards EnterpriseOne Platform Pack Installer will select this component. Likewise, if you rerun the JD Edwards EnterpriseOne Platform Pack Installer to add an environment it will check to ensure that this component is already installed. Also if rerunning, you will not be given an option to install the environment in a different ORACLE_HOME.

- Production Databases
- Prototype Databases
- Development Databases
- Pristine Databases

JD Edwards EnterpriseOne Enterprise Server


- JD Edwards EnterpriseOne Foundation


Note: This selection includes system files. You must choose this feature for all initial installations of the Enterprise Server. If you do not select this feature, the JD Edwards EnterpriseOne Platform Pack Installer automatically selects it for installation.

- ES Production
- ES Prototype
- ES Development
- ES Pristine

Note: For Upgrades, you should always select the Pristine environment. Otherwise, Table Conversions may not process correctly.

11. After you have verified your selection of components, click the **Next** button.





12. On Would you like to Install or Upgrade EnterpriseOne?, choose whether you want to install or upgrade JD Edwards EnterpriseOne. The list below describes each run mode.

- *Install (Install EnterpriseOne)*

This selection installs Central Objects and Business Data / Control Tables for the selected environments.

Note that the installer checks for the existence of the Business Data and Control Tables libraries and will not proceed if any of these libraries already exist:

- DV910
- PD910
- PY910
- TESTDTA
- PRODDTA
- CRPDTA
- TESTCTL
- PRODCTL
- CRPCTL

- *Upgrade (Upgrade EnterpriseOne)*

In this mode, the JD Edwards EnterpriseOne Platform Pack Installer checks for the existence of the Business Data and Control Tables libraries which are prerequisites to an upgrade of JD Edwards EnterpriseOne.

Caution: You should always back up all databases that you want to preserve.

13. Click the **Next** button.

14. On IBM i Server and User Profile, complete these fields:

- *Server Name*

Enter the name of the IBM i machine.

- *IBM i User Profile*

Enter QSECOFR or another user on the host that has *ALLOBJ *SECADM *SAVSYS *IOSYSCFG *JOBCTL rights.

- *IBM i Password*

Enter the password for the User Profile above.

- *Enter Secure Password*

This password allows you to change the password for users created on the IBM i. The default creates user profiles with password = user (for example, JDE JDE). If this violates the password rules on your IBM i machine, supply a secure password that will pass your password rules, then change the INI files and change the JD Edwards EnterpriseOne security definitions using JD Edwards EnterpriseOne applications P980001 and P98OWSEC before starting services.

Leaving this as the default password, will allow the JD Edwards EnterpriseOne services to be started immediately after the installation.


- *Confirm Password*

Leave this as the default unless the Secure Password has been entered.

15. Click the **Next** button.

If the installer begins with no errors, you can proceed to the Step 16. Otherwise, refer to the next section of this guide entitled: [Section 4.6, "Troubleshooting the IBM i Platform Pack Installation"](#).


If all specified conditions are valid, the installer displays the Summary screen.




16. On Summary, in the top half of the screen review your selections and in the bottom half of the screen review the NOTES, which detail the disk space requirements for OUI support files and also for the Platform Pack being installed on the IBM i machine.

17. Click the **Install** button.

As the installer runs it displays the Install progress, as shown in the following example.



After the installation is complete, the following End of Installation screen is displayed.




18. On End of Installation, verify the installation of the EnterpriseOne Platform Pack was successful.

Review the **Please remember ...** portion for the installer log file location. The log file name is specified with the date and stamp when the installer ran. For example:

```
c:\Program Files (x86)\Oracle\Inventory\logs\installActions2011-09-14_03-40-11-PM.log
```

19. Click the **Exit** button to exit OUI.



20. On Exit, click the **Yes** button.

4.6 Troubleshooting the IBM i Platform Pack Installation

This section discusses these potential error or warning conditions and their probable causes and resolutions when running the JD Edwards EnterpriseOne Platform Pack Installer:

- [Section 4.6.1, "Invalid User or Password"](#)
- [Section 4.6.2, "Abnormal Program Termination - jt400.jar and/or util.jar Missing"](#)
- [Section 4.6.3, "Business Data or Control Tables Already Exist"](#)
- [Section 4.6.4, "Business Data or Control Tables Do Not Exist"](#)


4.6.1 Invalid User or Password

If you enter an invalid user or password, you will see the following screen pop up multiple times. At this point you should start the Windows Task Manager, find the OUI process (javaw.exe) and end it. Then start the installer again.




4.6.2 Abnormal Program Termination - jt400.jar and/or util.jar Missing

If you receive the following message, it indicates that you have failed to correctly copy the jt400.jar and util400.jar into the ..\stage\ext\jlib directory. To remedy, you must copy these files to the appropriate directory, exit from the installer, and restart the installer.



4.6.3 Business Data or Control Tables Already Exist

If you select Install Mode and the Business Data or Control Tables already exist, the installer displays the following error:




To remedy the above error, your choices are: must: or Deselect the Prototype Database or

- Change the Install Type to Upgrade
- Deselect the Prototype Database
- Delete the CRPDTA and CRPCTL library (if they are empty)

4.6.4 Business Data or Control Tables Do Not Exist

The following is displayed if you selected the Upgrade mode but the Business Data or Control Tables do not exist:



4.7 Rerunning the JD Edwards EnterpriseOne Platform Pack Installer

You must rerun the JD Edwards EnterpriseOne Platform Pack Installer to support these scenarios:

- You want to install the Enterprise Server and the Database Server on physically different machines.
- You want to add an Enterprise Server environment to the Enterprise Server.
- You want to add a Database Server database to the Database Server.
- You want to reinstall the JD Edwards EnterpriseOne Foundation on the Enterprise Server.
- You want to reinstall the System Database on the Database Server.

You should never reinstall any optional components without first uninstalling the components. If you select to uninstall the mandatory components you must also select to uninstall or have already uninstalled all related optional components. This table lists the mandatory and related optional components:

Server	Mandatory Component	Optional Components
Enterprise Server	JD Edwards EnterpriseOne Foundation	ES Production ES Prototype ES Development ES Pristine
Database Server	System Database	Production Databases Prototype Databases Development Databases Pristine Databases

4.7.1 Enterprise Server

If you are rerunning the JD Edwards EnterpriseOne Platform Pack Installer in order to add environments, you must specify the same DB2/400 instance as that which you selected for JD Edwards EnterpriseOne Foundation during the initial installation of the Platform Pack.

Note: If you are installing any JD Edwards EnterpriseOne component on multiple IBM i machines (for example, if you are installing multiple logic servers), you must run the Platform Pack installer from a different Microsoft Windows machine for each separate machine you install. Otherwise, the installer detects that some components (for example Foundation for a logic server) have already been installed, and by design ignores subsequent requests to install the same component, regardless of whether the installation is intended for a different target machine.

4.7.2 Database Server

If you are rerunning the JD Edwards EnterpriseOne Platform Pack Installer in order to add databases, you must specify the same DB2/400 instance as that which you selected for System Database during the initial installation of the Platform Pack.

4.8 Installing the Latest Tools Release and Latest Tools Release Patch to the Enterprise Server

Caution: The Tools Release level must match what was installed on the Deployment Server.

For instructions on installing the tools release, refer to *JD Edwards EnterpriseOne Tools Release 8.98 Installation Guide*, which is available by platform.

To install the latest tools release and latest tools release patch:

1. From the Update Center home page, download the latest Tools Release Patch (for example, 9.1.A1) and Tools Release documentation.
2. Using the Tools Release documentation, install the Tools Release Patch to the Enterprise Server.

4.9 Working with Database Security

The libraries and tables delivered by the Platform Pack installation are not secured. In order to provide sufficient security, you should run the tool SETOWAUT which allows you to 'lock down' libraries and IFS directories delivered by the Platform Pack installation. You can obtain the latest version of the SETOWAUT tool from the Update Center using the Change Assistant.

In order to maximize your database security, you should change the passwords on all table owners created during the Platform Pack installation; these are created with the user and password equal to the same value. Such a user and password relationship could expose you to worms and viruses aimed at gaining access to your database. Consult with your DBA for advice on changing passwords to meet the security requirements of your database installation.

The Installation Workbench assumes that the database user is JDE and that the password is the same, unless it finds this override in the `jde.ini` file on the Deployment Server. Once the database passwords have been changed, you will need to add this section to the `jde.ini` file:

```
[DSPWD]
JDE=new_password
```

For example, if you changed the password for JDE to `alaska5`, your section would look like this:

```
[DSPWD]
JDE=alaska5
```

Caution: The Installation Workbench can only process passwords equal to or less than 10 characters in length. Therefore, you cannot use passwords greater than 10 characters even if your RDMS allows it.

After you change the [DSPWD] section of the `jde.ini` file, logon to OneWorld in the JDEPLAN environment on the Deployment Server with the new password in the correct case.

Caution: Whenever you change the password on your database, as recommended for security purposes, you must also ensure that your security settings in the Enterprise Server `jde.ini` file match that of your database. Refer to [Chapter 12, "Working With Signon Security"](#) in this guide for applicable instructions.

You should secure the `jde.ini` file on the Deployment Server to prevent unauthorized access.

You should delete the [DSPWD] section once the install or upgrade is complete.

Note: If you are upgrading from JD Edwards EnterpriseOne Releases 8.10 or 8.11, you should consider disabling the legacy user, which is PSFT.

Working with the Installation Planner for an Upgrade

This chapter consists of the following topics:

- [Section 5.1, "Understanding the Planner Process for Upgrades"](#)
- [Section 5.2, "Working with JD Edwards EnterpriseOne Software Requirements"](#)
- [Section 5.3, "Reviewing Installation Planner Processing Options"](#)
- [Section 5.4, "Running the Installation Planner for an Upgrade"](#)
- [Section 5.5, "Deleting Machines from an Installation Plan"](#)
- [Section 5.6, "Verify and Configure Data Source for Previous Release"](#)

See Also

- A separate chapter in this guide entitled: [Chapter 19, "Creating a Remote Installation Plan"](#)
- A separate chapter in this guide entitled: [Chapter 20, "Adding a Server to an Existing Configuration"](#)
- A separate chapter in this guide entitled: [Chapter 21, "Creating a Language-Only Installation Plan"](#)

5.1 Understanding the Planner Process for Upgrades

Installation Planner is an Release 9.1 application that runs on the Deployment Server. It is a system administration tool that guides through the process of configuring the machines on which you will run Release 9.1.

This chapter contains the tasks for defining a custom installation plan. The information you provide on the Installation Planner forms, such as database type and Enterprise Server type, determines the information you see on the remaining forms. The Installation Planner processing options also affect which choices you are given while setting up your plan. For a complete description of the processing options, refer to [Section 5.3, "Reviewing Installation Planner Processing Options"](#).

Caution: To use Installation Planner remove machines from an existing installation plan, see [Section 5.5, "Deleting Machines from an Installation Plan"](#)

This chapter contains the following topics:

- [Section 5.1.1, "Dropping SQL Packages"](#)
- [Section 5.1.2, "Defining the SQL Package Creation Location"](#)
- [Section 5.1.3, "Assumptions about Mandatory Pre-Upgrade Process"](#)
- [Section 5.1.4, "Mandatory Pre-Upgrade Process - Upgrading the Pristine Environment"](#)
- [Section 5.1.5, "Running Table Conversions Locally"](#)
- [Section 5.1.6, "Deferring Index Builds \(Tools Release 9.1 Update 2\)"](#)

5.1.1 Dropping SQL Packages

When upgrading with IBM i data sources, the SQL packages must be dropped before starting the planner. The IBM i caches the table layout in the SQL package and does not look at what the current table layout is. If the SQL packages are not dropped, errors may occur in tables with changed formats.

To drop SQL packages:

1. Ensure that JD Edwards EnterpriseOne is shut down (or make sure that you have not attached to the IBM i yet).
2. On the IBM i, for each Business Data and Control Tables library, enter the following:

`WRKOBJ OBJ (xx*ALL) OBJTYPE (*SQLPKG) , where xx is your library`

or

`WRKOBJ OBJ (*ALLUSR*ALL) OBJTYPE (*SQLPKG) and choose your business data and control table libraries from the list.`
3. Type a 4 next to each of the packages, and press Enter.

5.1.2 Defining the SQL Package Creation Location

Verify the JDE.INI setting on the Enterprise Server that controls where SQL Packages are created. The applicable setting is:

```
[DB SYSTEM SETTINGS]
sqlPackageLibrary=value
```

where value must be set to 2 in order for Table Conversions to work correctly. Otherwise you will see Table Conversion failures. For an explanation of other values, refer to [Section 11.9, "UBE Performance ' SQL Package Location"](#) in the section of this guide entitled: [Example 11, "Performing Post Upgrade Tasks"](#).

5.1.3 Assumptions about Mandatory Pre-Upgrade Process

This table outlines the assumptions about the mandatory pre-upgrade process.

Personnel	Installer
Logon Status	On the Deployment Server, logged on to Release 9.1 as user JDE into either the JDEPLAN or DEP910 environment (each step will tell you which environment to use.)

Personnel	Installer
Prerequisites	Verify that the Deployment Server is installed and the latest Tools Release, Tools Release Patch, and Planner Update have been installed, in that order. Verify that the Pristine database is installed and the Pristine Central Objects loaded.
Concurrent Tasks	None.

5.1.4 Mandatory Pre-Upgrade Process - Upgrading the Pristine Environment

Due to the hundreds of table conversions, which will run during the upgrade process, the process has changed to run the table conversions on the server. The following process is necessary to run Table Conversions on the server.

Caution: The Pristine (PS910) environment must be installed prior to running Table Conversions. Each step must be completed and checked off in the exact order listed below.

- Create an Upgrade Plan for the Pristine (PS910) environment.
- Follow the steps in the [Section 5.4.1, "Starting Installation Planner"](#) section and create a plan for Pristine only.
- Run the Upgrade Plan just created for the Pristine (PS910) environment.

Note: Table Conversions will not run when upgrading the Pristine (PS910) environment.

The following steps may be completed while the Installation Workbench is running the Pristine (PS910) upgrade plan.

- Install the latest Tools Release and Tools Release Patch on the Enterprise server (the Tools Release level must match what was installed on the Deployment Server).

Note: This step may also be performed while the Installation Workbench is running.

- Ensure that JD Edwards EnterpriseOne services are up and running on the Enterprise server.

Note: Installation Workbench for the Pristine Environment must be completed before proceeding with following steps.

- Continue upgrading your desired environments.

5.1.5 Running Table Conversions Locally

The functionality to run the Table Conversions locally on the Deployment Server is still available, and works much as it did in previous releases. Run Table Conversions on the Enterprise Server in order to minimize Upgrade time.

If you choose to run your Table Conversions locally instead of on the Enterprise Server, some steps in the Mandatory Pre-Upgrade Procedure must still be completed before running the Installation Workbench. These are:

- Installing latest Tools Release
- Loading latest Planner Update

These steps are described in the [Section 5.1.4, "Mandatory Pre-Upgrade Process - Upgrading the Pristine Environment"](#).

5.1.6 Deferring Index Builds (Tools Release 9.1 Update 2)

Beginning with JD Edwards Tool Release 9.1 Update 2, if you want to defer index builds during the JD Edwards EnterpriseOne upgrade process, refer to the Chapter of this guide entitled: [Chapter 5, "Working with the Installation Planner for an Upgrade"](#) in the section of that chapter entitled: [Section 6.16.5, "Deferring Index Builds During Table Conversion Workbench \(Tools Release 9.1 Update 2\)"](#).

5.2 Working with JD Edwards EnterpriseOne Software Requirements

The goal of the JD Edwards EnterpriseOne Release 9.1 Installation is to include the most current tools releases and updates at the time the installation image is mastered. However, subsequent to that time it is possible that critical fixes may become necessary and available. You should check [Section 1.3.1, "Accessing Minimum Technical Requirements \(Certifications\)"](#) to verify if any such JD Edwards EnterpriseOne Release 9.1 Installation fixes are required.

5.3 Reviewing Installation Planner Processing Options

Processing options control how Installation Planner responds as you set up plans and options you see as you work through the custom planner. If processing options are not set up correctly, you will not see the appropriate options as you work through the planner. You set up these processing options to control replication functions and business functions mapping.

You should review the default processing options for the Installation Planner application prerequisite to create the plan. First-time users can set up the processing options to step through the planner with informational messages. If you do not want to see these messages, you can turn them off.

5.3.1 Assumptions About Reviewing Installation Planner Processing Options

This table lists the assumptions about reviewing the processing options for the installation planner.

Personnel	Installer
Logon Status	On the Deployment Server, logged on as user JDE with the database password for user JDE, in the Planner environment.
Prerequisites	The Deployment Server must be installed.
Concurrent Tasks	The Platform Pack installer can be running.

5.3.2 Accessing Processing Options

To access processing options, you must first log on to Release 9.1 and specify your installation plan type.

1. Log on to Release 9.1 as user JDE with the database password for user JDE.
2. Access the planner environment (JDEPLAN).
3. From the System Installation Tools menu (GH961), right-click either Typical Installation Plan or Custom Installation Plan.
4. Choose Prompt for Values.

The Processing Options form appears.

5.3.3 Choosing Processing Option Values

Once you have accessed processing options, perform the following tasks to choose the processing option values:

- [Section 5.3.3.1, "Specifying the Prompt Mode"](#)
- [Section 5.3.3.2, "Specifying the Process Mode"](#)
- [Section 5.3.3.3, "Specifying the Default Mode"](#)
- [Section 5.3.3.4, "Verifying Status Change Values Have Not Changed"](#)
- [Section 5.3.3.5, "Specifying Plan Completion Processes"](#)
- [Section 5.3.3.6, "Specifying Replication Options"](#)

5.3.3.1 Specifying the Prompt Mode

To specify the prompt mode:

1. Select the Prompt Mode tab.

Processing Options

Prompt Mode | **Process Mode** | **Default Mode** | **Status Ch:** ◀ ▶

Enter a '0' for Silent Mode. This mode will only show the data entry forms.
Enter a '1' for Additions Prompt Mode. This mode will prompt for the addition of multiple servers. This is the default mode.
Enter a '2' for Verbose mode. This Mode will direct you through the process with a series of Prompt forms.

Prompt Mode

OK **Help** **Cancel**

2. On the Prompt Mode tab, select a prompt mode:

Value	Model	Description
0	Silent	Installation Planner displays only the data entry forms.
1	Additions Prompt	Installation Planner prompts you to add servers.
2	Verbose	Installation Planner directs you through creating a plan with a series of prompting forms.

5.3.3.2 Specifying the Process Mode

To specify the process mode:

1. Select the Process Mode tab.

Processing Options

Prompt Mode **Process Mode** **Default Mode** **Status Ch:** ◀ ▶

Enter a '1' if you are adding servers to your existing setup. This will step through the process of adding different types of servers (Deployment, Enterprise, Data, JAS) to your existing configuration. Enter a '0' or leave blank if not adding servers to your existing setup. This is the default.

Additional Servers

This value must always be a '1' for the Installation process.

Installation

OK **Help** **Cancel**

2. On the Process Mode tab, select the options for the processes that you want to run when you create your plan:
 - *Additional Servers*
Enter 1 to add servers to your existing setup (Deployment Server, Enterprise Server, Database Server, HTML Web Server). Enter 0 or leave blank for regular plans.
Caution: You should only change this value when running a Server Plan.
 - *Installation*
Enter 1 to run the JD Edwards EnterpriseOne installation automatically.

5.3.3.3 Specifying the Default Mode

To specify the default mode:

1. Select the Default Mode tab.

Processing Options

Prompt Mode **Process Mode** **Default Mode** **Status Ch.**

Enter one of the following values for each default Options:
 '0' - Do not take defaults and do not prompt.
 '1' - Prompt for defaults option at runtime.
 '2' - Always take defaults without prompting. This is the default

Default Data Source Information: 1

Default Environments: 1

Default Data Load: 1

Default Advanced Parameters: 1

Default Languages: 1

OK Help Cancel

2. On the Default Mode tab, enter these values into the processing option fields:

Value	Description
0	Do not use default values and do not prompt.
1	Prompt for default options at run-time.
2	Default mode. Always use defaults without prompting.

- *Default Data Source Information*
Select whether you want the ability to modify data source information or just take the default values.
- *Default Environments*
Select whether you want the ability to select environments or take the default values.
- *Default Data Load*
Select whether you want the ability to modify data load parameters or take the default values.
- *Default Advanced Parameters*
Select whether you want the ability to modify advanced parameters or take the default values.
- *Default Languages*

Select whether you want the ability to select an alternate language or take the default values.

- *Upgrade/Update Plan Generation*

Select whether you want the ability to generate a plan automatically from locations and machines defined in a previous version of the software.

5.3.3.4 Verifying Status Change Values Have Not Changed

On the Status Change tab, this tab form appears.

Note: Do not make any changes on this tab. These values are hard coded in the application

Processing Options

Process Mode | Default Mode | **Status Change** | Completi

Enter the Detail Status for the line to be changed to when the following actions are taken:

Mark as Complete must always be 60	<input type="text" value="60"/>
Disable	<input type="text" value="70"/>
Enable	<input type="text" value="10"/>

5.3.3.5 Specifying Plan Completion Processes

To specify plan completion processes:

1. Select the Completion tab.

Processing Options

Default Mode | Status Change | Completion | Replication

After defining a plan, there are several processes which can be run. For each of the processes, enter one of the following values:
 '0' - Do not automatically run.
 '1' - Prompt to be run.
 '2' - Run automatically

Finalize Plan. The default for this process is '2' to run automatically.

Validate Plan. The default for this process is '2' to run automatically.

- On the Completion tab, complete the fields using these values:

After defining the plan, the options on this tab specify which processes are run. one of the following values:

Value	Description
0	Do not run automatically.
1	Prompt to be run.
2	Run automatically.

- *Finalize Plan*
Enter the default option 2 to run automatically.
- *Validate Plan*
Enter the default option 2 to run automatically.

5.3.3.6 Specifying Replication Options

To specify replication options:

- Select the Replication tab.

Processing Options

Status Change **Completion** **Replication** **Packages**

Enter one of the following values for each remote location option:
 '0' - Do not use and do not prompt.
 '1' - Prompt for option at runtime.
 '2' - Always use without prompting. This is the default.

Replicate System Tables

Replicate Data Dictionary Tables

Replicate Control Tables

Replicate Constant Tables

Replicate Master Tables

2. On the Replication tab, complete the fields using these values:

Value	Description
0	Do not use and do not prompt.
1	Prompt for option at run-time.
2	Always use without prompting .

- *Replicate System Tables*
Select whether you have the option to replicate system tables automatically for remote locations.
- *Replicate Data Dictionary Tables*
Select whether you have the option to replicate data dictionary tables automatically for remote locations.
- *Replicate Control Tables*
Select whether you have the option to replicate control tables, menus, and user defined codes automatically for remote locations.
- *Replicate Constant Tables*
Select whether you have the option to replicate constant tables automatically for remote locations. Business data tables are Object Librarian type 280.
- *Replicate Master Tables*

Select whether you have the option to replicate master tables automatically for remote locations. Business data tables are Object Librarian type 210 and 211.

5.4 Running the Installation Planner for an Upgrade

This section consists of the following tasks:

- [Section 5.4.1, "Starting Installation Planner"](#)
- [Section 5.4.2, "Entering a Plan Description"](#)
- [Section 5.4.3, "Entering Location Information"](#)
- [Section 5.4.4, "Entering Deployment Server Information"](#)
- [Section 5.4.5, "Entering Enterprise Server Information"](#)
- [Section 5.4.6, "Enter Data Source Information for Server Map"](#)
- [Section 5.4.7, "Entering HTML Web Server Information"](#)
- [Section 5.4.8, "Entering Data Server Information"](#)
- [Section 5.4.9, "Entering Shared Data Source Information"](#)
- [Section 5.4.10, "Setting Up Environments"](#)
- [Section 5.4.11, "Setting Up Environment Data Sources"](#)
- [Section 5.4.12, "Adding a Remote Location"](#)
- [Section 5.4.13, "Finalizing the Installation Plan"](#)
- [Section 5.4.14, "Concluding the Validation Planner Report"](#)
- [Section 5.4.15, "Resetting the jde.ini Prior to Running Table Conversions"](#)
- [Section 5.4.16, "Clearing SQL Packages from QRECOVERY"](#)

5.4.1 Starting Installation Planner

To start Installation Planner from within JD Edwards EnterpriseOne:

1. Go to the System Installation Tools Menu (GH961).
2. From the System Installation Tools menu, double-click Custom Installation Plan.
3. On Work with Installation Plans, click Add.

The Installation Planner form appears. Enter a Plan description.

5.4.2 Entering a Plan Description

To enter a plan description:

Custom Installation Plan - [Installation Planner]

File Edit Preferences Form Window Help

OK Cancel Dismiss Apply Links Deplo... OLE ... Internet

Plan Information:

Name: UPGRADE

Description: Upgrade Installation Plan

Status: 10 In Planning

Install Type:

☐ Install ☒ Upgrade ☐ Software Update (ASU/ESU)

Release:

From Release: B7333 To Release: E910

Table Conversion Properties:

☐ Run TC on Deployment Server ☐ Tracing

1. On Installation Planner, complete the following fields:

Field	Description
Name	Enter the name of your plan.
Description	Enter the description of your plan.
Status	Select 10. This is the default value.
Install Type	<p>Select Upgrade.</p> <p>If the Installation Planner detects registry settings indicating a previous installation of JD Edwards EnterpriseOne has been installed on this Deployment Server, it automatically changes the Install Type to Upgrade. You can also manually change the Install Type to Upgrade.</p> <p>If the previous installation of the Deployment Server is on a different machine, or if this installation is on a remote Deployment Server, the Install Type will be set to Install. In either of these cases, you must manually change the Install Type to Upgrade and the Installation Planner will prompt you for the data source information in a subsequent screen.</p>
From Release	<p>Enter the number of the release you are upgrading from.</p> <p>For example, enter E910 for Release 9.1.</p>
To Release	Verify that the release number is E910 (the default value).
Table Conversion Properties	Check box to run table conversions on the Deployment Server. The default is to run on the Enterprise Server.
Tracing	Turns on debug logging.

Field	Description
Include Languages	This is an optional selection that is only available if you have previously specified this Custom plan to install languages. Select yes if you are installing an alternate language.

- Click OK.

Note: If you are installing the Deployment Server on the same machine as a previous release, and the Installation Planner has detected that previous release, you can proceed to the next step.

However, if you manually changed the Install Type to Upgrade, most likely because the previous release of JD Edwards EnterpriseOne was installed on a different machine, or this installation is on a remote, Deployment Server, you will be presented with the following screen in which you must enter the data source information that will enable the Installation Planner to locate the previous release.


The screenshot shows the 'Database Data Sources - [Data Source Revisions]' window. The 'Data Source Name' is 'System - 910'. 'Data Source Use' is 'DB'. 'Data Source Type' is 'I' (DB2 UDB on OS/400). 'Data Class' is 'S' (System). 'Platform' is 'AS400' (IBM AS/400 (CISC)). 'Database Server Name' is 'TITANIC'. The 'DB2 OS/400' tab is selected, showing 'Library Name' as 'SY910' and 'ODBC Data Source Name' as 'System - 910'.

On Data Source Revisions, complete the following fields:


Field	Description
Data Source Name	Enter the name of the System data source to be upgraded. For example: System - 910
Data Source Use	You can accept the default value of DB.

Field	Description
Data Source Type	Choose the type of data source. Valid value is: I - IBM i
Platform	Enter your platform. For example, AS400.
Database Server Name	Enter the name of your database server on which your previous System data source resides.
Library Name	Enter the Library Name.
ODBC Data Source Name	Enter the ODBC data source name.

3. Click OK.



4. This form imports information from your previous system data source. The previous system data source you are upgrading from should be prepopulated. Use the Data Sources form exit to verify the data source is set up correctly.
5. If this is correct, click OK and proceed to step 9. For more control over the process, click the Advanced form exit and continue with the next step. This screen sets up to copy information from the previous system data source into planner while providing some default information for the user. It is also used for spec merge and table conversions to provide access to the previous environments.




Note: The Release Master checkbox may not be selected, but the release master has already been copied at this point in the process.

6. Select the objects to be copied from the previous release, then specify the data source where each of the objects reside.
7. Select the appropriate radio button for your data load:

Radio Button	Description
Append	Adds records to your existing tables. This is the typical selection.
Replace	Clears existing tables prior to loading new data.

8. Click OK.
9. Select one of the following options:



Note: The above screen may not always appear for upgrades, which is preferable because the recommended method is to step through the planner rather than taking defaults. See ["Caution When Choosing Take Defaults"](#) below.

- From this form, you have the option to automatically enter the locations and machines into the plan that you defined in the previous version of the software.

10. Choose a method for generating your plan:

- To manually create your plan, click OK and continue with [Section 5.4.3, "Entering Location Information"](#).
- To enable the system to automatically enter the locations and machines from the previous version, click Take Defaults.

The machines that were imported from the previous system data source are entered into the current plan. Skip the sections on entering locations, Deployment Servers, Enterprise Servers, and machines or servers, and continue with [Section 5.4.9, "Entering Shared Data Source Information"](#).

Caution When Choosing Take Defaults

In order to ensure the validity of all subsequent plan information, it is strongly recommended that even advanced users should not choose this Take Defaults option. Instead, you should step through plan and verify that the Planner is populating information exactly as you expect to match your requirements.

- To exit the plan, click Cancel.

5.4.3 Entering Location Information

A location groups related Deployment Servers for use in a multi-tier environment.

To enter location information:

1. On Location Revisions, complete these fields:


Field	Description
<i>Location</i>	Enter the location to which this plan applies; the location can be a city, company headquarters, or a division of the company.
<i>Description</i>	Enter a description for this location.
<i>Location Code</i>	If this is the base location, this field is only available when you are adding the base location. If you are editing an existing base location, the field is unavailable.
<i>Parent Location</i>	If this is the base location, this field is only available when you are adding the base location. If you are editing an existing base location, the field is unavailable.

2. Click OK.


5.4.4 Entering Deployment Server Information

Once a plan location is specified, specify the information for the primary Deployment Server you will use in this plan. While Release 9.1 enables more than one Deployment Server to be defined, only the primary Deployment Server is defined at this time. You can choose a primary Deployment Server from the list of existing servers or you can enter information for a new server.

Note: If you installed JD EnterpriseOne Files to a remote Deployment Server, you should click the OK button to define a new Deployment Server. The deployment server name is the remote machine name by default.



1. On Deployment Server, click OK to define a new Deployment Server, or click Select to choose from a list of existing Deployment Servers.



If you choose Select, you are presented with the Machine Search table, from which you can make your selection.

The screenshot shows a software configuration window titled "Custom Installation Plan - [Deployment Server Revisions]". It has a menu bar (File, Edit, Preferences, Form, Window, Help) and a toolbar with icons for OK, Cancel, Dismiss, and Apply. Below the toolbar are several tabs: Workstation, Deployment (selected), Enterprise, Data, JAS, VMS, Crystal, and CWS. The main area contains several input fields: Machine Usage (15), Machine Name (DEPLOY), Description (Deployment Server), Release (E910), Host Type (50), Location (Denver), and Primary User (JDE). Below the tabs, there are two more fields: Primary Deployment Server (1) and Server Share Path (\\E910).

2. On Deployment Server Revisions, complete or verify these fields:

Field	Description
<i>Machine Usage</i>	Displays the value 15 by default to indicate that this is a Deployment Server.
<i>Machine Name</i>	Displays the name of the Deployment Server appears by default. The name is case sensitive, should not exceed 15 characters, and should not contain any special characters. Remote Deployment Server. If you installed JD EnterpriseOne Files to a remote Deployment Server, you should click the OK button to define a new Deployment Server. The deployment server name is the remote machine name by default.
<i>Description</i>	Enter a long description for the machine. This description should include the location with which this Deployment Server is associated and whether or not it is the primary server.
<i>Release</i>	Enter the Release 9.1 release number you are installing or use the visual assist button to choose one from the list. The default value is E910.
<i>Host Type</i>	Displays the value of 50 appears by default to indicate that the server type is Intel NT.
<i>Location</i>	Displays your current location as the default value.
<i>Primary User</i>	Specify the user to whom an email is sent when a package is deployed. The default value for Primary User is JDE.

3. On the Deployment tab, complete these fields:

Field	Description
Primary Deployment Server	<p>Define the hierarchy of the servers. Values are:</p> <p>1- Primary Deployment Server (default value)</p> <p>0 - Secondary Deployment Server</p> <p>The server share name of the directory to which you installed Release 9.1 on your Deployment Server. Verify that the server share name for Release 9.1 is \E910.</p>

4. Click OK.

Tip: If you enter invalid information into a tab field, a stop sign symbol appears next to the tab name, such as Deployment Server. For more information about the error, click the stop sign icon in the bottom right-hand corner of the form.


Release 9.1 asks if you want to add another Deployment Server.

5. To add another Deployment Server, click Yes and repeat steps 1 through 3.
6. To continue with Installation Planner setup, click No.


5.4.5 Entering Enterprise Server Information

Note: During the definition of the Enterprise Server, a port number must be defined. While Enterprise Servers running the same release can use the same port number, an Enterprise Server running two different versions of software must use two different port numbers.


To enter Enterprise Server information:



1. On Enterprise Server, click OK to define a new Enterprise Server, or click Select to choose from a list of existing Enterprise Servers.



If you choose Select, you are presented with the Machine Search table, from which you can make your selection.



2. On Enterprise Server Revisions, verify or complete these fields:

Field	Description
<i>Machine Name</i>	<p>The name of the primary Enterprise Server. The name is case sensitive and should not contain any special characters.</p> <p>Because the machine name is used to create the Server Map datasource name, and because the Platform Pack Installer does not restrict you from entering a machine name that results in a datasource name greater than 30 characters; if the machine name for the Enterprise Server is longer than 13 characters, the resulting datasource name will be longer than the allowed 30 characters. For example, if your machine name is 15 characters (A23456789012345), the base datasource name input into the Planner would be: A23456789012345 - 910 Server Map.</p> <p>Note: The field in table F98611 is a hard restriction; the field only allows 30 characters. The actual field size cannot be modified or changed.</p> <p>When the Planner runs it truncates the value to 30 characters because that is the restriction in the F98611 table. The Platform Pack does not truncate the value when it builds the <code>jde.ini</code> for the Enterprise Server. Therefore, any value greater than 30 characters will result in a mismatch between the <code>jde.ini</code> and the F98611 table. That is, using the previous example, the <code>jde.ini</code> would have the full length value A23456789012345 - 910 Server Map (which is 32 characters) while the F98611 populated by the Planner would have a value of A23456789012345 - 910 Server M.</p> <p>To remedy, you could do any one of the following:</p> <ul style="list-style-type: none"> Manually modify values in table F98611 to match the truncated value in the <code>jde.ini</code> file. Ensure that the value is not truncated by limiting the datasource name to 30 characters (this would mean limiting the machine name for the Enterprise Server to 13 characters). Manually truncate the value in the F98611 table (for example, A23456789012345 - 910 Svr Map). <p>In any case, you must ensure that the values for Server Map datasource names in the F98611 table exactly match those in the <code>jde.ini</code> file on the Enterprise Server.</p>
<i>Description</i>	Enter a description for the machine.
<i>Release</i>	Enter the Release 9.1 release number to which this plan applies, or use the visual assist button to choose one from the list. The default value is E910.
<i>Host Type</i>	Click the visual assist button and select the type of Enterprise Server you are adding to the plan. In this case, IBM i (AS/400).
<i>Location</i>	Displays the location chosen for this plan by default.
<i>Primary User</i>	Specify the user to whom an email is sent when a package is deployed. The default value for Primary User is JDE.

Note: The case of machine name must also match the network ID for that machine.

Caution: For information on supported clustering environments, see *Release 9.1 on a Cluster* in *JD Edwards EnterpriseOne Tools Server and Workstation Administration Guide* and the clustering vendor's software documentation.

- On Enterprise Server Revisions, select the Enterprise tab and complete or verify these fields:


Field	Description
Port Number	The port number value (6016) for this Enterprise Server as supplied from the <code>jde.ini</code> .
Logical Machine Name	Displays this information by default when the host type is entered. The name is case sensitive, should not exceed 15 characters, and should not contain any special characters.
Database Type	Enter the value for your database: <i>I - DB2 400</i>
Server Map Data Source	Whenever you enter a host type, the Installation Planner populates this field with a default value: <i>machinename - 910 Server Map</i> where <i>machinename</i> is the name of your machine.
Installation Path	Verify that the default value is the installation directory path to which you want to install Release 9.1 on the Enterprise Server. Make sure the value is specific to your version of the release. For example, for Release 9.1 the default path is: <code>\JDEdwards\PPack\E910SYS</code> This is the system library. Caution: You must change the value that defaults into the <i>Installation Path</i> field as shown in the screen capture above.
Deployment Server Name	Using the visual assist button, choose the name of the Deployment Server to which this Enterprise Server is attached. A Deployment Server name appears in this field by default, but it can be changed if necessary.

Note: If you change the port number to a value other than 6016, you must also change this setting to be synchronous between both the `jde.ini` on the Enterprise Server and workstation.

- Click OK.

5.4.6 Enter Data Source Information for Server Map

To enter data source information for Server Map:




- On Data Source, you are prompted to enter Data Source Information for the Enterprise Server.

Choose one of these options:

- Click OK to continue entering unique data source information. If you choose this option, continue with this task.
- Click Take Defaults to select the default data. If you choose this option, you can skip to [Section , "Caution When Choosing Take Defaults"](#)

Caution: In order to ensure the validity of all subsequent plan information, it is strongly recommended that even advanced users should not choose this Take Defaults option. Instead, you should step through plan and verify that the Planner is populating information exactly as you expect to match your requirements.



2. On Data Source Revisions

On Data Source Revisions, verify the accuracy of the Server Map data source.


3. Click OK.

5.4.7 Entering HTML Web Server Information


Note: For Release 9.1 the current terminology and that used in this guide is to refer to the machine running the JD Edwards EnterpriseOne Java Application Server (JAS) as the HTML Web Server. Functionally, these terms are all synonymous. However, this guide only uses the terms JAS or Java Server when explicitly labeled as such by the software.

Caution: The HTML Web Server is mandatory for the majority of JD Edwards EnterpriseOne applications because the end-user applications are only accessible through a web interface.

To enter HTML Web Server information:



1. On the HTML Application Server dialog, click OK to continue entering HTML Web Server information, or click Select to select an existing HTML Web Server.



2. On HTML Server Revisions, complete these fields:

Field	Description
<i>Machine Usage</i>	The default value of 30 indicates that this is a HTML Web Server.
<i>Machine Name</i>	Enter the name of your HTML Web Server. The name is case sensitive, should not exceed 15 characters, and should not contain any special characters.

Field	Description
<i>Description</i>	Enter a description of the HTML Web Server machine.
<i>Release</i>	Enter E910 to indicate the release number that you are installing.
<i>Host Type</i>	The default value of 50 specifies the server type as Intel NT. Select the correct server type.
<i>Location</i>	The location chosen for this plan appears in this field by default.
<i>Primary User</i>	The user to whom an email is sent when a package is deployed. The default for Primary User is listed in the JDE.INI.


3. On the HTML tab, complete these fields:

Field	Description
<i>Primary HTML Server</i>	When the system code generates an email message with a web shortcut pointing to a form, the web shortcut generated points to the "Primary" HTML Web Server. Only one of all the HTML Web Servers defined in installation planner can be defined as primary ("1").
<i>Protocol</i>	This is the protocol used by the HTML Web Server. Valid values are http or https .
<i>Server URL</i>	This is the Domain Name System (DNS) host name of the HTML Web Server. For example: www.oracle.com
<i>HTTP Port</i>	This is the port number the HTML Web Server is listening to. For HTTP, the typical port number is 80. For HTTPS, the typical port number is 443. Note: You can choose to implement a HTML Web Server using a different port number.
<i>JDENET Listen Port</i>	This is the port on which the JDENET communications protocol communicates with the JD Edwards EnterpriseOne Enterprise Server. The value is dependent on the release of JD Edwards EnterpriseOne. For JD Edwards EnterpriseOne Release 9.1, the value is 6016.
<i>Default Login</i>	Defines how shortcuts to a web form are generated by the system code. Values are either a reserved value or an explicit servlet name. Reserved values are: <ul style="list-style-type: none"> ■ Standard The URL generated will point to a servlet on the Primary HTML Web Server. ■ Redirector The URL generated will point to redirector in the Primary HTML Web Server, and redirector will point to a servlet on another HTML Web Server for load balancing. The servlet name to use is generated by the system. ■ Explicit Servlet Name The user can specify an explicit servlet name in this field. In this case, the redirector functionality cannot be used. The URL generated will point to the specified servlet in the Primary HTML Web Server. Usage of Explicit servlet name is for backward compatibility only. You should not use it unless you have a direct need.

Field	Description
<i>Installation Path</i>	<p>Enter the installation directory path to which you are installing Release 9.1 on your HTML Web Server. Make sure this is specific to your version of the release, and also the platform and application server on which your HTML Web Server is running.</p> <p>For default paths, refer to the applicable platform- and application server-dependent version of the <i>JD Edwards EnterpriseOne HTML Web Server Reference Guide</i> (WebLogic for Windows, WebLogic for UNIX, WebSphere for Windows, WebSphere for UNIX, WebSphere for IBM i). Otherwise, you must obtain this value from the HTML Web Server machine itself, or its administrator.</p>

4. Click OK.
5. To add another HTML Web Server, click Yes and repeat steps 1 through 4 to define another HTML Web Server.

5.4.8 Entering Data Server Information



1. On Data Server, choose one of these options:
 - OK
If your database resides on a separate server, choose click OK to continue entering unique Data Server information.
 - Select
Click this option to select an existing Data Server.
 - Skip
Click this option if you do not want to define a Data Server. Continue with the Planner using the environment selection in step 6 of this task.

2. On Data Server Revisions, complete these fields:

Field	Description
<i>Machine Usage</i>	The default value of 25 indicates that this is a Database Server.
<i>Machine Name</i>	Enter the name of the Database Server where your central objects reside. If you are using the IBM i to store your central objects, enter the name of this server. The name is case sensitive, should not exceed 15 characters, and should not contain any special characters.
<i>Description</i>	Enter a description of the Database Server machine.
<i>Release</i>	Enter the release number you are installing, for example, E910.
<i>Host Type</i>	Select the type of Database Server that you are adding to the plan. Values are: <ul style="list-style-type: none"> 10 — IBM i 25 — Sun Solaris 30 — RS\6000 35 — Linux 50 — Microsoft Windows (Intel) 80 — Client - Microsoft Windows 90 — Client - Microsoft Windows
<i>Location</i>	The Installation Planner populates this field by default, based on previous selections.
<i>Primary User</i>	The user to whom an email is sent once a package is deployed. The default for Primary User is JDE.

3. On the **Data** tab, complete the following field:

Field	Description
<i>Data Source Type</i>	Choose the type of data source. For example: <ul style="list-style-type: none">■ I - IBM i

4. Click OK.
5. To add another Data Server, click Yes and repeat steps 1 through 4 to define another Data Server.
6. On Data Source, click OK to continue entering unique shared data source information, or click Take Defaults to select the default data for the shared data sources.
7. On Location, select Yes to add another location, or click No to continue with Installation Planner.

5.4.9 Entering Shared Data Source Information

To enter or confirm information for data sources that are shared across all of your environments, complete the following tasks:

- [Section 5.4.9.1, "Specifying \(Custom or Default\) Shared Data Source setup information"](#)
- [Section 5.4.9.2, "Verifying the Data Source for Data Dictionary"](#)
- [Section 5.4.9.3, "Verifying the Object Librarian Data Source"](#)
- [Section 5.4.9.4, "Verifying the OWJRNL Data Source"](#)
- [Section 5.4.9.5, "Verifying the System Data Source"](#)

5.4.9.1 Specifying (Custom or Default) Shared Data Source setup information

Release 9.1 prompts you for the data source information for the shared data sources. Choose one of the following options:

- To use the Release 9.1 data sources, click Take Defaults.
Continue with [Section 5.4.10, "Setting Up Environments"](#).

Note: This option limits your customization choices.

- Click OK to enter the data sources. Verify the data source information.

5.4.9.2 Verifying the Data Source for Data Dictionary

To verify the data source for Data Dictionary:

Custom Installation Plan - [Data Source Revisions]

File Edit Preferences Form Window Help

Tools Form Advanced Port Database Sizing Default Sizing

OK Cancel Dismiss Abort Links Advanced OLE DB Internet

Data Source Name: Data Dictionary - 910

Data Source Use: DB Local Data Source

Data Source Type: DB2 UDB on OS/400 ☐ JDBNET Data Source?

Data Class: D Data Dictionary

Platform: AS400 IBM AS/400 (CISC)

Database Server Name: DS2

SQLMSDE ODBC SQLMSDE OLEDB Oracle **DB2 OS/400** DB2 UDB Access Logical

Library Name: DD910

ODBC Data Source Name: Data Dictionary - 910


1. On Data Source Revisions, verify the accuracy of the settings for the Data Dictionary data source.

The library name in the Library Name field is the Release 9.1 data dictionary library (DD910).

2. Click OK.

5.4.9.3 Verifying the Object Librarian Data Source

To verify the Object Librarian data source:



1. On Data Source Revisions, verify the accuracy of the settings for the Object Librarian data source.
2. Click OK.

5.4.9.4 Verifying the OWJRNL Data Source

To verify the OWJRNL data source:

Custom Installation Plan - [Data Source Revisions]

File Edit Preferences Form Window Help

OK Cancel Dis... Abort Links Advan... OLE ... Internet

Data Source Name: OWJRNL

Data Source Use: DB Local Data Source

Data Source Type: DB2 UDB on OS/400 ☐ JDBNET Data Source?

Data Class: L Local

Platform: AS400 IBM AS/400 (CISC)

Database Server Name: Ent6

SQLMSDE ODBC SQLMSDE OLEDB Oracle **DB2 OS/400** DB2 UDB Access Logical

Library Name: OWJRNL

ODBC Data Source Name: OWJRNL

1. On Data Source Setup, verify the accuracy of the OWJRNL data source.
2. Click OK.

5.4.9.5 Verifying the System Data Source

To verify the System data source:

Custom Installation Plan - [Data Source Revisions]

File Edit Preferences Form Window Help

OK Cancel Dis... Abort Links Advan... OLE ... Internet

Data Source Name: System - 910

Data Source Use: DB Local Data Source

Data Source Type: DB2 UDB on OS/400 ☐ JDBNET Data Source?

Data Class: S System

Platform: AS400 IBM AS/400 (CISC)

Database Server Name: DS2

SQLMSDE ODBC SQLMSDE OLEDB Oracle **DB2 OS/400** DB2 UDB Access Logical

Library Name: SY910

ODBC Data Source Name: System - 910

1. On Data Source Setup, verify the accuracy of the settings for the System data source.
2. Click OK.

The Environment Selection screen appears.

See Also


For more information about System data source fields or fields for other data sources mentioned in this process, refer to Chapter 23, "Understanding Data Source Charts".

5.4.10 Setting Up Environments

By default, Release 9.1 configures your system using values for typical environments. Depending on the options chosen when you set up your plan, Release 9.1 displays one or more of the following parameters, which you can customize in the following tasks:

- Environments
- Data Load Options
- Advanced Parameters
- Languages

You can customize any of these parameters by turning off the default option on the Environment Selection form. As you move through the plan, Release 9.1 will display a customization form for each parameter that you turn off.



1. On Environment Selection, turn off the options for those parameters that you want to customize.

Note: The parameters that display might vary depending on which options you chose at the beginning of the planning process.

2. Click OK.

Note: If you checked the default option for all parameters, skip to [Section 5.4.11, "Setting Up Environment Data Sources"](#).


Use the following tasks to customize each of the parameters listed above. Release 9.1 displays customization forms only for those parameters for which were turned off the default options. Skip the tasks for those parameters that were left turned on.

3. Continue with the following relevant tasks:
 - [Section 5.4.10.1, "Selecting an Environment"](#)
 - [Section 5.4.10.2, "Specifying Environment Data Load Parameters"](#)
 - [Section 5.4.10.3, "Verifying Advanced Parameters"](#)
 - [Section 5.4.10.4, "Selecting Languages \(optional\)"](#)

5.4.10.1 Selecting an Environment

The Select Environment form appears.

Note: Environments prefixed with Jxx are required for the HTML Web Server.



1. On **Select Environments**, double-click the environment that you want to define.
2. To set up multiple environments, choose and define them one at a time. Release 9.1 returns to this screen after the following tasks are completed.
3. Click the **Close** button to exit the Select Environments screen.

5.4.10.2 Specifying Environment Data Load Parameters

If you turned off Default Data Load on the Environment Selection form, the Data Load Parameters form appears.

To specify environment data load parameters:

Custom Installation Plan - [Data Load Parameters]

File Edit Preferences Form Window Help

OK Cancel Next Dis... Abort Links Next OLE ... Internet

The data load options are used when creating new tables (R98407) during an Upgrade. The option must be set to Load Production or Load Development in order to populate F9861 and F983051.

☐ Load Production Data ☒ Load DemoData

Data Load Setup

Environment	PS910	E910 Pristine Environment
Previous Environment		
Plan Detail Status	10	In Planning
Program Name	R98403	Environment Database Creation
Version	XJDE0033	Express Install
<input checked="" type="radio"/> Source Environment	JDEPLAN	Planner
<input type="radio"/> Source Data Source	Business Data Local	

5.4.10.3 Verifying Advanced Parameters

If you turned off Default Advanced Parameters on the Environment selection form, the Advanced Parameters form appears.

To verify advanced parameters:

1. On Advanced Parameters, complete the following fields and turn on the following options:

Field	Description
Logic Data Source	The server data source where the table conversions will run
Table Conversion Throttle	The number of table conversions to be run concurrently on the server

Note: The Table Conversion Workbench checks the maximum jobs for the default job queue for the logic server. It will only submit up to the number of maximum jobs on the queue to run at once. If the throttle is set higher than the queue, it uses the queue maximum number of jobs. If the queue is set higher than the throttle, it uses the throttle.


2. Click OK.

If you turned off Default Languages on the **Select Environments** selection form, continue with [Section 5.4.10.4, "Selecting Languages \(optional\)"](#).

If you are not installing languages, Release 9.1 prompts you for data source information. Skip to [Section 5.4.11, "Setting Up Environment Data Sources"](#).

5.4.10.4 Selecting Languages (optional)

To select languages:



1. On Language Selection, to set up a language for the selected environment, choose the appropriate language.
2. From the Row menu, click Select.
3. Repeat the above steps until all your languages have been selected.
4. Click OK.

Note: Customization Considerations. If you have customizations that you do not want to merge, you can prevent individual conversions and merges from running by changing their status or deleting the appropriate records from the plan before you run the Installation Workbench.

5.4.11 Setting Up Environment Data Sources

Once the Environments have been set up, it is necessary to set up the Data Sources for those Environments. If you created a custom environment, data source information is generated from the data source template provided by JD Edwards EnterpriseOne.

See Also

To modify this template, refer to the *JD Edwards EnterpriseOne Configurable Network Computing Implementation Guide*.

5.4.11.1 Selecting an Environment Data Source Setup Option

On the Installation Planner prompt that enables you to set up data sources for the environment you just configured:

- Click OK to manually enter the data sources as described in the remaining tasks in this section.
- Click Take Defaults to accept the Release 9.1 default data sources.

5.4.11.2 Setting Up the Data Source for Business Data

To set up the Business Data data source:


The screenshot shows the 'Custom Installation Plan - [Data Source Revisions]' window. The 'Form' menu is open, and the 'Advanced' option is selected. The main area contains the following fields and options:

- Data Source Name:** Business Data - TEST
- Data Source Use:** DB (Local Data Source)
- Data Source Type:** DB2 UDB on OS/400 (JDBNET Data Source? checkbox is unchecked)
- Data Class:** B (Business Data)
- Platform:** AS400 (IBM AS/400 (CISC))
- Database Server Name:** DS2

Below these fields are tabs for different data source types: SQLMSDE ODBC, SQLMSDE OLEDB, Oracle, **DB2 OS/400** (selected), DB2 UDB, Access, and Logical. The DB2 OS/400 tab shows:

- Library Name:** TESTDTA
- ODBC Data Source Name:** Business Data - TEST

1. From the Form menu, click Advanced.



2. On Advanced Parameters, verify the UNICODE flag is off. If your Business Data was not set to Unicode in a previous release and the data source had not yet been converted to Unicode, the Unicode flag must match the contents of the data source.
3. Click OK.
4. On Data Source Revisions, verify the data source for your Business Data.
Be sure this data source points either to the existing production data source you want to upgrade or to a copy of it.

Note: Business Data data sources are specific to the environment and pathcode.

5. When you ran Copy Plan, some fields were changed to reflect the previous release values. Change the following fields:

Field	Description
Data Source Type	Enter <i>I</i> for IBM iSeries Access.
iSeries Database Name	Enter the name of the data source. For example, Business Data - TEST.

6. Click OK.

5.4.11.3 Setting Up the Data Source for Central Objects

Caution: You should change the data source if Central Objects are not on an IBM i machine.

To set up the Central Objects data source:

The screenshot shows the 'Custom Installation Plan - [Data Source Revisions]' window. On the left is a vertical toolbar with icons for Tools, Form, Advanced, Port, Database Sizing, and Default Sizing. The main area contains the following fields:

- Data Source Name:** Central Objects - DV910
- Data Source Use:** DB (Local Data Source)
- Data Source Type:** I (DB2 UDB on OS/400) ☐ JDBNET Data Source?
- Data Class:** C (Central Objects)
- Platform:** AS400 (IBM AS/400 (CISC))
- Database Server Name:** DS2


Below these fields is a tabbed interface with tabs for SQLM8DE ODBC, SQLM8DE OLEDB, Oracle, **DB2 OS/400**, DB2 UDB, Access, and Logical. The 'DB2 OS/400' tab is active, showing:

- Library Name:** CODV910
- ODBC Data Source Name:** Central Objects - DV910

1. On Data Source Setup, verify the information for your Central Objects data source.
2. Click OK.

Verify that your Central Objects data source is Central Objects - <Path Code>.

Note: Central Objects data sources are specific to the pathcode.




- On Advanced Set-Up, because the central objects data source must be Unicode, verify the **Unicode** setting is checked.

For IBM i, ensure the **AS/400 BLOB Support** setting is checked.

5.4.11.4 Setting Up the Data Source for Control Tables

To set up the Control Tables data source:



- On Data Source Revisions, verify the accuracy of the Control Tables data source.

Field	Description
<i>Data Source Name</i>	Verify the name of the data source.
<i>Server Name</i>	Verify the name of the Enterprise Server. When you defined your plan, some fields were changed to reflect the previous release values. Verify the values for Data Source and Database type are set as follows: <i>I</i> for IBM iSeries Access
<i>Library Name</i>	Enter the name of the library housing your Control Tables for the selected environment.
<i>ODBC Data Source Name</i>	Enter the name of the data source. For example, Control Tables - Test.

Note: Control Tables data sources are specific to the environment and pathcode.

- Click Advanced and verify that UNICODE is off only if the Control Tables are not set to Unicode in a previous release.

Note: If you upgrade from Release 8.9 the Unicode flag is on.

- Click OK.

5.4.11.5 Verifying the Data Dictionary Data Source

To verify the Data Dictionary data source:

The screenshot shows the 'Custom Installation Plan - [Data Source Revisions]' window. The 'Advanced' tab is selected. The 'Data Source Name' is 'Data Dictionary - 910'. The 'Data Source Use' is 'DB' (Local Data Source). The 'Data Source Type' is 'I' (DB2 UDB on OS/400). The 'Data Class' is 'D' (Data Dictionary). The 'Platform' is 'AS400' (IBM AS/400 (CISC)). The 'Database Server Name' is 'DS2'. Below the main fields are tabs for different database types: 'SQLMSDE ODBC', 'SQLMSDE OLEDB', 'Oracle', 'DB2 OS/400' (selected), 'DB2 UDB', 'Access', and 'Logical'. The 'DB2 OS/400' tab shows the 'Library Name' as 'DD910' and the 'ODBC Data Source Name' as 'Data Dictionary - 910'.

1. On Data Source Setup, verify the accuracy of the Data Dictionary data source.
The library name in the Library Name field is the Release 9.1 data dictionary library (DD910).
2. Click OK.

5.4.11.6 Verifying the Data Source for Versions

To verify the Versions data source:


The screenshot shows the 'Custom Installation Plan - [Data Source Revisions]' window. The 'Data Source Name' is 'Versions - DV910'. The 'Data Source Use' is 'DB'. The 'Data Source Type' is 'DB2 UDB on OS/400'. The 'Data Class' is 'Versions'. The 'Platform' is 'AS400'. The 'Database Server Name' is 'DS2'. The 'Library Name' is 'CODV910' and the 'ODBC Data Source Name' is 'Versions - DV910'. The 'DB2 OS/400' tab is selected in the bottom section.

1. On Data Source Revisions, verify the accuracy of the Versions data source.
2. Click OK.

Note: Versions data sources are specific to the pathcode, and the Unicode flag on the Advanced Form must be checked.

5.4.12 Adding a Remote Location

To add remote location:



Release 9.1 asks if you want to add another (remote) location.

1. On Location, choose one of the following options:

- Click Yes to add a remote location.

Repeat all processes for adding a location starting with [Section 5.4.3, "Entering Location Information"](#). Refer to the Creating a Remote Installation Plan task in the Installation Planner Utilities section for information about adding remote locations to your plan.

- Click No to conclude the Installation Plan setup.

2. Continue with [Section 5.4.13, "Finalizing the Installation Plan"](#) task.

5.4.13 Finalizing the Installation Plan

To finish the Installation Plan.

1. A message appears to let you know that the installation plan has been finalized.

When the plan is finalized:

- The status is set to 20, which signals that several adjustments to tables were made according to your plan.
- Create the OCM.
- Modify the ini file.
- The following tables are upgraded:
Release Master table (F00945)
Path Code Master table (F00942)
Package Plan table (F98404)
Machine Detail table (F9651)
Language table (F984031), if you are installing an alternate language.

2. Click OK to exit the concluding message box and initiate the Planner Validation Report.
 - If processing option default was chosen, Planner Validation Report automatically prompts you to run this report.
 - If processing option default was not chosen, on the tree view of your plan, click Validate to initiate the Planner Validation Report.

5.4.14 Concluding the Validation Planner Report

To conclude the validation planner report:

1. On Report Output Destination, choose On Screen or To Printer, and click OK.
2. Review the report to confirm that all records were validated.
3. After reviewing the report, on the Batch Versions form, click Close.

For more information about [Section 25.1, "Installation Planner Validation Report \(R9840B\)"](#), refer to [Chapter 25, "Working with Reports"](#).

4. On Work with Installation Plans, click Expand to review the plan you created.

See Also

- A separate chapter in this guide entitled: [Chapter 19, "Creating a Remote Installation Plan"](#)
- A separate chapter in this guide entitled: [Chapter 20, "Adding a Server to an Existing Configuration"](#)
- A separate chapter in this guide entitled: [Chapter 21, "Creating a Language-Only Installation Plan"](#)

5.4.15 Resetting the jde.ini Prior to Running Table Conversions

If you changed the `jde.ini` on the Enterprise Server at the end of upgrading a previous environment, you will need to change it back before running the upgrade for this environment. Verify this setting:

```
[DB SYSTEM SETTINGS]
SQL Package Library=2
```

If you have any other setting than 2 for the `SQL Package Library` parameter, your Table Conversions will fail.

5.4.16 Clearing SQL Packages from QRECOVERY

You may have one or more packages (Rnnnnn) in QRECOVERY if you are upgrading from JD Edwards ERP 8.9 onwards, and you were running with this setting:

```
[DB SYSTEM SETTINGS]
SQL Package Library=1
```

If these packages exist in QRECOVERY, you could experience problems after the upgrade. However, the problem will not be apparent during the upgrade, because the upgrade installer uses a `jde.ini` with `SQL Package Library=2`.

Note: With the setting `SQL Package Library=2`, the system assigns each job its own unique package (for example, T123456), which is not based on the UBE name.

You should delete any old UBE SQL packages in QRECOVERY.

Note: No UBEs can be running on the server while you are deleting these packages.

To delete the packages, use this command:

```
DLTSQLPKG QRECOVERY\R*
```

5.5 Deleting Machines from an Installation Plan

As you work through the Installation Planner application, you might find that you need to delete a server or machine that you have created. You can use Installation Planner to delete machines as needed; however, doing so can affect related databases, shared Enterprise Servers and Deployment Servers, and associated records.

To delete machines from an installation plan:

1. In the Release 9.1 planner environment, enter P9654A in the Fast Path field and press Enter.
2. On Work With Locations and Machines, click Find.
3. Expand the location.

A list of your locations, machines, or servers appears for the base location in the tree view.

4. Select the location, machine, or server that you want to delete.
5. Click Delete.
6. To close the application, click Close.

5.6 Verify and Configure Data Source for Previous Release

Note: This section is only applicable if you installed your E910 deployment server a different machine (as the previous release). If you install the E910 Deployment Server on the same machine (as the previous release), the Installation Planner automatically detects the local System data source and uses it to configure the upgrade.

Before you run the Installation Planner for an upgrade, you must ensure that you have a data source properly configured on the E910 Deployment Server so this machine can access system tables for the previous release residing on a different machine. This is because the installation planner must import information from previous system data source in order to recognize and upgrade your existing environment.

If the Installation Planner cannot detect the System data source on this machine and it is an upgrade plan, it displays this screen prompting you to enter the information about the previous System data source.

Custom Installation Plan

File Edit Preferences Form Window Help

Data Source Revisions

OK Cancel Dismiss Help

Links Advanced OLE DB Internet

Data Source Name:

Data Source Use: DB Local Data Source

Data Source Type: ☐ JDBNET Data Source?

Data Class:

Platform:

Database Server Name:

SQL/MSDE ODBC SQL/MSDE OLEDB Oracle DB2 OS/400 DB2 UDB Access

1. On Custom Installation Plan, Data Source Revisions, select the appropriate tab for your previous database and complete the fields to match your previous data source.

For example, if your previous data source was Oracle, your previous platform was Linux, and your previous EnterpriseOne applications release was 9.0, a properly completed form would look like this:

Custom Installation Plan

File Edit Preferences Form Window Help

Data Source Revisions

OK Can... Dis... Adv... OLE ... Internet

Data Source Name: System - 900

Data Source Use: DB Local Data Source

Data Source Type: O ORACLE ☐ JDBNET Data Source?

Data Class: S System

Platform: LINUX Linux

Database Server Name: orclvmdb

SQL/88E/MSDE ODBC | SQL/MSDE OLEDB | **Oracle** | DB2 OS/400 | DB2 UDB | Access

Object Owner ID: SY900

Database Name (TNS): orcl

2. Click the **OK** button to verify your data source connection information to the System data source on the remote machine.

Working With Installation Workbench

This section discusses:

- [Section 6.1, "Understanding Workbench Components"](#)
- [Section 6.2, "Verifying OCM Mappings"](#)
- [Section 6.3, "Adding an Entry to the Remote Database Directory"](#)
- [Section 6.4, "Verifying the Language Code Character Set"](#)
- [Section 6.5, "Working with Unattended Workbench Mode"](#)
- [Section 6.6, "Solution Explorer"](#)
- [Section 6.7, "Changing the Status of the Control Table Workbench Tasks"](#)
- [Section 6.8, "Verify and Update P98MOQUE Settings"](#)
- [Section 6.9, "Starting Installation Workbench"](#)
- [Section 6.10, "Working With Initial Tasks Workbench"](#)
- [Section 6.11, "Configuring Your Locations"](#)
- [Section 6.12, "Configuring Your Data Sources"](#)
- [Section 6.13, "Configuring Your Environments"](#)
- [Section 6.14, "Using Machine Workbench"](#)
- [Section 6.15, "Understanding Control Table Merges"](#)
- [Section 6.16, "Understanding Table Conversions"](#)
- [Section 6.17, "Understanding Obsolete Tables"](#)
- [Section 6.18, "Understanding Specification Table Merges"](#)
- [Section 6.19, "Using the Package Workbench"](#)
- [Section 6.20, "Using Remote Location Workbench"](#)
- [Section 6.21, "Finishing Installation Workbench"](#)

6.1 Understanding Workbench Components

After planning the Release 9.1 upgrade using Installation Planner, you should run the plan using Installation Workbench. The logic of this program runs specific workbench programs according to the plan you created.

For example, if you are upgrading and not installing, when performing a data-only upgrade, you do not incorporate the specification merges into your plan; therefore, the Specification Table Merge Workbench is not displayed.

Installation Workbench can be run in attended mode or unattended mode. In attended mode, you start each workbench after the previous workbench completes. In unattended mode (the default value), each workbench runs without user intervention. You can set task breaks before or after any specific workbench to stop the process at any point. If using unattended mode, you must check that each task ran successfully.

This section describes:

- [Section 6.1.1, "Verifying the Network Share on the Deployment Server"](#)
- [Section 6.1.2, "Loading Data \(Demo Data and Production Data\)"](#)
- [Section 6.1.3, "Creating the Job Queue"](#)
- [Section 6.1.4, "Deferring Indexes for Table Conversion Workbench \(Tools Release 9.1 Update 2\)"](#)

As listed in this table, Installation Workbench includes the components, some or all of which might be used for your upgrade, depending on your installation plan:

Installation Workbench Component	Functional Description
Initial Tasks Workbench	When using unattended workbench mode, this workbench runs Media Object Conversion (only for Xe and ERP 8.0), Release Master, Copy Data Dictionary, Copy System Tables, and Security Copy (applies to upgrades from Xe and ERP 8.0) after Installation Workbench is started and before Location Workbench begins.
Location Workbench	This workbench copies all locations that are defined in the plan from the F9654 and F984021 tables in the Planner data source to the System - 910 data source.
Data Source Workbench	Copies all data sources that are defined in the plan from the F98611 and F986115 tables in the Planner data source to your System - 910 data source. It also updates the F98401 table to indicate completion.
Environment Workbench	Copies the F0094, F00941, and F00942 tables, as well as the F986101 table for each environment, from your Planner data source to your System - 910 data source. It then updates the F98403 table to indicate completion. Depending on the plan settings, it also runs a batch application to copy new generic text and to create and populate Object Management Workbench and version tables.
Machine Workbench	Copies the F9650 and F9651 tables from the Planner data source to the System - 910 data source. It then updates the F98402 table to indicate completion and uses the environment information to populate the F986101 and F98611 tables in the Server Map data source. Only valid environments, data sources, and server map tables are created.

Installation Workbench Component	Functional Description
Control Table Workbench	<p>Runs the batch applications for the planned merges that update the data dictionary, user defined codes (UDCs), Solution Explorer, and other Control Tables. It then updates the F98405 table to reflect completion, and writes a conversion log record to the F984052 table.</p> <p>Also runs the batch applications for the planned merges to update language files. This workbench runs only for users who are adding an alternate language to their installations.</p> <p>For Tools Release 9.1 Update 2. If you wish to defer index builds, you can choose to do so beginning with Tools Release 9.1 Update 2. During your upgrade you may choose to defer index builds for very large tables, for tables that are converted several times during the Table Conversion Workbench, or if you are planning on a Unicode conversion. For details and instructions on deferring index builds, refer to the subsection in this guide entitled: Chapter 6.1.4, "Deferring Indexes for Table Conversion Workbench (Tools Release 9.1 Update 2)".</p>
Table Conversion Workbench	Runs the table conversions that convert the technical and application tables to the new format for Release 9.1. It then updates the F98405 table to indicate completion, and writes a conversion log record to the F984052 table.
Control Table Workbench	<p>Runs the batch applications for the planned merges that update the data dictionary, user defined codes (UDCs), Solution Explorer, user overrides tables, and other control tables. It then updates the F98405 table to indicate completion, and writes a conversion log record to the F984052 table.</p> <p>Also runs the batch application for the planned control table merges to update language files. Also runs the batch applications for the planned merges to update the data dictionary. It then updates the F98405 table to indicate completion, and writes a conversion log record.</p>
Specification Table Merge Workbench	Runs the batch applications that merge custom modifications into the new specification tables. It then updates the F98405 table to indicate completion, and writes a conversion log record. The Object Librarian and Versions List merges are now a part of the specification merge.
Package Workbench	Transfers the F9603 and F9631 tables from the Planner data source to the System - 910 data source. It then updates the F98404 table to indicate completion.

See Also

[Chapter 24, "Major Technical Tables"](#) in this guide for more information about individual tables and their uses.

[Chapter 18, "Performing a Data-Only Upgrade"](#) for more information about data-only upgrades.

6.1.1 Verifying the Network Share on the Deployment Server

When you created the plan, this network share was created:

```
\\depsvrname\E910
```

where `depsvrname` is the name of your Deployment Server.

Because several of the Workbenches update files through the network share, these workbenches will fail if the share is not writeable. Sometimes the security settings on your Deployment Server will prevent the Planner from creating the share as a writeable share.

Use this procedure to ensure that the share is writeable before proceeding:

1. On the Deployment Server, navigate to Start | My Computer | Manage
2. Open Shared Folders.
3. Open Shares.
4. Right click on E910 and select Properties and then Share Permissions.
5. Select properties then select Share Permissions
6. Make sure that Everyone is set to Full Control, Change, Read permissions.

Note: Even after the Workbenches are complete, you will still need these settings on the Deployment Server's share in order to successfully perform client installs.

6.1.2 Loading Data (Demo Data and Production Data)

While previous versions of JD Edwards EnterpriseOne used Workbench components to load data, for Release 9.1 the Platform Pack Installer loads appropriate data into specific environments as follows:


- Demo data to Development and Pristine environments.
- Production data to Production and Prototype environments.

To load demo data in Production or Prototype environments, you must run a UBE (R98403E) to copy the data to those environments.

Note: The "from" (source) environment can be the Planner environment or your Pristine environment.

Caution: You should **not** change the record selection on this UBE.

1. Run R98403E using the XJDE0009 version and set the processing options as follows:



Processing Options


Environments | Advanced




R98403E copies each table identified by data selection to the target data source.
 If the table already exists in the target data source, data will not be replaced.
 If the table format mismatch the table spec.s in the target data source, the table will be re-created.

1. Enter the name of the source environment (the environment of the table to be copied).

2. or Enter the name of the source Data Source (the data source of the table to be copied).

3. Enter the name of the target environment (the environment to copy the table to).

4. or Enter the name of the target Data Source (the data source to copy the table to). 

2. On Processing Options 1-4, complete these fields:

■ *Option 1*

Enter the name of the source environment, which is the environment of the table to be copied. For example, JDEPLAN.

■ *Option 2*

This field must be blank because this UBE is used to copy a mixture of business data and control tables which are specified to environments, not data sources.


■ *Option 3*

Enter the name of the target environment, which is the environment to which you wish to copy the table. In this case, you would specify either the Production or Prototype environments. For example, PD910.

■ *Option 4*

This field must be blank because this UBE is used to copy a mixture of business data and control tables which are specified to environments, not data sources.

3. Click OK to continue specifying processing options.



The image shows a 'Processing Options' dialog box with two tabs: 'Environments' and 'Advanced'. The 'Advanced' tab is selected. It contains five numbered options, each with a text input field. At the bottom are 'OK', 'Help', and 'Cancel' buttons.

Option	Description	Value
5	Enter a '0' for Proof Mode, enter a '1' to copy the table. The default is Proof Mode.	1
6	Enter a 'Y' to create all selected tables in target data source, even if they do not exist in source data source. (Default is 'N')	N
7	Enter a 'Y' to re-create tables that already exist in the target data source. (Default is 'N')	Y
8	Enter a 'Y' to copy data based on table 'CPYD' flag in Object Librarian (F9860). (Default is 'N')	N
9	Enter a 'Y' to add index(es) after copy data. (Default is 'N')	N

4. On Processing Options 5-9, complete these fields:

Field	Description
Option 5	<p>The recommended value is 1, which copies the table.</p> <p>The default value is 0, Proof Mode.</p>
Option 6	<p>The recommended value is N, which copies tables only if they exist in the source.</p> <p>Enter Y to copy tables whether or not they exist in the source data source.</p> <p>The default value is N.</p>
Option 7	<p>The recommended value is Y, which recreates tables that already exist in the target data source.</p> <p>Note: If you do not recreate the tables, you will end up with a mixture of production and demo data in the tables.</p> <p>The default value is N.</p>
Option 8	<p>The recommended value is N, which forces a copy of the data, ignoring the CPYD flag.</p> <p>Note: A value of Y will leave almost all tables empty. That is, a production data load.</p> <p>The default value is N.</p>

Field	Description
Option 9	The recommended value is N, which creates the indexes on the tables before copying the data. This prevents duplicate rows. Note: A value of Y copies the data and then create the indexes. The default value is N.

- Click OK to accept the values and start the UBE.

6.1.3 Creating the Job Queue

You may set up the job queues before running the Installation Workbench. If you do not, Initial Tasks Workbench will create a default entry for QBATCH with a setting of *maximum=4*.

Note: For Queue Type 2, the Release 9.1 Job Queue name must match an existing IBM i JOBQ.

To create the job queue:

- Enter GH9013 in the Fast Path field and start the Job Queues program (P986130).
- Click Add.

- On Job Queue Revisions, add a queue by completing these fields:

Field	Description
Host	Enter the Enterprise Server name.
Job Queue	Ensure that the queue name matches the batch queue name on the IBM i. Typically IBM i machines use the batch queue QBATCH as their default.
Default Queue	Turn on this option by clicking the check box.
Job Queue Status	Enter 01 .
Queue Type	Enter 02 .
Maximum Batch Jobs	Enter a value that equals the number of processors on the Enterprise Server machine.
Port Number	Enter 6016 . If you receive a Network Failed error, you can safely ignore it in this case.

4. Add another queue called *I-ACTIVE*.

5. On Job Queue Revisions, add a queue by completing these fields:

Field	Description
Host	Enter the Enterprise Server name.
Job Queue	Enter the Job Queue name: <i>I-ACTIVE</i> .
Default Queue	Turn off this option by clicking the radio button.

Field	Description
Job Queue Status	Enter 01 .
Queue Type	Enter 02 .
Maximum Batch Jobs	Enter a value that equals the number of processors on the Enterprise Server machine.
Port Number	Enter 6016 .

6.1.4 Deferring Indexes for Table Conversion Workbench (Tools Release 9.1 Update 2)

Beginning with Tools Release 9.1 Update 2, if you wish to delay building indexes during the Table Conversion Workbench, you must set that attribute in the Table Conversion Plan before running the Installation Workbench. For implementation details, refer to [Section 6.16.5, "Deferring Index Builds During Table Conversion Workbench \(Tools Release 9.1 Update 2\)"](#).

6.2 Verifying OCM Mappings

If you are upgrading from Xe or ERP8, before running the Workbench ensure that the OCM mappings for any previous environments in your plan are correct. From B9 onwards, JD Edwards EnterpriseOne on IBM i systems use LOBs instead of BLOBs.

When you created your upgrade plan and copied the data sources and OCM from your previous System data source, the Planner flagged all the regular data sources as LOB data sources. However, any existing *data_source_name* ' DNT data sources were not flagged, and remain as BLOB data sources. When you finalize the plan, it automatically deactivates all *data_source_name* ' DNT OCM mappings for the previous environments in your plan, and activated the non-DNT data sources instead.

When you created your upgrade plan and copied the data sources and OCM from your previous System data source, the Planner flagged all the regular data sources as LOB data sources. However, any existing *data_source_name* DNT data sources were not flagged, and remain as BLOB data sources. When you finalize the plan, it automatically deactivates all *data_source_name* DNT OCM mappings for the previous environments in your plan, and activated the non-DNT data sources instead.

As a result, prior to running the Workbench, you should verify the accuracy of the OCM mappings after you run the Planner. Ensure that no *data_source_name* - DNT mappings are active for the previous environment(s) in this plan.

Examples of *data_source_name* - DNT mappings are:

Table	DNT Data Source
F98811	Control Tables - <i>data_source_name</i> - DNT
F9060	System - <i>release_number</i> - DNT
F983051	Versions - <i>data_source_name</i> - DNT

Tip: In order to verify basic functionality of your OCM mappings, you should run a sample UBE (for example, R0006P or R014021) in PS8910 on your Enterprise Server.

6.3 Adding an Entry to the Remote Database Directory

You can add an entry to the remote database directory by completing these steps:

1. Log on to the IBM i as QSECOFR.
2. On the command line, enter WRKRDBDIRE.
3. Look for an entry on your IBM i for Remote Location *LOCAL. This entry must have the same name as your machine.
4. If you do not have an entry like this, enter 1 in the Option column and type your machine name in the Relational Database column, and press enter. In the Remote Location Name or Address field, enter *LOCAL and press Enter. If you already have a *LOCAL entry and the Relational database name is not the same as your machine name, you must remove the entry that you have and add a new entry as previously described.

Note: In previous JD Edwards EnterpriseOne releases, installation of Vertex required adding an entry to the Remote Database Directory, but no special naming was required. It is possible, in some cases, an entry was added with some other naming convention for this purpose. Vertex will work with a Remote Database Directory entry that is correct for Release 9.1.

5. Once you have added or change the entry, you should recycle the database host server prestart jobs by issuing these commands:

```
ENDPJ SBS(QSERVER) PGM(QSYS\QZDAINIT) OPTION(*IMMED)
ENDPJ SBS(QUSRWRK) PGM(QSYS\QZDASOINIT) OPTION(*IMMED)
ENDPJ SBS(QUSRWRK) PGM(QSYS\QZDASSINIT) OPTION(*IMMED)
STRPJ SBS(QSERVER) PGM(QSYS\QZDAINIT)
STRPJ SBS(QUSRWRK) PGM(QSYS\QZDASOINIT)
STRPJ SBS(QUSRWRK) PGM(QSYS\QZDASSINIT)
```

Note: Users will not be able to use JD Edwards EnterpriseOne while you are running these commands.

6.4 Verifying the Language Code Character Set

Note: This step is only required if your Business Data and Control Tables are non-Unicode. For example, if you are upgrading from JD Edwards Xe.

To verify that the code character set ID for your preferred language is set:

1. On the IBM i, enter this command:

```
WRKUSRPRF JDE
```
2. Choose option 2 to edit.
3. Press F10 to verify and edit all fields.
4. Scroll to the character set ID (CCSID).
5. Change the setting to your preferred language character set. For example, CCSID=37 (English language).

For more information, refer to [Code Page Settings](#).

This setting will be returned to its original value before you start Release 9.1 on your Enterprise Server.

6.5 Working with Unattended Workbench Mode

This section discusses:

- [Section 6.5.1, "Selecting Attended or Unattended Workbench Mode"](#)
- [Section 6.5.2, "Setting a Task Break in Unattended Workbench Mode"](#)

6.5.1 Selecting Attended or Unattended Workbench Mode

The workbenches can be run manually (attended workbench mode) or automatically (unattended workbench mode). When running Workbench in unattended mode, start Installation Workbench as described below, and then the status of each workbench is displayed as the workbench begins. Unattended workbench is the default value.

In unattended workbench, if an error is encountered in any of the individual workbenches, the process stops. After fixing the error, unattended workbench resumes where it left off.

To choose attended workbench mode:

1. Open the System Installation Tools menu (GH961).
2. Right-click on Installation Workbench.
3. Select Prompt For and then Values.

The Processing Options form appears.

4. In the appropriate field, enter 1 for unattended workbench mode or 0 (zero) for attended workbench mode.

The default value is 1 (unattended).

5. Click OK.

Work with Installation Plan appears.

6.5.2 Setting a Task Break in Unattended Workbench Mode

In unattended workbench, you can set task breaks before or after any of the individual workbenches. You can use the task break to verify successful completion of a workbench or for other tasks. For example, set a task break after Table Conversion Workbench to verify that all table conversions completed successfully. An automatic task break occurs after Control Table Workbench, preceding Table Conversion Workbench.

To set a task break in unattended workbench mode:

1. Open the System Installation Tools menu (GH961).
2. Select Advanced Operations.
3. Double-click Work with Task Breaks.

The Work with Task Breaks form appears.

4. Click Find.

A list of the workbenches appears.

5. To set a break before or after a workbench, choose the workbench name, and, on the Row menu, select Break Before or Break After.

You can clear task breaks on the Row menu.

6. On Task Break Revisions, specify the following fields:

- *email Address (optional)*

Specify (or choose from a list) the address book number of the person who is to be notified when the task break occurs.

- *Task Break*

Specify (blank) for no task break or 2 for a customer task break. If the field is left blank, then no task break is configured.

- *Task Break Short Text (required)*

Enter a short text description of the task break.

- *Optional Detail (optional)*

Enter detailed information about the task break.

7. Click OK.

Task Break Revisions closes, and Work with Task Breaks reappears. Specify any further task breaks.

8. Click Close.

6.6 Solution Explorer

If you used both Menu and Solution Explorer Task tables in the previous release, you need to synchronize the Menu tables. If you used Solution Explorer Task tables in the previous release, you need to disable the R9000C report before running the Control Table Workbench.

6.7 Changing the Status of the Control Table Workbench Tasks

To change the status of a Control Table Workbench task:

1. Enter GH961 in the Fast Path field to open the System Installation Tools menu.
2. Double-click Custom Installation Plan.
3. On Work with Installation Plans, select your installation plan.
4. On the Row menu, click Expand.
The plan components, including the Control Table Merge, are displayed.
5. Choose the task whose status you want to change.
6. On the Row menu, click Disable, Enable, or Complete (see the list below).

The task status changes.

- *Disable*

Displays a status of 70 to indicate the task is incomplete, and will not be rerun.

- *Enable*

Displays a status of 10 to indicate the task will be rerun.

- *Complete*

Displays a status of 60 to indicate the task is complete, and will not be rerun.

6.8 Verify and Update P98MOQUE Settings

To verify and update the P98MOQUE settings:

1. Log into Release 9.1 as JDE in the JDEPLAN environment.
2. Enter P98MOQUE in the Fast Path field.
3. Click Find.
4. Ensure your P98MOQUE grid lines are set to point to the location of the previous release media objects.
5. Click OK.

6.9 Starting Installation Workbench


Caution: Do not lock the Deployment Server during Installation Workbench processes (for example, with a screen saver password); doing so pauses some processes.

Do not run Installation Workbench from a remote access program that simulates a local connection.


To start the Installation Workbench:

1. On your Deployment Server, log in to the Planner environment, which is JDEPLAN.
2. From the System Installation Tools menu (GH961), choose Installation Workbench.

When this application is run the first time, the system downloads all required objects using Just In Time Installation (JITI).



- If you specified attended workbench mode, use the following procedures, including the Initial Tasks Workbench, to complete the workbenches.
 - If you specified unattended workbench mode, the process begins and all workbenches are completed automatically, unless task breaks are set. If you did not set any task breaks, continue with [Chapter 7, "Working With the Enterprise Server"](#).
3. On Work with Installation Plan, double-click your plan.
 4. If you have selected that you want to run Table Conversions on the Enterprise Server, the Installation Workbench displays the following message:



This message warns that before proceeding with the Upgrade, you must delete the glbltbl, ddtext, and dddict spec files from the target path code on the Enterprise Server. Failure to do this usually causes data corruption due to customized Display Decimals.

At this point you should delete these spec files as instructed, and then click the OK button in the Message to continue.

6.10 Working With Initial Tasks Workbench

Before the workbench is run, the F00945 table in the System data source is blank because it is no longer populated when a plan is validated. However, after you run the Initial Task Workbench several tables in the System data source are populated including the F00945 table.

The Initial Tasks Workbench form lets you complete the following preliminary tasks before the individual workbenches begin:

- Security copy
- Media Object (Inplace) Unicode Conversion (applies to upgrades from Xe and ERP 8.0)
- Data Dictionary Media Object Unicode Conversion (applies to upgrades from Xe and ERP 8.0)
- Copy data dictionary
- Copy system tables
- Release Master

You can also change the status of any of the initial tasks, for example, if you need to rerun a task.

You use this procedure if you are running Workbench in attended mode or if you set a task break before Initial Tasks Workbench.

6.10.1 Using Initial Tasks Workbench

To use Initial Tasks Workbench:

The screenshot shows the 'Initial Tasks Workbench' window. At the top, there is a menu bar with 'File', 'Edit', 'Preferences', 'Form', 'Row', 'Window', and 'Help'. Below the menu bar is a toolbar with icons for 'Find', 'Close', 'Seg...', 'New...', 'Prev...', 'Next', 'Con...', 'Dis...', and 'Abo'. To the right of the toolbar are buttons for 'Links', 'Previo...', 'OLE ...', and 'Internet'.

Below the toolbar, there are two input fields: 'Plan Name' with the value 'UPGDV910' and 'Upgrade Plan for DV910', and 'New Plan Status' with the value '60'.

Below the input fields is a table with the following data:

Description	Program Name	Version	Det Sts	Status Description	From Release	To Release
Copy Tables from	R98403	XJDE0051	70	Duplicate Convers	B9	E900
Copy Tables from	R98403	XJDE0020	70	Duplicate Convers	B9	E900
Copy Tables from	R96983051	XJDE0001	20	Finalized	B9	E900
Copy Tables from	R98403	XJDE0023	70	Duplicate Convers	B9	E900
Copy Tables from	R98403	XJDE0123	70	Duplicate Convers	B9	E900
Create/Copy System Tables	B9800400		20	Finalized	B9	E900

At the bottom of the window, there is a status bar with the text 'Row:1' and a small icon.

On Initial Tasks Workbench, click the Form menu and select Configure.

The tasks are performed, and the Location Workbench form appears.

During the Initial Tasks Workbench, there are two UBEs scheduled for media object Unicode Conversion if upgrading from ERP 8.0 or earlier:

- The R8900165 report converts the media objects stored in Business Data.
- The R8900165U report converts the Data Dictionary media objects.

The following list of error messages and the corresponding resolutions, (inspect the jde.log for more information):

Error Message	Resolution
SelectKeyed to F00165T failed	Check F00165T spec, and run again.
Read Failed: Media Object data not available in F00165T blob	The object is missing or corrupted, and must be added manually.
Read Failed: Cannot allocate memory for Media Object Blob	Check virtual memory, and run again.
Read Failed: Missing records for BLOB concat - Total(###) - Read(###)	The object is missing or corrupted, and must be added manually.
Cannot allocate memory for Generic Text Blob	Check virtual memory, and run again.
Fail to open OLE storage file (<Queue Path> -<.stg file name>)	Make sure the file exists in the path that defined in the System - 910 F98MOQUE table (based on <Queue Path>), and run again.

Error Message	Resolution
OLE storage file might be corrupted - <.stg file name>	The object is missing or corrupted, and must be added manually.
OLE substorage file might be corrupted - <.stg file name>	The object is missing or corrupted, and must be added manually.
OLE Fail: Insufficient memory to create new file (<Queue Path>) - <filename>	Check virtual memory, and run again.
OLE Fail: Access Denied - cannot create new file (<Queue Path>) - <filename>	Check security setting on OLE queue path folder, and run again.
OLE Fail: Program error - cannot create new file (<Queue Path>) - <filename>	The object is missing or corrupted, and must be added manually.
OLE Fail: Cannot create new file (<Queue Path>) - <filename>	Check rights and disk space on OLE queue path, and then run again.
JDB CommitUser Fails	Check Database (blocks) setting, and run again.
Invalid Shortcut Data - <file name>	The object is missing or corrupted, and must be added manually.
Invalid Shortcut Data - cannot allocate memory	Check virtual memory, and run again.
Invalid Document ID - <vendor name>	The object is missing or corrupted, and must be added manually.
Secondary RTF File fails to open (<Queue Path>) - <filename>	Make sure the file exists in the path that defined in "System - 910" F98MOQUE (based on <Queue Path>), and run again.
Cannot allocate memory for RTF Blob	Check virtual memory, and run again.

6.10.2 Changing the Status of Initial Tasks Workbench

You use this procedure if you are running Workbench in attended mode or if you set a task break before Initial Tasks Workbench.

To change the status of Initial Tasks Workbench:

Plan Name: Upgrade Plan for DV910

New Plan Status:

Description	Program Name	Version	Det Sts	Status Description	From Release	To Release
Copy Tables from	R98403	XJDE0051	70	Duplicate Convers	B9	E900
Copy Tables from	R98403	XJDE0020	70	Duplicate Convers	B9	E900
Copy Tables from	R96983051	XJDE0001	20	Finalized	B9	E900
Copy Tables from	R98403	XJDE0023	70	Duplicate Convers	B9	E900
Copy Tables from	R98403	XJDE0123	70	Duplicate Convers	B9	E900
Create/Copy System Tables	B9800400		20	Finalized	B9	E900

Row:1

You might want to change the status of one or more of the initial workbench tasks. To change the status of a task, use the following procedure.

1. Enter GH961 in the Fast Path field to open the System Installation Tools menu.
2. Double-click Custom Installation Plan.
3. On Work with Installation Plans, select your installation plan.
4. Select Expand on the Row menu.

The plan components, including the initial tasks, appear.

5. Select the task whose status you want to change.
6. On the Row menu, click Disable, Enable, or Complete (see the table below).

The task status changes.

- *Disable*

Displays a status of 70 to indicate the task is incomplete, and will not be rerun.

- *Enable*

Displays a status of 10 to indicate the task will be rerun.

- *Complete*

Displays a status of 60 to indicate the task is complete, and will not be rerun.

6.11 Configuring Your Locations

Location Workbench copies all locations that are defined in the plan from the F9654 table in the Planner data source to the System - 910 data source. It also updates the F984021 table. Use this procedure when running Workbench in attended mode or if you set a task break before Location Workbench.

Plan Name	Location	Location Description	Detail Status	Status Description
UPGDV910	DENVER	DENVER	20	Finalized

1. On Location Workbench, verify that all of your locations are listed.
2. Select Configure from the Form menu.
Locations are configured, and the Data Source Workbench form appears.
The system updates the Detail Status to 60 and changes the Status Description from Validated to Installed.

6.12 Configuring Your Data Sources

Data Source Workbench copies all data sources that are defined in the plan from the F98611 table and the F98615 table in your Planner data source to your System - 910 data source. It also updates the F98401 table to indicate completion. Use this procedure when running Workbench in attended mode or if you set a task break before Data Source Workbench.

1. On Data Source Workbench, verify that all of your data sources are listed as illustrated in this example.

Data Source	Detail Status	Status Description	Create Table	User ID	Up
Business Data - PROD	20	Finalized	1		
Central Objects - PD910	20	Finalized	1		
Control Tables - Prod	20	Finalized	1		
Data Dictionary - 910	20	Finalized	1		
DNITHP21	20	Finalized	1		
DNITHP21 - 910 Server Map	20	Finalized	1		
DNITHP21 - Logic	20	Finalized	1		
DNITHP21 - RTE	20	Finalized	1		
DNITHP21 - XAPI	20	Finalized	1		
LOCAL	20	Finalized	1		
Local - PD910	20	Finalized	1		
Object Librarian - 910	20	Finalized	1		

2. Select Configure from the Form menu.

Your data sources are configured, and the Environment Workbench form appears.


When the system has configured your data sources, it updates Detail Status to 60 and changes the Status Description from Validated to Installed.

6.13 Configuring Your Environments

Environment Workbench copies the F0094, F00941, and F00942 tables, as well as the F986101 table for each environment, from your Planner data source to your System - 910 data source. It then updates the F98403 table to indicate completion. Depending on the plan settings, it also runs a batch application to copy new generic text and to create and populate Object Management Workbench and version tables.

Environment Workbench can run multiple batch applications simultaneously, which enables Release 9.1 to load multiple environments at the same time. This reduces the amount of time it takes to load environments.

Use this procedure when running Workbench in attended mode or if a task break is set before Environment Workbench.



1. On Environment Workbench, review each environment and its associated parameters to make sure the values are correct.
2. After you review the environments, select Configure.
3. When Environment Workbench has completed, verify that the status of each environment has been updated to 60 and that the status description has changed from Validated to Installed.
4. Using Adobe Acrobat, review all XJDE reports, and confirm that all configuration statuses indicate Success.

6.14 Using Machine Workbench

Machine Workbench copies the F9650 and F9651 table from the Planner data source to the System - 910 data source. It then updates the F98402 table to indicate completion and uses the environment information to populate the F986101 and F98611 tables in the Server Map data source.

Note: Only valid environments, data sources, and server map tables are created.

Host Name	Port Number	Host Description	Machine Usage	Detail Status	St Des
DENITSD21	0	PRIMARY DEP SRV	15	30	Finalized
denitrs33	85	Jas	30	30	Finalized
dnithp21	6016	PRIMARY ENT SRV	20	30	Finalized

1. On Machine Workbench, review each server and its associated parameters for the correct values.
2. Select Configure from the Form menu.

When the system has configured your servers, it changes the detail status to 60, and Status Description changes from Validated to Installed.

6.15 Understanding Control Table Merges

Control Table Workbench runs the batch applications for the planned merges that update the data dictionary, user defined codes (UDCs), Solution Explorer, and other control tables. It then updates the Table Conversion Scheduler table (F98405) to indicate completion, and writes a conversion log record to the Table Conversion - History Log table (F984052).

Note: The number of control tables to be merged varies, depending on the upgrade being performed. Your Control Table Workbench form may list fewer or more tables than shown in the figure above. If you used Solution Explorer task tables in a previous release, disable R9000C before running the Control Table Workbench.

6.15.1 Language Installation

This information applies to users installing an alternate language. The distributed language tables consist of control tables, system tables, and data dictionary tables. The

UDC tables contain only the desired language text, while the Solution Explorer text and data dictionary files add the desired language on top of the already-installed English records.

Control Table Workbench also copies the language text from the Oracle tablespace that contains the language text into the control table database and central object database.

You use this procedure when running Workbench in attended mode, or if a task break is set before Control Table Workbench.

6.15.2 Configuring Control Tables

To configure your control tables:

1. On Control Table Workbench, Release 9.1 displays all control table merges in the detail area.

Environment Name	Table Name	Detail Status	Status Description	Program Name	Version	Cmv. Seq.
PD910	F9200	30	Finalized	R989200P	XJDE0001	25
PD910	F0004	30	Finalized	R9600042	XJDE0001	45
PD910	F91100	30	Finalized	R96911002	XJDE0001	70
PD910	F91400	30	Finalized	R96914002	XJDE0001	75
PD910	F91500	30	Finalized	R96915002	XJDE0001	80
PD910	F9000	30	Finalized	R9690002	XJDE0001	90

If you are installing an alternate language, on the Control Table Workbench form, the Plan Name field will contain the name of your language plan.

2. If you want to do one merge at a time, choose the appropriate grid row, then click Merge. Otherwise, choose Merge All from the Form menu.

For an explanation on merges, see Chapter 9, "Performing Merges".

3. The system displays all control table merges in the detail area.

Custom Installation Plan - [Control Table Planner]

File Edit Preferences Form Row Window Help

Del... Can... New... Back Next Save Dis... Abo Links Save OLE ... Internet

Plan Name PD910UPG PD910 Upgrade

Environment	Table Name	Detail Status	Status Description	Program Name	Version	Cnv. Seq.	From Rel. Level	To Release Level
PD910	F9200	60	Installed	R989200P	XJDE0001	25	B9	E910
PD910	F0004	60	Installed	R9600042	XJDE0001	45	B9	E910
PD910	F91100	60	Installed	R96911002	XJDE0001	70	B9	E910
PD910	F91400	60	Installed	R96914002	XJDE0001	75	B9	E910
PD910	F91500	60	Installed	R96915002	XJDE0001	80	B9	E910
PD910	F9000	60	Installed	R9000C	XJDE0002	85	B9	E910
PD910	F9000	60	Installed	R9690002	XJDE0001	90	B9	E910
						0		

Row:1

- Select Merge All from the Form menu.
- When running Installation Workbench in unattended mode, a task break automatically occurs after Control Table Workbench, and before Table Conversions.

After each merge finishes, verify the output of the report produced. Refer to [Working with Reports](#) for more detailed information.

6.16 Understanding Table Conversions

Table Conversion Workbench runs the table conversions that convert technical and application tables to the new format for Release 9.1. It updates the F98405 table to indicate completion, and writes a conversion log record to the F984052 table for each conversion.

Use the following procedures when running Workbench in attended mode or if a task break is set before Table Conversion Workbench.

All users must run the table conversions that appear in the Release 9.1 Table Conversion Workbench.

Tip: You can safely ignore GT98DSA and GT98DSB errors reported in R8900165_XJDE0001.

Note: If you have chosen to run TCs on the Enterprise Server (the default), the following TCs will still run on the Deployment Server:

- Any TC below sequence 100
- Any TC with the Run On Deployment Server flag turned on

The Data Message column is a flag that tells the TC Workbench NOT to check the table to see if it is already in the target format. For other TCs, the workbench will not run the Table Conversion if the table is already converted.

This section discusses:

- [Section 6.16.1, "Running Table Conversions"](#)
- [Section 6.16.2, "Table Conversion Workbench Architecture"](#)
- [Section 6.16.3, "Configuring Table Conversions to Run on the Enterprise Server"](#)
- [Section 6.16.4, "Verifying the Table Conversion Process"](#)
- [Section 6.16.5, "Deferring Index Builds During Table Conversion Workbench \(Tools Release 9.1 Update 2\)"](#)

6.16.1 Running Table Conversions

Note: For Tools Release 9.1 Update 2. If you wish to defer index builds, you can choose to do so beginning with Tools Release 9.1 Update 2. During your upgrade you may choose to defer index builds for very large tables, for tables that are converted several times during the Table Conversion Workbench, or if you are planning on a Unicode conversion. For details and instructions on deferring index builds, refer to the subsection in this guide entitled: [Section 6.16.5, "Deferring Index Builds During Table Conversion Workbench \(Tools Release 9.1 Update 2\)"](#).

To run table conversions:

1. If it is not already open, open Installation Workbench, double-click your plan on Work with Installation Plan, and click Next until Table Conversion Workbench appears.

Installation Workbench - [Table Conversion Workbench]

File Edit Preferences Form Row Window Help

Find Close Seg... New... Prev... Next... Con... Dis... Abo...

Links Previo... OLE... Internet

Plan Name: PD910UPG PD910 Upgrade

New Status: 60

Mode: ☐ Synchron ☒ Asynchron

☐ Run TC on Deployment Server TC Throttle: 4 ☐ Tracing On

Target Environ	Previous Environ	Table Name	Dtl Sts	Status Description	Run History	Program Name	Version	Crw. Seq.	Dep. On	Error Code	Bus. View For Merge	Run Local	Prc Typ	Process Desc.	Ran on Server
PD910	PD9	F7306	60	Installed		*ALTER		50	0			1	5	Table Conversion	LOCAL
PD910	PD9	F0009	60	Installed		*ALTER		55	0			1	5	Table Conversion	LOCAL
PD910	PD9	F0010	60	Installed		*ALTER		55	0			1	5	Table Conversion	LOCAL
PD910	PD9	F4009	60	Installed		*MERGE	V894009	55	0		V894009	1	5	Table Conversion	LOCAL
PD910	PD9	F00921	60	Installed		R8900921	XJDE0001	60	0			1	5	Table Conversion	LOCAL
PD910	PD9	F0007	60	Installed		R890007C	XJDE0001	80	0			1	5	Table Conversion	LOCAL
PD910	PD9	F3009	60	Installed		R893009C	XJDE0001	80	0			1	5	Table Conversion	LOCAL
PD910	PD9	F41001	60	Installed		*MERGE		80	0		V8941001	1	5	Table Conversion	LOCAL
PD910	PD9	F49002	60	Installed		*ALTER		80	0			1	5	Table Conversion	LOCAL
PD910	PD9	F40205	60	Installed		R8940205	XJDE0001	81	0			1	5	Table Conversion	LOCAL
PD910	PD9	F4322	60	Installed		*ALTER		81	0			1	5	Table Conversion	LOCAL
PD910	PD9	F986167	60	Installed		R89986167A	XJDE0001	87	0			1	1	Simple Report	LOCAL
PD910	PD9	F42199	60	Installed		R8942199D	XJDE0001	103	0			0	5	Table Conversion	JDEP
PD910	PD9	F42199	60	Installed		R8942199A	XJDE0001	104	103			0	5	Table Conversion	JDEP
PD910	PD9	F42199	60	Installed		R8942199B	XJDE0001	105	104			0	5	Table Conversion	JDEP
PD910	PD9	F42199	60	Installed		R8942199F	XJDE0001	106	105			0	5	Table Conversion	JDEP
PD910	PD9	F49219	60	Installed		*ALTER		107	0			0	5	Table Conversion	JDEP

Row:1

- To override where the Table Conversions will be run, click on Run TC on Deployment Server.
- To change how many Table Conversions are submitted simultaneously to the Enterprise Server, change the value in TC Throttle. This value should match the maximum jobs set up for the QBATCH queue on the Enterprise Server. You control how many TCs are actually running at any time by your queue set up by using WRKJOBQE.

On your IBM i machine, make sure JOBQ MAX ACT is set to match the TC Throttle that you choose.

Tip: To set the maximum number of simultaneous jobs submitted, refer to [Section 6.16.3.3, "Select Enterprise Server and Maximum Jobs On Select Environments - Advanced Exit"](#).

- Select Convert All from the Form menu.

Tip: To do one conversion at a time, select the appropriate detail records, and then select Convert Selected from the Form menu. While the conversions run, you can track their progress by choosing Table Conversion\Merge Log (P984052). To do so, on the System Installation Tools menu (GH961), double-click Advanced Operation, and then Table Conversion\Merge Log. The program shows a scrolling list of the conversions that have processed.

6.16.2 Table Conversion Workbench Architecture

Select Convert All (this is used automatically when running unattended) or Convert Selected to run the TC Workbench program (P98413).

The Convert All selection causes the program to run with two loops. The outer loop keeps running until there are no more TCs to run, and there are no more TCs in a running status. The inner loop runs through the F98405 table looking for all TCs at a status less than 60. As it reads each new record, it then checks to see if there are any TCs waiting at status 35 for dependencies. It first tries to run those (checks again if their dependencies are satisfied), before trying to run the new TC that it just read.

The Technical TCs (those that are at conversion sequence < 100) run one at a time. For TCs above sequence 100, Convert All uses the maximum batch jobs specified in the Plan (4 by default), meaning it submits up to that number of TCs at once. You control how many are actually running at any time by your queue set up by using the P986130 program. The default setup is four (4) batch jobs at once. Selecting Convert All submits 4, then loops waiting for a job to end and submits the next job. If you set your queue to a number larger than 4, only 4 are submitted at a time.

For each TC it tries to submit, it first checks whether that TC has dependencies and checks the status of those dependencies. If any of the dependencies is still running (status 45), this TC is changed to status 35 (waiting for dependencies).

The Convert Selected option can be used to submit several TCs at once and keeps looping till they are submitted. It does not keep looping till they have run. Press Find to see if they are done.

The P98413 program monitors and updates the F98405 table, which is maintained locally in JDEPLAN. The TCs update the F984052 table, which is maintained in System - 910. At any point in time, there are records in the F98405 table at status 45 for TCs that actually have completed. The TC Workbench calls a business function at various points in its loop, which compares the F984052 and F98405 table, and updates the status in the F98405 to completed (60) or failed (50). If the TC Workbench fails (for example, you cancel out of it), go into the Custom Plan application and drill down into your TCs, and press Find. This synchronizes the F98405 table with the F984052 table. Clicking the Find button on the TC Workbench also synchronizes the F98405 and F984052 tables.

If the Enterprise Server fails while running the TC Workbench, you may have up to 4 jobs at status 45 (running), even though they may have failed. Follow the instructions in the write-up on restarting the TC Workbench, to get everything back into sync. (Remember the Find button on the Custom Plans [Table Conversions] synchronizes the F98405 with F984052 tables.) If a TC actually fails on the server (for example, you cancel the job) it will never get as far as updating the F984052 table, and the process is not able to update the F98405 table correctly. Selecting either Convert Selected or Convert All, does not re-submit anything that is at status 45. When restarting the TC Workbench, you need to resolve manually whether any of the jobs at status 45 are still running, and set the status back to 30 or 50 if you want the TC Workbench to re-submit them.

All the Table Conversions have the same job name, which is R98405A. When looking in the `jde.log` for that job, there is a message stating which TC is running.

6.16.3 Configuring Table Conversions to Run on the Enterprise Server

There are three settings that control the location for running Table Conversions. These are:

- [Section 6.16.3.1, "Table Conversion Schedule"](#)

- [Section 6.16.3.2, "Upgrade Plan Definition"](#)
- [Section 6.16.3.3, "Select Enterprise Server and Maximum Jobs On Select Environments - Advanced Exit"](#)
- [Section 6.16.3.4, "Configuring Queues"](#)
- [Section 6.16.3.5, "Starting Table Conversions"](#)
- [Section 6.16.3.6, "Monitoring Table Conversions"](#)
- [Section 6.16.3.7, "Working With Table Conversion Log Files"](#)
- [Section 6.16.3.8, "Stopping Table Conversions"](#)
- [Section 6.16.3.9, "Restarting Installation Workbench"](#)

6.16.3.1 Table Conversion Schedule

When the table conversions are scheduled using JD Edwards EnterpriseOne, schedule owners decide whether their conversions can run on the Enterprise Server. If not, then the Run TC on Deployment Server option is selected. Most conversions can run on the Enterprise Server. Table conversions that cannot include Technical Conversions (sequence < 100), UBEs, and cross-data source conversions (for example, printers, user preferences). The Table Conversion Schedule is accessed through the Advanced Operations Menu (GH9611).

Conversion Type	3	Application Table
Table Name	F3003	Routing Master File
Business View Name		
From Release	B9	B9 J.D. Edwards
To Release	E910	E910 J.D. Edwards
Conversion Sequence Nbr	102	
Dependent on Sequence	0	
Conversion Program	R893003A	Data Conversion for F3003 From
Version	XJDE0001	
Process Type	5	Table Conversion
<input type="checkbox"/> Run TC on Deployment Server		<input type="checkbox"/> Data message Y/N

6.16.3.2 Upgrade Plan Definition

It is not required to run table conversions on an Enterprise Server. The main advantage to doing so is performance. If you have a small database you may decide to run them on the Deployment Server by selecting Run TC on Deployment Server when defining your plan. The default is to run conversions on the Enterprise Server.

Custom Installation Plan - [Installation Planner]

File Edit Preferences Form Window Help

Tools
Form
Deploy...

OK Can... Dis... Ab... Links Deplo... OLE ... Internet

Plan Information:

Name: UPGRADE

Description: Run Table Conversions on Svr

Status: 10 In Planning

Install Type:

☐ Install ☒ Upgrade ☐ Software Update (ASU/ESU)

Release:

From Release: B9 To Release: E910

Table Conversion Properties:

☐ Run TC on Deployment Server ☐ Tracing

6.16.3.3 Select Enterprise Server and Maximum Jobs On Select Environments - Advanced Exit

After selecting an environment on Select Environments, select Advanced on the Form menu to access Advanced Parameters. Select the logic data source for the Enterprise Server where table conversions will be run for that environment. If you do not follow these steps, Installation Planner will select a default Enterprise Server. The port number is specified in the Deployment Server `JDE.INI`. Also on Advanced Parameters, you can override the maximum jobs for the default job queue on the Enterprise Server.

Custom Installation Plan - [Advanced Parameters]

File Edit Preferences Form Window Help

OK Cancel Dismiss Abort Links ▼ Options... OLE ... Internet

☒ Upgrade Environment

Plan Name PD910UPG

Library List Name PD910 E910 Production Environment

Previous Environment PD812 E812 Production Environment

Object Configuration Manager

☒ Recreate Object Mappings

Table / Specification

☒ Table Conversions

☐ Specification Merges

Control Table Merges

☐ None

☒ Upgrade Merges

TC Properties

Logic Data Source JDEP

Table Conversion Throttle 4

6.16.3.4 Configuring Queues

The job queues (GH9013) are implemented in the queue kernel. During the Initial Tasks Workbench, the Release Master copies the default queue set up during the plan to the Enterprise Server job queue table.

On your IBM i, make sure you set up QBATCH to match the TC Throttle you set in the plan. You must also select a Queue Type of iSeries and use IBM i tools to configure the queue (CHGJOBQE).

6.16.3.5 Starting Table Conversions

To start Table Conversions, run Installation Workbench. If you are in Unattended Mode, a task break is displayed before Table Conversion Workbench reminding you to set up your Enterprise Server. If you press Stop on the task break, you will need to press the Convert All exit to start the conversions.

When running conversions on the Deployment Server, the R98405 program is launched and runs all conversions, producing a report when complete.

When running conversions on the Enterprise Server, Table Conversion Workbench launches a R98405A program for each conversion including any conversions that run locally. This is the UBE that is displayed in Submitted Reports (GH9011). When all conversions are complete, the R984052 program produces a report.

6.16.3.6 Monitoring Table Conversions

Table Conversion Workbench implements a throttling mechanism to control conversions. If conversions are run on the Deployment Server, it launches one conversion at a time. If conversions are run on the Enterprise Server, it looks up the maximum number of batch jobs in the queue table and submits that many conversions at a time. Either way, technical conversions are always throttled to 1. The list of submitted conversions can be seen in Table Conversion Planner.

1. Go to the System Installation Tools menu (GH961)
2. Open Typical Installation Plan or Custom Installation Plan.
3. Click Find.
4. Expand the plan. Drill down to Environments, Environment Name, Table Conversions.
5. Highlight the Table Conversions node and click Select.
6. Enter 45 into the Detail Status QBE.
7. Click Find.

Custom Installation Plan - [Table Conversion Planner]

File Edit Preferences Form Row Window Help

Find Del... Can... New... Back Next Save Dis... Abo Links Save OLE ... Internet

Plan Name PD910UPG PD910 Upgrade TC Throttle

	Prev Env	Table Name	Dtl Sts	Status Description	Program Name	Version	Criv. Seq.	Dep. Seq.	Error Code	Run Local	Dta Msg	Hst Sts	Ran on Machine	From Rls
	PD9	F7306	60	Installed	*ALTER		50	0		1	0	4	LOCAL	B9
	PD9	F0009	60	Installed	*ALTER		55	0		1		4	LOCAL	B9
	PD9	F0010	60	Installed	*ALTER		55	0		1		4	LOCAL	B9
	PD9	F4009	60	Installed	*MERGE	V894009	55	0		1	0	2	LOCAL	B9
	PD9	F00921	60	Installed	R8900921	XJDE0001	60	0		1	1	2	LOCAL	B9
	PD9	F0007	60	Installed	R890007C	XJDE0001	80	0		1		2	LOCAL	B9
	PD9	F3009	60	Installed	R893009C	XJDE0001	80	0		1		2	LOCAL	B9
	PD9	F41001	60	Installed	*MERGE		80	0		1		2	LOCAL	B9
	PD9	F49002	60	Installed	*ALTER		80	0		1		4	LOCAL	B9
	PD9	F40205	60	Installed	R8940205	XJDE0001	81	0		1		2	LOCAL	B9
	PD9	F4322	60	Installed	*ALTER		81	0		1		4	LOCAL	B9
	PD9	F986167	60	Installed	R89986167A	XJDE0001	87	0		1		2	LOCAL	B9
	PD9	F42199	60	Installed	R8942199D	XJDE0001	103	0				2	JDEP	B9
	PD9	F42199	60	Installed	R8942199A	XJDE0001	104	103				2	JDEP	B9
	PD9	F42199	60	Installed	R8942199B	XJDE0001	105	104				2	JDEP	B9

Row:1

Use Submitted Reports (GH9011) to view the status of submitted conversions. Notice all the jobs show the R98405A program. To link the jobs to conversions, note the job number. The jde.log, jdedebug.log, and conversion log all have the job number in the name. The jde.log contains a message with the conversion name. For more on the log files, see the section below.

Queue	Status	Description	Priority	Type	User	Job Details	Host	Job #
QBATCH	P	Processing	5	UBE	JDE	R98405A_XJDE0001_2_PD	DEVNTA	
QBATCH	P	Processing	5	UBE	JDE	R98405A_XJDE0001_4_PD	DEVNTA	
QBATCH	P	Processing	5	UBE	JDE	R98405A_XJDE0001_6_PD	DEVNTA	
QBATCH	P	Processing	5	UBE	JDE	R98405A_XJDE0001_8_PD	DEVNTA	
QBATCH	W	Waiting	5	UBE	JDE	R98405A_XJDE0001_14_P	DEVNTA	
QBATCH	W	Waiting	5	UBE	JDE	R98405A_XJDE0001_16_P	DEVNTA	
QBATCH	W	Waiting	5	UBE	JDE	R98405A_XJDE0001_18_P	DEVNTA	
QBATCH	W	Waiting	5	UBE	JDE	R98405A_XJDE0001_20_P	DEVNTA	
QBATCH	W	Waiting	5	UBE	JDE	R98405A_XJDE0001_22_P	DEVNTA	
QBATCH	W	Waiting	5	UBE	JDE	R98405A_XJDE0001_28_P	DEVNTA	
QBATCH	W	Waiting	5	UBE	JDE	R98405A_XJDE0001_30_P	DEVNTA	
QBATCH	W	Waiting	5	UBE	JDE	R98405A_XJDE0001_34_P	DEVNTA	
QBATCH	W	Waiting	5	UBE	JDE	R98405A_XJDE0001_36_P	DEVNTA	
QBATCH	W	Waiting	5	UBE	JDE	R98405A_XJDE0001_40_P	DEVNTA	
QBATCH	W	Waiting	5	UBE	JDE	R98405A_XJDE0001_10_P	DEVNTA	
QBATCH	W	Waiting	5	UBE	JDE	R98405A_XJDE0001_12_P	DEVNTA	
QBATCH	W	Waiting	5	UBE	JDE	R98405A_XJDE0001_24_P	DEVNTA	
QBATCH	W	Waiting	5	UBE	JDE	R98405A_XJDE0001_38_P	DEVNTA	
QBATCH	W	Waiting	5	UBE	JDE	R98405A_XJDE0001_42_P	DEVNTA	
QBATCH	W	Waiting	5	UBE	JDE	R98405A_XJDE0001_44_P	DEVNTA	

Server Manager can be used to monitor processes and queues, and view jde.log, jdedebug.log, and jde.ini.

Platform-specific utilities such as WRKACTJOB can also be used to monitor the conversions.

Database Specific Queries that query unconverted tables, temp tables, converted tables, and database system tables can be helpful in monitoring conversions.

6.16.3.7 Working With Table Conversion Log Files

The log files are stored in these specific locations:

- The jde_ProcessId.log and jdedebug_ProcessId.log are stored in while the conversion is running.

Once the conversion has finished, the logs are moved to and renamed to these names:

R98405A_XJDE0001_EnterpriseOne_Job_Number_PDF.jde.log

R98405A_XJDE0001_EnterpriseOne_Job_Number_PDF.jdedebug.log

- The JDE_IBM i_Job_Number.LOG and JDEDEBUG_IBM i_Job_Number.LOG are stored in \E910.
- The conversion logs are stored in the Printqueue directory. The log will be named one of the following:
 - Report_Version_Ddate_Ttime_Jjob_number.log
 - Table_ALTERTABLE_Ddate_Ttime_Jjob_number.log
 - Table_MERGETABLE_Ddate_Ttime_Jjob_number.log
- The directory for the printqueue is \E910SYS\PrintQueue

INI Settings

- [DEBUG]
;Turn off jdedebug.log, set to FILE to turn on jdedebug.log
Output=NONE
;Turn on jde.log, set to 0 to turn off jde.log
LogErrors=1
;Do not send logging info to client, set to 1 to send logging info to client (not recommended)
ClientLog=0
- [JDENET]
;Turn off JDENET tracing. Set to 1 to turn on JDENET tracing.
netTrace=0
- [TCENGINE]
;Turn on minimal table conversion tracing. Set to 0 to turn off tracing (not recommended). Set to 10 for maximum tracing (useful for troubleshooting).
TraceLevel=1

Note: There is a possibility that there may be invalid errors in the JDE.log. You can ignore any error along the lines that read:

No rounding record found in table *tablename* - *datasource*

where *tablename* is the name of the table and *datasource* is the name of the datasource.

Tip: You can run the TC verification report prior to running spec merge to ensure tables are in the correct format. Refer to [Section 25.8.4, "Compare Tables and Indexes Against Central Objects or TAM Specifications \(R9698711\)"](#) in the chapter entitled: [Chapter 25, "Working with Reports"](#).

6.16.3.8 Stopping Table Conversions

To stop table conversions:

1. Close Workbench.
2. On the Deployment Server, open Task Manager (press Ctrl+Alt+Del and choose Task Manager).
3. On the Applications tab, select Installation Workbench and click End Task.
4. Locate waiting jobs from Submitted Reports (GH9011) by entering **W** in Status QBE and clicking Find.
5. Highlight any row you wish to delete and click Delete.

All conversions should now be stopped. There are several more steps involved with cleaning up the database and resetting Table Conversion Workbench. You may choose to leave one or more table conversions running but close Installation Workbench and restart the remaining conversions. See [Section 6.16.3.9, "Restarting Installation Workbench"](#).

Note: Installation Workbench should not be closed if Table Conversions are running normally. Only close it if problems have occurred and conversions need to be restarted.

6.16.3.9 Restarting Installation Workbench

When you restart Installation Workbench, these items create a temporary table in the new format:

- Temp tables (used for in-place table conversions)
- Alter conversions
- Merge conversions

The temporary table is named *TableNameTCTEMP*. If you are restarting a conversion, first verify the original table was not dropped, then drop the temp table. For a Table Conversion, the base table must be in the old format. For Alter and Merge Conversions, no further action is necessary.

For performance reasons, several conversions use their own temporary table that has been defined in the specifications. The recovery for each of these may be different.

Check in the *JD Edwards EnterpriseOne Programmers Guide* for individual Table Conversions that may have special re-run instructions.

To rerun a conversion, reset the status of the conversion in Table Conversion Planner from 35, 45, or 50 to 30. If a conversion is still running when workbench is restarted, leave its status at 45.

6.16.3.10 Troubleshooting Table Conversions

If Table Conversion Workbench fails to submit a conversion to the server, such as services are not running, it sets the conversion status to 50 and it does not submit any more conversions.

6.16.3.10.1 Enabling the Print UBE Job Log When you are upgrading, the Print UBE job log on your IBM i Enterprise Server can help you debug any potential Table Conversion problems. For example, if you are trying to insert alpha data into a

numeric column your Table Conversion will fail and you can only isolate the problem by analyzing the Print UBE job log.

By default, the Platform Pack installer configures these `jde.ini` settings on your Enterprise Server, which enable the Print UBE job log:

```
[AS400]
PrintUBEJoblog=TRUE
PrintUBEJoblogOnError=TRUE
```

Note: You can set these values to `FALSE` once you have completed your upgrade.

6.16.3.10.2 General Problems This section describes these general problems:

- [TC Has No Saved Input Table Specs](#)
- [TC Input Table Does Not Exist](#)
- [Unable to Submit TC to Server](#)
- [Unknown Table Conversion Error](#)
- [Unknown Error TC Input Checking](#)
- [Conversion Program Failed](#)
- [Conversion Has Unprocessed Dependencies](#)
- [Default Environment Missing on Server](#)
- [Inconsistent Queue Definitions](#)
- [Invalid TC Max Jobs in Plan](#)
- [Security Server Turned On](#)
- [Services Inactive, Cannot Run on Server](#)
- [Submission Problems](#)

TC Has No Saved Input Table Specs

This error indicates that the table conversion cannot be run from the Table Conversion Workbench because it does not have saved input table specifications. To resolve the error, you must either fix the table conversion using TC Design Aid or run it from batch versions.

TC Input Table Does Not Exist

This error indicates that the table conversion cannot be run because the input table does not exist. This problem can be caused by DBMS or host operating system security issues. Use these steps to resolve the issue:

1. The table that is being reported as missing is the input table for the specified table conversion. Review the description of this table conversion in the online document entitled: *JD Edwards EnterpriseOne Programmer's Guide*. Usually the missing table is the based-on table in the TC Schedule, but in some cases it is not.
2. Check the `jde.log` and your security setup in the DBMS to determine whether this is a security issue. If so, take corrective actions.

3. If this is not a security issue, you must determine why the table is missing and whether you have a business purpose for this particular table conversion to be run.

Unable to Submit TC to Server

This error may occur when you choose to run your TCs on the Enterprise Server but the TC Workbench was unable to submit the TC to the server. You should check to ensure the JD Edwards EnterpriseOne services on the Enterprise Server are up and running. Also check the logs on the Enterprise Server.

Unknown Table Conversion Error

The error occurs when the table conversion shell UBE (R98405A) to due to an unknown error. If you ran the table conversion locally, check the `jde.log` and the table conversion log (if it exists). If you ran the table conversion on the Enterprise Server, check the logs on that machine.

Detailed instructions for re-running some table conversions are in the online documented entitled: *JD Edwards EnterpriseOne Programmer's Guide*. If you cannot locate any special re-run instructions for this table-conversion, use these procedures to resolve:

1. Correct the problems that caused the failure.
2. Restore tables if necessary.
3. Drop the temporary table (FTCTEMP) if necessary.
4. Re-run the process.

Unknown Error TC Input Checking

This error occurs when the Table Conversion Workbench checks the input table against the saved input table specifications in the table conversion and it encounters an unknown error. As a result, the table conversion was marked as failed. Check the `jde.log` to diagnose this error.

Conversion Program Failed

This error occurs when a scheduled table conversion program did not complete successfully. If you ran the table conversion locally, checked the `jde.log` and the TC Engine log (if it exists). If you ran the table conversion on the Enterprise Server, check the R98405A log and the TC Engine log on the server.

Detailed instructions for re-running some table conversions are in the online documented entitled: *JD Edwards EnterpriseOne Programmer's Guide*. If you cannot locate any special re-run instructions for this table-conversion, use these procedures to resolve:

1. Correct the problems that caused the failure.
2. Restore tables if necessary.
3. Drop the temporary table (FTCTEMP) if necessary.
4. Re-run the process.

Conversion Has Unprocessed Dependencies

This error occurs when a conversion program could not be launched because it is dependent on other scheduled conversion programs which did not run to successful completion. You must correct the errors for the conversion program on which this conversion is dependent. You must either run Convert All or run the dependency

conversion and then run this conversion. If you choose Convert All, it will automatically retry this table conversion.

Default Environment Missing on Server

This error occurs if your Upgrade Plan indicates to run table conversions on the server and the default environment defined in the server `jde.ini` file has not been installed on your server. For example, JD Edwards EnterpriseOne includes this default setting in the `jde.ini` on your Enterprise Server:

```
[SERVER ENVIRONMENT MAP]
JDEPLAN=PSnnn
```

where *nnn* is the JD Edwards EnterpriseOne application release level. For example, 910. Ensure that the specified environment exists.

Inconsistent Queue Definitions

This error occurs if your Upgrade Plan indicates to run table conversions on the server and the default queue defined in Queue Control Status Master (F986130) in JDEPlan does not exist in the Queue Control Status Master on the Enterprise Server. To resolve the error condition, perform either of these steps:

1. Change the default queue defined in the planner environment to match the queue that is defined on the server.
2. Sign in to the Deployment Environment (for example, DEP910), or a deployed development client, and add a queue definition on the server to match the default queue that is defined in the Planner environment.

In either case, you must run application P986130 to update the table.

Note: This error may also be generated by a failure to open the Queue table in the System datasource. Use the `jde.log` to verify if this is the case.

Invalid TC Max Jobs in Plan

This error indicates your plan has specified the maximum table conversion job as 0 while the Table Conversion Workbench is assuming the maximum jobs are set to 4.

Security Server Turned On

This error indicates you have turned on the Security Server in the `jde.ini` file on the Deployment Server, Enterprise Server, or both. As previously stated, you cannot run Table Conversions with the Security Server turned on. Refer to the `jde.log` for more details.

This setting in the `jde.ini` indicates whether the Security Server is turned on:

```
[SECURITY}
SecurityServer=value_or_blank
```

In order to turn off the Security Server, the value for the `SecurityServer=` setting must be blank.

Services Inactive, Cannot Run on Server

This error occurs if your Upgrade Plan specifies to run table conversions on the Enterprise Server but the services are not started. You must ensure that the JD

Edwards EnterpriseOne services on your Enterprise Server are up and running before running table conversions on the server.

Submission Problems

This section discusses troubleshooting submission problems for these tables:

- [F9843 and F9843T](#)
- [F98405](#)
- [F984052](#)
- [F986110](#)
- [F986130](#)

F9843 and F9843T

The Table Conversion Schedule (GH9611) application reads these tables to find all conversions that will be run. They are conversion types 3, 31, and 32. Table Conversions that must run on the Deployment Server are flagged here.

These tables reside in the System Local and System - 910 data sources.

F98405

The Workbench Status (GH961) application reads this table to find table conversion scheduler records (among others) that are copied from F9843 to F98405 during Finalize Plan. The Workbench uses records in this table, which resides in the Planner - 910 data source..

F984052

The History (GH9611) application uses this table to store table conversion history. A new record is created in this table every time a conversion is launched. The R98405A report writes the status for a completed conversion to this table. Table Conversion Workbench polls this table for completion status and updates the status in the F98405 table.

This table resides in the System - 910 data source. The table is originally mapped to the OneWorld Planner The B7334 data source. It is copied to the System - 910 data source and remapped during Release Master. The table must be in the System data source so conversions on the Enterprise Server can communicate their completion status back to Table Conversion Workbench.

F986110

The Submitted Reports (GH9011) application creates records in this table for conversions that are launched on the server. They can be viewed using Submitted Reports. This table resides in the Server Map data source.

F986130

The Job Queues (GH9013) application is used to define job queues that can be used by the Installation Planner in the JDEPLAN environment. If any queues have been defined, they are copied to the system data source during Release Master. If no queues have been defined, Release Master creates default queues in the system data source. The Enterprise Server is mapped to the table in the system data source. The job queues can be viewed by logging into the DEP9 environment and opening the Job Queues application. This table resides in the System - Local and System - 910 data sources.

6.16.4 Verifying the Table Conversion Process

To verify that the table conversion process completed successfully:

- [Section 6.16.4.1, "Understanding Table Conversion Dependencies"](#)
- [Section 6.16.4.2, "Verifying Table Conversions"](#)
- [Section 6.16.4.3, "Understanding Table Format Verification"](#)
- [Section 6.16.4.4, "Rerunning Table Conversion Programs"](#)

See Also

JD Edwards EnterpriseOne Programmers Guide for a more thorough understanding of the table conversions performed during the upgrade process.

For each Table Conversion that runs locally, you will see error messages in `jde.log` similar to the following:

- TAMInitX (*path*\jdeblc.xdb): Error opening index file "*path*\jdeblc.xdb" : The system cannot find the path specified. WinErrNum=3.

The path name will vary by environment and release, where references to TAM are only applicable to releases prior to Release 8.12, at which point TAM is superceded by Metadata.
- 2248\2420 Thu Dec 26 11:18:36.326 ODBC_U1.C823 ODB0000154 - SQLPrepare failed. Table F00926, ODBC DSN JDE_DEV.
- 2248\2420 Thu Dec 26 11:18:36.326 JDBODBC.C2695 ODB0000027 - JDBODBC_DescribeTable failed. Table F00926.

The exact syntax varies by database type and environment.

- Because they do not affect the table conversion, you can disregard any error messages for these tables:
 - F00921
 - F00926
 - F98830
 - F9100TCTEMP

6.16.4.1 Understanding Table Conversion Dependencies

Table conversions with a conversion sequence number of 99 or below are technical table conversions; conversions with a sequence number of 100 or above are application (business data) conversions. The sequence numbers are shown in the Conv Seq column. Note that application conversions are dependent on technical conversions: all technical conversions must complete successfully for application conversions to complete.

6.16.4.2 Verifying Table Conversions

Before continuing the upgrade process, verify that the table conversions ran successfully. Run R9698711 from the Deployment Server. Verify that the amount of data in the log file and the converted table are the same.

The report R984052 lists all of the conversions that ran. Refer to the *JD Edwards EnterpriseOne Programmers Guide* for information on verifying individual table conversions.

Note the following information about the table conversions:

- Conversion programs listed as Process Type 1 generate a .pdf and a .log file in the printqueue directory.
- Conversion programs listed as Process Type 5 generate a .log file in the printqueue directory.
- The table conversions shown below are cumulative: for whatever previous version you are upgrading from, the conversions shown in the table are carried out, plus conversions shown in all subsequent tables. For example, if you are upgrading from OneWorld version B73.3, the conversions shown in the first table occur, plus those shown in the subsequent tables.

Note: The table F76B0411 is not shipped in Xe base. If you did not apply the localization ASU which contained the table, you will see a status of 'TC Inp Spec\Tbl Mismatch ' next to this TC. This is normal.

6.16.4.3 Understanding Table Format Verification

The best way to verify table formats is to run R9698711 (version XJDE0001). Audit results of TC Workbench to make sure all tables in correct format. Change Environment name to your upgraded environment.. This UBE lists all of the tables that differ from the specifications.

Before You Begin

Before you run the report, you should add Data Selection with these values:

Operator	Left operand	Comparison	Right operand
Where	BC Product Code (F9860) (SY)	is not equal to	"55,89"
And	BC Data Class (F9860) (CLDF)	is equal to	" ,B,T"
And	BC Object Type (F9860) (FUNO)	is equal to	"TBLE"

Operator	Left operand	Comparison	Right Operand
Where	BC Product Code (F9860) (SY)	is not equal to	"55,89"
And	BC Data Class (F9860) (CLDF)	is equal to	" ,B,T" where the first value is a space character that specifies blank, B specifies Business Data, and T specifies Control Tables.
And	BC Object Type (F9860) (FUNO)	is equal to	"TBLE"

Processing Options

Runtime options

Environment for which you want to run the compare. Will determine which Central Objects to use and where the tables are (OCM). Defaults to logon environment.

Summary/Detail
 0 - List all tables
 1 - Only list tables in error
 2 - Ignore missing specification errors
 3 - Ignore missing table errors

Table Data Source
 This overrides OCM. Usually you should let OCM determine which data source the table is in.

Central Objects Data Source
 Will override the Central Objects Data Source for the specified Environment. Should not usually be supplied.

Enter the type of Specs used to verify tables. The default is Local TAM.
 0 - Central Objects (RDB)
 1 - Local TAM

OK **Help** **Cancel**

Or, look in the table conversion logs that are created in the pathcode printqueue directory. Review the table conversion logs, JDE.LOG and JDEDEBUG.LOG, to make sure the table conversion program finished successfully. The table conversion log states Completed Successful or Completed with Errors.

If the table conversion finishes with errors, review the entire table conversion log for specific error messages, and then review the JDE.LOG and JDEDEBUG.LOG for more specific messages about the failure.

If the table conversion log states that the table conversion finished successfully, review the table being converted in the data source that it is mapped to for the new release. The following task shows what to verify for each table being converted.

6.16.4.3.1 Verifying Table Formats To verify table formats:

1. Verify table conversions that have a conversion sequence number of 99 or below by reviewing the .pdf and .log files generated to the printqueue directory.

These conversions also can be verified by reviewing the log for R8998504.

2. Verify conversions with a conversion sequence number of 100 or above and process type 5 by reviewing the .log file generated in the printqueue directory. The following illustration shows the last few lines of a sample .log file for the R8903B20 report:

```

TCEngine Level 1 D:\E910\system\TCEngine\tcinit.c(1581):
    Format F03B20 contains 55 column(s)
TCEngine Level 1 D:\JDEdwards\E910\system\TCEngine\tcinit.c(1581):
TCEngine Level 1 D:\JDEdwards\E910\system\TCEngine\tcinit.c(1581):
    Format F03B20 contains 61 column(s)
TCEngine Level 1 D:\JDEdwards\E910\system\TCEngine\tcinit.c(1581):
TCEngine Level 1 D:\JDEdwards\E910\system\TCEngine\tcinit.c(1581):
    There is ER logic associated with the event Row Fetched from F03B20
TCEngine Level 1 D:\JDEdwards\E910\system\TCEngine\tcinit.c(1581):
    System function Insert Row into format F03B20
TCEngine Level 1 D:\JDEdwards\E910\system\TCEngine\tcinit.c(1581):
TCEngine Level 1 D:\JDEdwards\E910\system\TCEngine\tcrun.c(689):
    Conversion R8903B20 XJDE0001 done successfully.
    Elapsed time - 1.843000 Seconds.
TCEngine Level 1 D:\JDEdwards\E910\system\TCEngine\tcrun.c(697):
    Fetched 11 rows from F03B20
TCEngine Level 1 D:\JDEdwards\E910\system\TCEngine\tcrun.c(705):
    Inserted 11 rows, failed to insert 0 rows into F03B20

```

3. Use the information above to verify the conversion program using the following procedures:
 - a. If the bottom of the .log file says the conversion was unsuccessful, review the rest of the .log from the beginning for specific errors. Also review the jde.log and jdedebug.log for more specific error information.
 - b. If the bottom of the .log file says that the conversion was successful, review the file format of the physical file to see that the number of columns has changed.

From the example .log shown above, F03B20 should now have 61 columns in the target data source instead of 55.
 - c. Verify the record count in the physical file based on the log information.

From the example .log shown above, F03B20 should now have 11 rows in the target data source.
 - d. If the .log file says that there were insert failures, review the jde.log and jdedebug.log for more detailed information.
 - e. If the conversion cannot be verified through the above procedures, check the table in [Section 6.16.4.2, "Verifying Table Conversions"](#) for more specific verification information.

Troubleshooting

For more information about which tables have been changed or added in the new release, see the *JD Edwards EnterpriseOne Database Changes Guide* for the release from which you are upgrading.

6.16.4.4 Rerunning Table Conversion Programs

To rerun table conversion programs:

1. Technical conversions can be rerun without restoration. For process type 5 only, when you run a table conversion program from Table Conversion Workbench, the following occurs:

- All table conversions should be rerun through the Table Conversion Workbench. If the status of the conversion is 60, you might need to change it back to 30.
- The table conversion engine uses the object map to locate the table being converted in both the From and To environments.

In the upgrade to Release 9.1, most application tables being converted will reside on the same data source on the from and to environments. This creates an in-place conversion.

The physical table on the data source should be formatted following the specifications for the previous release.

The table conversion engine creates a temporary table on this data source. Drop all temporary tables before starting the Table Conversion rerun procedure. The temporary file name has the notation <Table>TCTemp 'for example, F03B20TCTEMP.

To find these tables:

- Test List is Upgrade only
- Enter these commands:

```
STRSQL
SELECT SYSTEM_TABLE_SCHEMA, TABLE_NAME FROM SYSTABLES
WHERE TABLE_NAME LIKE 'F%TCTEMP'
DROP TABLE PRODDTA\F0101TCTEMP
```

- Do not drop temp tables for conversions still running.
 - Enter this command:
- ```
CLRPFM PRODDTA\F40941
```
- If restarting a conversion, first verify the original table was not dropped, then drop the temp table. For a Table Conversion, the base table must be in the old format. For Alter and Merge Conversions, this is not necessary.

Data is copied to the temporary table, the original table is deleted, and the temporary table is renamed to the original table name.

Clear out tables F40941, F40942, F40943, F0618TA, F42140A, F42150A, F42160A, F3201, F3211, F3215, F3216, F3290.

See the *JD Edwards EnterpriseOne Programmers Guide* for any additional instructions when rerunning Table Conversions.

2. If the table conversion program has run but the table is still in its original format in the data source for the release from which you are upgrading, run the conversion program without file restoration. If the table conversion program has run but the table format in the data source has changed in the release from which you are upgrading, restore the table to its original format before running the conversion program again.

When the table conversion engine runs an in-place table conversion, the temporary table required for an in-place conversion could be created and never dropped. In this case, rerunning the conversion program fails when creating the temporary table because the table already exists. To resolve this, drop or rename



the temporary table before rerunning the table conversion. The temporary table has the name of the table being converted followed by the initials "TC" followed by the report name of the conversion program being run. The temporary name has the notation TableTCTEMP, for example, F03B20TCTEMP.

3. When the upgrade is complete and you are satisfied with the results, delete all SY = 89 tables from their data sources.

### 6.16.5 Deferring Index Builds During Table Conversion Workbench (Tools Release 9.1 Update 2)

Beginning with Tools Release 9.1 Update 2, before running the Installation Workbench, you can mark specific Table Conversions to direct the TC Engine not to build indexes during those conversions. You may wish to defer building indexes on such table conversions where:

- The underlying table is very large (for example, F0911)
- The underlying table is very large and is converted several times during the Table Conversion Workbench. For example, if upgrading from Xe or ERP8:
  - F42199
  - F49219
  - F42119
  - F43199
  - F43121
  - F4101
  - F4102
  - F3111
  - F0618
- You are planning to do a Unicode conversion directly after the Upgrade and before you return the system to the end users. (The Unicode conversion recreates all indexes in any case).

When you mark a table with the Defer Index flag, the TC Engine creates the primary key and any other unique keys on that table before marking the conversion as complete. In almost all cases there is only one unique key on the tables and that is the primary key. However, there are a few tables with more than 1 unique key (for example F0902 has 4 unique keys, while F4101 has 3 unique keys).

---

**Caution:** The absence of non-unique keys will not stop EnterpriseOne from working, but will have a severe impact resulting in poor performance. If you choose to defer index builds, you are responsible for creating the missing indexes once the Workbench is complete.


---

To use the Defer Index Build functionality, you must have the latest Planner Update and JD Edwards EnterpriseOne Tools Release 9.1 Update 2 or higher on both Deployment Server and Enterprise Server. The Planner Update must be applied to the Pristine path code (PS910) and an update package must be built and deployed to PS910.


To use the Defer Index Build functionality:

1. Run the Custom Plan application on menu GH961.
2. Drill down into Upgrade Plan, highlight Table Conversions, click on Select, and go into TC Planner.

If Tools Release 9.1 Update 2 or higher is not installed on the Deployment Server, the Advanced button will be disabled as shown in this example:




If Tools Release 9.1 Update 2 or higher installed on the Deployment Server, the Advanced Button is available as shown in this example:



3. On Table Conversion Planner, click on **Advanced** button. As shown in the example below, a new column called Defer Index is displayed next to the Dependency Sequence column.






**Note:** By default, all values for the Defer Index column are set to N (do not defer index build).

4. Change the value in the Defer Index column to Y for any TC for which you do not want to build indexes during the Table Conversion Workbench.
5. Click the **Save** button.
6. Run the Upgrade plan to execute the Table Conversion Workbench that includes your specified Defer Index settings. If the TC Workbench does not complete successfully, you will see that the Error Text / History Status field is updated with the below value for any table that was marked as Defer Index:

**\*\* Build Indexes! \*\***

Below is an example TC Workbench where the Defer Index value was set:



For the above TC Workbench results screen, the values of the Defer Index column are:

- Y

Indicates the TC Engine created the table with only Unique indexes and Primary key and returned as successful.

For TCs that have run where the "Y" was specified, you will see the **\*\* Build Indexes! \*\*** messages. This is not usually true for \*ALTER as the TC Engine does not recreate the table for \*ALTER.

■ N

Indicates the TC Engine completed successfully as it normally does, which includes the index build.

7. Review the Table Conversion Merge log (P984052).

If the TC ran with value set to Y, the Conversion Merge log (P984052) includes the **\*\* Build Indexes! \*\*** messages, as shown in the example below:

| CONC | Plan Name | Target Environ | Prev Environ | Cnv Type | Object Name | Cnv Sts                 | Conversion Status | Start Date | Beg Time | Compl Date | End Time | Program Name | Version | Defer Index | Data Item    |
|------|-----------|----------------|--------------|----------|-------------|-------------------------|-------------------|------------|----------|------------|----------|--------------|---------|-------------|--------------|
| CONC | STGACL    | STGACL         | 3            | F01131M  | 2           | Conversion Finished Nor | 3/21/20           | 15:32:1    | 3/21/20  | 15:32:2    |          | *ALTER       |         | N           |              |
| CONC | STGACL    | STGACL         | 3            | F01131M  | 3           | Conversion Finished Abn | 3/21/20           | 15:30:3    |          | 00:00:0    |          | *ALTER       |         | N           |              |
| CONC | STGACL    | STGACL         | 3            | F0901    | 2           | Conversion Finished Nor | 3/21/20           | 15:30:2    | 3/21/20  | 15:30:3    |          | *MERGE       | V890901 | Y           | ** Build Ind |
| CONC | STGACL    | STGACL         | 3            | F0911    | 2           | Conversion Finished Nor | 3/21/20           | 15:29:5    | 3/21/20  | 15:30:1    |          | *ALTER       |         | N           |              |
| CONC | STGACL    | STGACL         | 3            | F4101    | 2           | Conversion Finished Nor | 3/21/20           | 15:29:3    | 3/21/20  | 15:29:3    |          | *MERGE       | V894101 | N           |              |
| CONC | STGACL    | STGACL         | 3            | F0901    | 2           | Conversion Finished Nor | 3/21/20           | 15:24:5    | 3/21/20  | 15:25:3    |          | *MERGE       | V890901 | Y           | ** Build Ind |
| CONC | STGACL    | STGACL         | 3            | F3003    | 2           | Conversion Finished Nor | 3/21/20           | 15:21:0    | 3/21/20  | 15:22:0    |          | R893003F     | XJDE000 | Y           | ** Build Ind |
| CONC | STGACL    | STGACL         | 3            | F3003    | 2           | Conversion Finished Nor | 3/21/20           | 15:01:1    | 3/21/20  | 15:02:3    |          | *ALTER       |         | N           |              |

8. Review the R984052 report that runs at end of TC Workbench.

Each TC that ran with "Y" will have the **\*\* Build Indexes! \*\*** message text as shown in the example below:

R984052\_XJDE0001\_D120402\_T165255122.pdf - Adobe Reader

File Edit View Window Help

1 / 1

94%

CommentSign

|                       |                   |                               |         |              |                                |                    |         |         |         |                                 |                      |          |          |
|-----------------------|-------------------|-------------------------------|---------|--------------|--------------------------------|--------------------|---------|---------|---------|---------------------------------|----------------------|----------|----------|
| R984052               | XJDE0001          | Oracle - J.D. Edwards:        |         |              |                                |                    |         |         |         |                                 |                      | 4/2/2012 | 16:52:59 |
| Plan Name             | CONC              | Table Conversion/Merge Driver |         |              |                                |                    |         |         |         |                                 |                      | Page -   | 1        |
| Conversion/Merge Type | Application Table |                               |         |              |                                |                    |         |         |         |                                 |                      |          |          |
| Environment           | Object Name       | Description                   | Det Srs | Program Name | Description                    | Version / Bus View | Cur Seq | Dep Seq | Cur Hit | Conversion History / Error Text |                      |          |          |
| STGACLS               | STGACLS F43121    | Purchase Order Receiver File  | 60      | *ALTER       | ITCEAlter API                  |                    | 134     | 0       | 1       | Completed Normally              | ** Build Indexes! ** |          |          |
| STGACLS               | STGACLS F3003     | Routing Master File           | 60      | *ALTER       | ITCEAlterEx API                |                    | 138     | 0       | 2       | Completed Normally              |                      |          |          |
| STGACLS               | STGACLS F3003     | Routing Master File           | 60      | R893003F     | Modified Data Conversion TC fo | XJDE0001           | 139     | 138     | 2       | Completed Normally              | ** Build Indexes! ** |          |          |
| STGACLS               | STGACLS F4101     | Item Master                   | 60      | *MERGE       | ITCEMerge API                  | V894101B           | 157     | 0       | 2       | Completed Normally              |                      |          |          |
| STGACLS               | STGACLS F0911     | Account Ledger                | 60      | *ALTER       | ITCEAlterEx API                |                    | 201     | 0       | 2       | Completed Normally              |                      |          |          |
| STGACLS               | STGACLS F0901     | Account Master                | 60      | *MERGE       | ITCEMerge API                  | V890901A           | 402     | 0       | 2       | Completed Normally              | ** Build Indexes! ** |          |          |
| STGACLS               | STGACLS F01131M   | JDEM Multi Level Message      | 60      | *ALTER       | ITCEAlterEx API                |                    | 411     | 0       | 2       | Completed Normally              |                      |          |          |

9. It is important to remember that at the complete of the TC Workbench, prior to using the tables, you must manually create the missing indexes. To do so, you can use one of the following methods:

**Method One**


- a. Using the the GUI for your database (SQL Management StudioOracle Enterprise ManagerDB2 UDB Control CenterSystem i Navigator for IBM i), highlight the same table in the Pristine database (for example, F0911) and generate DDL to a file.
- b. Edit the SQL statements, substituting the tablespace names, owners, and databaselibrary for your target schema. For example, replace ps910dta with proddtaPS910DTA with PRODDTA.
- c. Run the SQL script from your database's GUI. Note that you should delete those CREATE INDEX statements that refer to indexes that already exist on the target table. The database GUI will tell you which indexes already exist.

#### **Method Two**

- a. Generate the indexes on a trial run, with jdedebug turned on, and harvest the CREATE INDEX statements from the jdedebug log.
- b. Use the GUI for your database (SQL Management StudioOracle Enterprise ManagerDB2 UDB Control CenterSystem i Navigator for IBM i) to run the identified index builds as a sql script.

#### **Method Three**

- a. Run R9698713 and select the tables where you deferred the indexes. It will create the indexes one table at a time, one index at a time. It is possible to run different versions of R9698713 from different 9.1 Admin clients, selecting different tables for each version.
- b. It is not necessary to be signed into the target environment because you can override the environment in the Processing Options. Set the value for Processing Option 3 to a value of 2 to generate only missing indexes, as shown in the screen below:



**Processing Options**

**Options**

R9698713 creates missing and mismatch indexes for each table identified by data selection.

1. Enter the name of the Environment.  
(If the data source is blank all tables for this environment are included in the verification.)

PD910

2. or Enter the name of the Data Source.  
(If both environment and data source are provided, only the tables which are mapped to this data source for the given environment are verified.)

3. Enter '0' for Proof mode, or '1' to recreate all the indexes on selected tables if any missing or mismatch indexes, or '2' to create only the missing and mismatch indexes on selected tables. (The default is proof mode.)

2

4. Enter '0' for a summary report of tables with invalid indexes or '1' to print all tables. (The default is to skip tables with correct indexes.)

0

OK Help Cancel

#### Method Four (if your business data is Unicode)

The advantage of this method is that the RSTxxx commands all do multiprocessing while building the indexes.

- a. Save the indexes for the table marked with Defer Index from the pristine library. For example:

```
SAVOBJ F0911_* PS910DTA *SAVF(X)
```

- b. Restore the indexes to the PRODDTA library. For example:

```
RSTOBJ OBJ(*ALL) SAVLIB(PS910DTA) DEV(*SAVF) SAVF(X) OPTION(*NEW)
RSTLIB(PRODDTA)
```

#### Method Five (if your business data is not Unicode, such as when upgrading from Xe)

- a. Temporarily create the table in another non-Unicode datasource using OMW in 9.1. For example, another such non-Unicode datasource is **Control Tables - Prod**.

- b. Save the indexes from the non-Unicode datasource. For example:

```
SAVOBJ F0911_* PRODC TL *SAVF(X)
```

- c. Restore the indexes from the SAVF of PRODC TL to the PRODDTA library. For example:

```
RSTOBJ OBJ(*ALL) SAVLIB(PRODCTL) DEV(*SAVF) SAVF(X) OPTION(*NEW)
RSTLIB(PRODDTA)
```

- d. After the restore is done, drop the "temporary" table from PRODCTL.

## 6.17 Understanding Obsolete Tables

This section discusses these tables that were obsoleted in Release 8.9 at either system code 88 or 89.

- [Section 6.17.1, "System Code 88 Obsolete Tables"](#)
- [Section 6.17.2, "System Code 89 Obsoleted Tables"](#)

### 6.17.1 System Code 88 Obsolete Tables

The following lists obsolete tables which may be deleted from an environment after the table conversion for that environment has completed successfully.

---



---

**Note:** You will not have all of the below obsolete tables.

---



---

F00001  
 F0004SL  
 F0004HI  
 F0004LI  
 F0004LS  
 F0004S  
 F00053  
 F0005LS  
 F000531  
 F000532  
 F0005HI  
 F0005LI  
 F0005S  
 F0017  
 F0005SL  
 F00165X  
 F00165XJ  
 F0016D  
 F00171  
 F0040  
 F00172  
 F00173  
 F0018VI  
 F0031  
 F00530  
 F009109  
 F00530E  
 F00530P  
 F00825  
 F0090  
 F0101D1  
 F03465  
 F0101QA

F0101QAA  
F0114W  
F01800  
F03B01  
F03C04  
F03B15P  
F03BUI06  
F03C02  
F03C03  
F03C05  
F03C15  
F03C11  
F03C12  
F03C13  
F03C14  
F03C16  
F06400  
F03CUI01  
F04516  
F04550  
F04552SB  
F06403  
F07402  
F06406  
F06410  
F06445  
F07401  
F07403  
F07409  
F07404  
F07405  
F07406  
F07408  
F07410  
F07416  
F07411  
F07412  
F07413  
F07414  
F07417  
F07422  
F07418  
F07419  
F07420  
F07421  
F07423  
F07431  
F07424  
F07425  
F07426  
F07429  
F07432  
F07441  
F07434  
F07435

F07437  
F07438  
F07442  
F07448  
F07443  
F07444  
F07445  
F07447  
F07449  
F085541  
F07451  
F075506  
F078332  
F078332A  
F085542  
F09UI001  
F087710  
F08901WF  
F0911Z3  
F09E111  
F09UI002  
F14104  
F09UI003  
F09UI012  
F105503  
F12UI001  
F14110  
F30UI003  
F14111  
F16UI002  
F3003J  
F3016J  
F30UI009  
F31UI003  
F3104  
F3112J  
F31950  
F31UI001  
F31UI004  
F3211Z1  
F31UI005  
F31UI410  
F31UI418  
F3211Z  
F3411Z1  
F34A04  
F34A00  
F34A01  
F34A02  
F34A03  
F34A05  
F34W01  
F34A06  
F34A07  
F34A08

F34A09  
F34W012  
F34W04  
F34W02  
F34W03  
F34W031  
F34W032  
F34W05  
F34W10  
F34W06  
F34W07  
F34W08  
F34W09  
F34W11  
F34W142  
F34W12  
F34W121  
F34W13  
F34W141  
F34W15  
F34W19  
F34W16  
F34W17  
F34W17B  
F34W18  
F34W20  
F34W25  
F34W21  
F34W22  
F34W23  
F34W24  
F34W26  
F35UI01J  
F34W27  
F34W28  
F34W29  
F34W30  
F4021W  
F4311KAY  
F40336  
F40343  
F4213  
F4215T  
F48S618T  
F48126  
F48098  
F48099  
F4810  
F4811  
F489111  
F53015  
F49090  
F49711  
F52801  
F53001



F5302  
F7302  
F53021  
F53024  
F53034  
F55MOIN  
F74100  
F74P04W  
F74800  
F74M0411  
F74P0018  
F74P03BW  
F74S0101  
F75K0101  
F74S347  
F74S349  
F74SN34  
F75C01Z1  
F75K0201  
F76012  
F75K0211  
F75KUI01  
F760018A  
F760090A  
F76031  
F7691SSA  
F7611BA  
F7618B  
F7691CBA  
F7691CSA  
F76A01  
F76A05  
F76A02  
F76A03  
F76A04  
F76A0403  
F76A06  
F76A8121  
F76A07  
F76A31  
F76A40  
F76A8120  
F76A8122  
F76A9003  
F76A8123  
F76A8124  
F76A8125  
F76A9002  
F76A9004  
F76AUI25  
F76A91  
F76A92  
F76A94  
F76AUI15  
F76AUI87

F76CI1  
F76AUI94  
F76AUI95  
F76B126  
F76C4001  
F76CI2  
F76CUI02  
F76CI3  
F46CT1  
F76CT2  
F76CUI01  
F76CUI03  
F76H0904  
F76H0301  
F76H0401  
F76H0402  
F76H0903  
F76H0905  
F80004  
F76H0906  
F80001  
F80002  
F80003  
F80005  
F8009E10  
F800110  
F800130  
F800140  
F8009E00  
F8009E20  
F800910  
F800900  
F800900S  
F800901  
F800901S  
F800920  
F8011  
F800930  
F800940  
F80100  
F80101  
F80111  
F801610  
F80151  
F80160  
F801600  
F801600S  
F801620  
F80300  
F801630  
F80170  
F80171  
F80200  
F804110  
F804300S

F804210  
F804210S  
F804220  
F804300  
F804301  
F804305  
F804302  
F804302S  
F804303  
F804304  
F804810  
F8399  
F809E00S  
F81A13  
F81A14  
F81A15  
F8800  
F8916V  
F8916  
F8916L  
F8916RS  
F8916S  
F8916V2  
F8926RS  
F8916X  
F8916Y  
F8916Z  
F8926  
F8926Y  
F9002HI  
F8926Z  
F89500  
F89500G  
F89601  
F9002LI  
F91013  
F9002LS  
F9002S  
F9002SL  
F9066  
F95000  
F9752  
F95020  
F950900  
F95100  
F9751  
F9753  
F98612  
F9754  
F98SYSGR  
F98311  
F98500  
F986120  
F98768  
F98614

F98701  
 F98744  
 F98751A  
 F98790  
 F99FSAR3  
 F98FLATM  
 F99FCOEX  
 F99FSAR1  
 F99FSAR2  
 F99FST02  
 FD3N015  
 F99F9911  
 F99WFMSG  
 F99WFSYS  
 FD3N010  
 FD3N017  
 FD3N025A  
 FD3N018  
 FD3N020  
 FD3N021  
 FD3N025  
 FD3N026  
 FD3N056  
 FD3N030  
 FD3N040  
 FD3N050  
 FD3N055  
 FD3N120L  
 FD3N901  
 FD3N120P  
 FD3N120T  
 FD3N120W  
 FD3N120X  
 FD3N902  
 FD3N913  
 FD3N903  
 FD3N904  
 FD3N910  
 FD3N911  
 FD3N915  
 JDECODE

## 6.17.2 System Code 89 Obsoleted Tables

For system code 89 there are two types of obsoleted tables:

- Business Data tables that JD Edwards EnterpriseOne no longer uses, but are required to access the data within for the upgrade. It is recommended to back these up somewhere until they're satisfied everything runs as should be.
- New temporary tables that are used by TCs. After the TC runs successfully, these can be deleted. They are not full tables, just a couple of columns used for performance (with millions of rows...) These are:

---



---

**Note:** You will not have all of the below obsolete tables.

---



---

F00151  
F05290T  
F06116T  
F06116TZ  
F0618TA  
F063951T  
F0901T  
F0911T  
F0911Z1T  
F0917S  
F186407D  
F186407T  
F32UI002  
F3214  
F3294  
F3294Z  
F32941  
F32942  
F32943  
F32944  
F32945  
F3295  
F3296  
F3296T  
F32961  
F329611  
F4009T  
F4100T  
F41001T  
F4101TT  
F4102TT  
F31172TE  
F4072TEM  
F41021A  
F40344A  
F42005A  
F42140A  
F42150A  
F42160A  
F31172TE  
F42199A  
F4311TA  
F43199A  
F43121TA  
F4211A  
F4211B  
F4074TEM  
F4094TEM  
F42119A  
F42119B  
F4600T  
F4600TPU  
F46011T  
F46091T  
F4611T

F4611TPU  
F7460  
F750401A

## 6.18 Understanding Specification Table Merges

Specification Table Merge Workbench runs the batch applications that merge custom modifications into the new specification tables. It then updates the Table Conversion Scheduler table (F98405) to indicate completion, and writes a conversion log record. The Object Librarian and Versions List merges are now a part of the specification merge.

For all users, the Specification Merge merges data in the following order:

- Object Librarian
- Versions
- Specifications

For users installing an alternate language, the Specification Merge Workbench merges the central objects and language text from the previous release into the new central objects database.


The central objects tables contain the alternate language records needed for displaying text in the selected language. Language-enabled tables include the Processing Option Text table (F98306), the Report Design Aid Text Information table (F98760), and the Forms Design Aid Text Information table (F98750). Depending on the environment choices made during the English installation, you might have several sets of central objects; for example, one set for each environment loaded during the English-language installation.

This section discusses:

- [Section 6.18.1, "Merging Specification Tables"](#)
- [Section 6.18.2, "Restarting the Specification Merge"](#)

### 6.18.1 Merging Specification Tables

To merge your specification tables:



To merge your specification tables:

1. On Specification Table Merge Workbench, choose Merge All from the Form menu.  
If you are installing an alternate language, the Plan Name field on the Specification Table Merge Workbench form will contain the name of your language plan.
2. After the merge finishes, verify the output of the report that is produced.

### 6.18.2 Restarting the Specification Merge

If the Specification Merge stops with a status of 50 before it completes successfully, you can restart it from the point at which it stopped. If the merge completed successfully, you can skip this task and continue with the next task.

To restart the specification merge:


1. Check the Specification Merge status as shown in the Specification Merge Workbench.

If the status is 50, you can restart the Specification Merge by clicking Merge or Merge All. The Specification Merge restarts and processes all non-processed objects. Before restarting, review all objects with merge status of error and follow the procedures in [Section 25.8.3.1, "Modifying the Merge Status of an Object"](#) to reset the merge status using P98700.

## 6.19 Using the Package Workbench

Package Workbench transfers the F9603 and F9631 tables from the Planner data source to the System - 910 data source. It then updates the F98404 table to indicate completion.

Use this procedure when running Workbench in attended mode or if a task break is set before Package Workbench. Refer to the *JD Edwards EnterpriseOne Tools Package Management Guide* for complete information about building and configuring packages.



1. On Package Workbench, review your packages.
2. Select Configure from the Form menu.

## 6.20 Using Remote Location Workbench

---

**Note:** This workbench only appears when Remote Locations have been set up.

---

Remote Location Workbench loads business (master and constant), control, data dictionary, and system tables from base location to remote location servers, by launching different versions of R98403 (XJDE0043, XJDE0044, XJDE0045, XJDE0046 and XJDE0047). It also pushes delivered packages to primary Deployment Servers at remote locations by launching the multi-tier UBE (R98825C). This workbench is processed only if you opted to install remote locations and chose to load replicated data and push packages.



Use this procedure when running Workbench in attended mode or if a task break is set before Remote Location Workbench.

## 6.20.1 Configuring Remote Locations

To configure remote locations:

| Action          | Location | Parent Location | Library List | Package Name | Program Name | Version  | Detail Status | Description         |
|-----------------|----------|-----------------|--------------|--------------|--------------|----------|---------------|---------------------|
| Package Push    | SEATTLE  | DENVER          |              | PD900FA      | R PP_100     | XJDE0001 | 20            | Finalized           |
| Repl - System   | SEATTLE  | DENVER          | 00PD910      |              | R SY_100     | XJDE0043 | 20            | Finalized           |
| Repl - DD       | SEATTLE  | DENVER          | 100PD910     |              | R DD_100     | XJDE0044 | 20            | Finalized           |
| Repl - Control  | SEATTLE  | DENVER          | 100JPD910    |              | R CT_100     | XJDE0045 | 20            | Finalized           |
| Repl - Control  | SEATTLE  | DENVER          | 100PD910     |              | R CT_100     | XJDE0045 | 70            | Duplicate Conversic |
| Repl - Constant | SEATTLE  | DENVER          | 100PD910     |              | R CO_100     | XJDE0046 | 70            | Duplicate Conversic |
| Repl - Constant | SEATTLE  | DENVER          | 100JPD910    |              | R CO_100     | XJDE0046 | 20            | Finalized           |
| Repl - Master   | SEATTLE  | DENVER          | 100JPD900    |              | R MS_100     | XJDE0047 | 20            | Finalized           |


To configure your remote locations:

1. On Remote Location Workbench, Release 9.1 displays all remote location activities in the detail area.
2. On the Form menu, select Configure to launch the workbench.
3. After all remote location activities are complete, click Next.

## 6.21 Finishing Installation Workbench

---

**Note:** In order to avoid issues with the JD Edwards EnterpriseOne Data Dictionary after an Upgrade, if you are running Table Conversions on the Enterprise Server, the Installation Workbench displays the following Message:



This message warns that before using the upgraded environment, you must delete the gbltbl, ddtxt, and dddict spec files from the target path code on the Enterprise Server. Failure to do this usually causes data corruption due to customized Display Decimals.

At this point you should delete these spec files as instructed, and then click the **OK** button in the Message to continue.

---

To finish the Installation Workbench:

1. From Congratulations, on the Form menu, click Finish.
2. From Work with Installation Plans, click Close.

---

**Note:** Post Install Procedures still need to be completed from a client. See [Chapter 11, "Performing Post Upgrade Tasks"](#).

---

---

## Working With the Enterprise Server

This chapter contains these sections:

- [Section 7.1, "Verifying the Enterprise Server Installation Using PORTTEST"](#)
- [Section 7.2, "Starting Network Services on the Enterprise Server"](#)
- [Section 7.3, "Stopping Network Services on the Enterprise Server"](#)
- [Section 7.4, "Creating an Output Queue for the Default Printer"](#)
- [Section 7.5, "Creating the Job Queue"](#)
- [Section 7.6, "Working with OCM Generation"](#)
- [Section 7.7, "Setting Up a Printer on the Enterprise Server"](#)
- [Section 7.8, "Enabling Multiple Concurrent Table Conversions"](#)

### 7.1 Verifying the Enterprise Server Installation Using PORTTEST

---

**Note:** When running PORTTEST after installing the Enterprise Server, the test returns a failure message. This is because it is not able to access the F0902 table at this time, (the format of the F0902 table changes during the Table Conversion Workbench). Ignore any errors relating to accessing the F0902 table, (for example, Select all on table F0902 failed - rcode=0). Once the Workbench tasks are all complete, and the Enterprise Server is configured, rerun PORTTEST.

---

To verify the Enterprise Server installation using PORTTEST:

1. Log on to the IBM i Enterprise Server as ONEWORLD (or other Release 9.1 user).
2. On Current Release 9.1 Versions, select the version of Release 9.1 that you want to use and press Enter.
3. To verify that Release 9.1 is installed correctly on the Enterprise Server, enter these command:  
  
`GO JDEOW\A98OWMNU`
4. On the A98OWMNU menu, select selection 4 to run PORTTEST.

This program initializes a user and an environment. The program selects records from the F0902 table, which appear as messages on your screen. If messages indicating your selections do not appear, review the jde.log file. You should log on

to each environment that you installed using JDE as the user and JDE as the password.

---

**Note:** If you are running PORTTEST prior to running Table Conversions, it will fail half-way through because the F0009 and F0010 are not in the correct format.

---

**Tip:** If PORTTEST fails to run, refer to [Section 17.1, "Using the PORTTEST Checklist"](#) for diagnostic assistance.

## 7.2 Starting Network Services on the Enterprise Server

To start the network services on the Enterprise Server:

1. Log on to the IBM i Enterprise Server as ONEWORLD (or other Release 9.1 user).
2. On Current 9.0 Versions, select the version of Release 9.1 that you just installed, and press Enter.
3. The first time you start the IBM i Enterprise Server, enter these commands and options:  
  
GO JDEOW\A980WMNU  
  
select selection 6 to end JDE Server.  
  
select selection 7 to clear the IPC.
4. To start the Enterprise Server, use these options:  
  
select selection 5 to start the JDE Server.  
  
select selection 8 to display active jobs.
5. Verify that the entry NETWORK is running with PGM-JDENET N in SELW status.

## 7.3 Stopping Network Services on the Enterprise Server

To stop the network services on the Enterprise Server:

1. Log on to the IBM i as ONEWORLD.
2. On the IBM i command line, enter this command:

```
ENDNET
```

This command ends JDENET from an IBM i display, ends the JDENET jobs, and cleans up JDENET run-time structures.

3. On the IBM i command line, enter:

```
ENDSBS SBS(JDE) OPTION(*CNTRL)
```

where is the release to which you are installing (for example, E910).

This command ends the JDE subsystem.

4. On the IBM i command line, enter:

```
WRKACTJOB SBS(JDEx)
```

where *x* is the release to which you are installing (for example, E910).

Wait until the JDE subsystem ends before you continue.

## 7.4 Creating an Output Queue for the Default Printer

To create an output queue for the default printer:

1. Log on to the IBM i as the QSECOFR.
2. Enter this command:  
`GO JDEOW\A980WMNU`
3. Enter the appropriate selection to create an output queue.
4. Complete these fields and press Enter:

| Field                       | Description                                                                                                                                                                                                                                                                 |
|-----------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>Outqueue Name</i>        | The outqueue name for the printer.                                                                                                                                                                                                                                          |
| <i>Printer IP Address</i>   | The network address of your printer.                                                                                                                                                                                                                                        |
| <i>Remote Printer Queue</i> | You are required to set the remote printer queue (parameter RMTPTQ) to something other than ( ` ) and ( ' ) for some printers. For example, you must set this parameter to PASS for the IBM network Printer 4317. See the printer's user manual for additional information. |

## 7.5 Creating the Job Queue

To create the job queue:

1. Log on to the IBM i as the QSECOFR.
2. Enter this command:  
`GO JDEOW\A980WMNU`
3. From the menu, select this option:  
`11 - Create Job Queue`
4. To determine the unused sequence number, enter this command:  
`DSPSBSD SBSD(QBATCH)`

Select the option for Job Queue Entries, and then record an unused sequence number.

## 7.6 Working with OCM Generation

This section discusses:

- [Section 7.6.1, "Understanding OCM Mappings"](#)
- [Section 7.6.2, "Understanding Data Source Setup"](#)
- [Section 7.6.3, "Understanding OCM Creation"](#)
- [Section 7.6.4, "Understanding OCM Customization"](#)

## 7.6.1 Understanding OCM Mappings

JD Edwards EnterpriseOne does not ship Object Configuration Manager (OCM) records for standard environments in Release 9.1. They are generated when you finalize an installation plan. OCM is created based on the Data Class for data sources and for a table or GT object. The Data Class is stored on the Data Sources By Environment (F98511), Data Source Master (F98611) and Object Librarian Master (F9860) tables.

## 7.6.2 Understanding Data Source Setup

Before OCM can be created, you must configure your data sources. Data source configuration and prompting is driven by the data in the F98511 table.

The first set of data sources to be configured is the Enterprise Server data sources. This includes the Server Map data source. Also, logic data sources are automatically configured without prompting. OCM records are not created for the server map data source. UBE, BSFN, RTE, and XAPI mappings are created for the logic data sources.

The next set of data sources to be configured is the shared data sources. This includes System, Data Dictionary, and Object Librarian data sources. The first time these data sources are configured, the shared data source template (F98511.SPLL = \*SHARED) is copied and tokens are replaced in the data source name and properties to create the shared data source records (F98511.SPLL = DEFAULT). These defaults are then used to create the data source definition in the F98611 table. If record in the F98611 tables already exists, the defaults from the F98511 table are overridden by the current definition. The user is then optionally prompted to customize the data source.

The last set of data sources is the environment data sources. A set of data sources is configured for each environment. This includes Business Data, Control Tables, Central Objects and Versions.

The environment data source template (F98511.SPLL = \*ENV) stores defaults for environment data sources. As data sources are configured for an environment, these records are copied and tokens are replaced in the data source name and properties to create records for the environment (F98511.SPLL = *Environment Name*). These defaults are then used to create the data source definition in the F98611 table. If records in the F98611 table already exists, the defaults from the F98511 table are overridden by the current definition. The user is then optionally prompted to customize the data source.

Given that the standard environments do not always follow the defaults that are specified in the \*ENV template, JD Edwards EnterpriseOne provides preconfigured records for the standard environments. Thus, the \*ENV template is only used for custom environments.

## 7.6.3 Understanding OCM Creation

After your data sources have been defined and the plan is complete, the plan is finalized. OCM is created during finalization.

This section describes:

- [Section 7.6.3.1, "Understanding Database Data Sources"](#)
- [Section 7.6.3.2, "Understanding Logic Data Sources"](#)

### 7.6.3.1 Understanding Database Data Sources

The process finds the data class for each table or GT object in Object Librarian (F9860.SICLDF). Based on the environment that is being configured and the data class

for the object, the data source name is fetched from F98511. If a record is not found, it looks for a record for the data class where environment name is DEFAULT (to determine whether it should be mapped to a shared data source). If a record is not found, no mapping is created and the table is effectively mapped to the default data source. If a record is found and that record is set as the default mapping data source (F98511.SPDFLTMAP), a mapping with object name DEFAULT is created; otherwise the actual object name is used. Mappings are not created for tables in the Planner and Internal data classes.

### 7.6.3.2 Understanding Logic Data Sources

The OCM generation algorithm for UBEs and BSFNs are identical to each other, but the output depends on whether the default mapping is LOCAL or an Enterprise Server.

The following table shows the default mappings for UBE and BSFN objects.

|             | Base Environment           | HTML Web Server Environment    |
|-------------|----------------------------|--------------------------------|
| UBE or BSFN | DV910, PS910, PD910, PY910 | JDV910, JPS910, JPD910, JPY910 |
| UBE         | Enterprise Server          | Enterprise Server              |
| BSFN        | LOCAL                      | Enterprise Server              |

The algorithm is:

- If the default is LOCAL, a default mapping to LOCAL is created. Server mappings are created for any object whose Location (labeled Business Function Location for BSFNs and Process Location for UBEs) in Object Management Workbench (OMW) is Server Only (F9860.SIBFLOCN = 3).
- If the default is Enterprise Server, a default mapping to the Enterprise Server is created. LOCAL mappings are created for any object whose Location (labeled Business Function Location for BSFNs and Process Location for UBEs) in OMW is Client Only (F9860.SIBFLOCN = 1).

## 7.6.4 Understanding OCM Customization

This section discusses:

- [Section 7.6.4.1, "Understanding Data Classes"](#)
- [Section 7.6.4.2, "Creating a New Data Class"](#)
- [Section 7.6.4.3, "Modifying the Data Source Template"](#)
- [Section 7.6.4.4, "Associating Table Data Classes"](#)

### 7.6.4.1 Understanding Data Classes

The data class is at the center of automatic OCM generation. It categorizes the type of data stored in data sources and tables, for example, in the Business Data data source the data class is **B** while in the System data source the data class is **S**. If you want to split business data into multiple data sources, you need to create a new data class, add a data source to the data source template for that data class (so Installation Planner prompts for the data source) and assign tables and GT objects to that data class. OCM will be created based on this information. You should do these steps before creating your plan.

#### 7.6.4.2 Creating a New Data Class

You must create a new data class by adding a value to the H96/DU User Defined Code (UDC) for data sources and H96/CL UDC for table and GT objects.

#### 7.6.4.3 Modifying the Data Source Template

A data source template defines the set of data sources that will be used by an environment, and the default values for the properties of the data source. They are stored in the F98511 table.

The information in this table can be edited using Data Source Templates By Environment (GH9611) program. By understanding this application, you can implement custom environment naming standards and ease the creation of environments.

Typically, you will add records to the template for new environments. The template can be found by filtering on \*ENV in the environment field. Installation Planner prompts for this set of data sources whenever a new environment is created. The first time data sources are configured for a new environment, these records are copied and tokens replaced to create records specific to the new environment.

If you want to add a new data source to a standard JD Edwards EnterpriseOne environment, enter the environment name into the filter field and add a record specifically for that environment.

Records with an environment \*LOGIC are for logic and server map data sources. They are set up when selecting an Enterprise Server.

#### 7.6.4.4 Associating Table Data Classes

A table is associated with a data class using a field on the Object Librarian table (F9860.sicldf). Table data classes can be modified two ways.

- Object Management Workbench (GH902) - Select the table in the left tree view in OMW and click Design.

Select the Install\Merge Codes tab and modify the data class value. Click OK. Modifying the data class does not affect existing OCM mappings, it is only used when creating mappings for a new environment.

- Table Data Classes - This application can be used to modify the data class for several tables at once.

This should only be used by a JD Edwards EnterpriseOne administrator. Go to GH9611 and open Table Data Classes. Use the QBE to filter the list of tables in the grid. Select one or more tables whose data class will be changed. Click Select. Type in the new data class value and click OK.

Once these three steps have been taken, planner will prompt for the new data source and create OCM mappings for the new data source whenever an environment is added to a plan and the plan is finalized.

| Environment | Object Name | User/Group | Data Source            |
|-------------|-------------|------------|------------------------|
| ENV1        | DEFAULT     | *PUBLIC    | Business Data - ENV1   |
| ENV1        | F0094       | *PUBLIC    | System - 910           |
| ENV1        | F9860       | *PUBLIC    | Object Librarian - 910 |
| ENV1        | F9200       | *PUBLIC    | Data Dictionary - 910  |
| ENV1        | F0004       | *PUBLIC    | Control Tables - ENV1  |



| Environment | Object Name | User/Group | Data Source            |
|-------------|-------------|------------|------------------------|
| ENV1        | F983051     | *PUBLIC    | Versions - PY910       |
| ENV1        | GT92002     | *PUBLIC    | Data Dictionary - 910  |
| ENV1        | GT9860A     | *PUBLIC    | Object Librarian - 910 |
| ENV2        | DEFAULT     | *PUBLIC    | Business Data - ENV2   |
| ENV2        | F0094       | *PUBLIC    | System - 910           |
| ENV2        | F9860       | *PUBLIC    | Object Librarian - 910 |
| ENV2        | F9200       | *PUBLIC    | Data Dictionary - 910  |
| ENV2        | F0004       | *PUBLIC    | Control Tables - ENV2  |
| ENV2        | F983051     | *PUBLIC    | Versions - DV910       |
| ENV2        | GT92002     | *PUBLIC    | Data Dictionary - 910  |
| ENV2        | GT9860A     | *PUBLIC    | Object Librarian - 910 |

## 7.7 Setting Up a Printer on the Enterprise Server

This section describes these tasks, which must be performed in the deployment environment:

- [Section 7.7.1, "Adding a New Printer"](#)
- [Section 7.7.2, "Defining a Default Printer"](#)

You also can print Release 9.1 reports, modify existing printers, and delete printers. These tasks are described in detail in the *JD Edwards EnterpriseOne Tools System Administration Guide*. Refer to that document to learn more about setting up a printer to run from the Release 9.1 Enterprise Server.

If a printer was installed in your previous release of Release 9.1, you do not need to re-install that printer. All printer settings are carried forward during the upgrade to this release.

### 7.7.1 Adding a New Printer

Release 9.1 provides a Printer Setup director to help you add printers. Instructions appear on each form of the director to guide you through the printer addition process. This procedure is used in conjunction with the steps that appear on the forms of the Printer Setup director.

To install your first printer:

1. On the Printers menu (GH9013), select Printers (P98616).

The Printers form appears.

2. On the Printers form, click Add Printer.

The welcome page for the Printer Setup director appears. This page describes the tasks that the director helps you perform.

3. Review the welcome page and click Next.

The Platform Information form appears. The platform type may appear by default, depending on the operating system on which Release 9.1 is running.

4. On Platform Information, complete these fields:

| Field                   | Description                                                                                                                                                                                                                                                             |
|-------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>Platform Type</i>    | Enter the platform type on which you are installing or use the visual assist button to select a platform type.                                                                                                                                                          |
| <i>Library Name</i>     | The physical printer name must be the same as the outqueue name. If you use the default QGPL library to store your outqueues, you need only enter the outqueue name in this field. Valid characters are all alpha (A-z), numeric (0-9), at ( @ ), and underscore ( _ ). |
| <i>Outputqueue Name</i> | If your outqueues reside in a library other than the default QGPL library, you need to enter the library name and the outqueue name in this field. For example, QUSRSYS\DEVDES3A. Valid characters are all alpha (A-z), numeric (0-9), at ( @ ), and underscore ( _ ).  |

- After you complete the requisite fields, click Next to access the Printer Setup form.  
Use this form to set information for the printer such as the printer model, physical location of the printer, printer definition language (PDL), and paper types.
- On the General tab, complete these fields:
  - Printer Model
  - Printer Location
- On the Details tab, in the box labeled Printer Definition Language, select one of these options:

- PostScript
  - PCL
  - Line Printer
  - Custom
8. In the Default box, specify one of the Printer Definition Language options as the default value.

You can select multiple PDLs, but only one default PDL. A user can override this default PDL at the time a batch process is submitted.

Choosing PostScript or Printer Command Language (PCL), Release 9.1 disables the Line Printer option. Choosing Line Printer, Release 9.1 disables the PostScript and PCL options.

When choosing the Line Printer option, this logic occurs:

- Release 9.1 disables the grid at the bottom of the form and any paper types you have chosen are cleared.  
JD Edwards EnterpriseOne automatically provides a printer type of \*JDE LINE PAPER for the printer.
- The Fields in the box labeled Line Printers are used to set the paper dimensions and line parameters.

This procedure is explained in later steps in this section.

The custom option uses advanced features of the printers application, which are explained in the later steps in this procedure.

9. On the Details tab, when choosing the PostScript option, the Paper Source box appears and you can change these options:

| Field                              | Description                                                                                                                    |
|------------------------------------|--------------------------------------------------------------------------------------------------------------------------------|
| <i>Max Number of Paper Sources</i> | Enter a numeric value in this field to indicate the number of paper trays this printer has available.                          |
| <i>Default Paper Source</i>        | Enter a numeric value in this field to indicate which tray number you want Release 9.1 to draw paper from as the default tray. |

10. On the Details tab, when choosing the Line Printer option, fields appear in a box labeled Line Printers, which you use to set the paper dimensions and line parameters.

Complete these fields:

| Field                      | Description                                                                                             |
|----------------------------|---------------------------------------------------------------------------------------------------------|
| <i>Characters Per Inch</i> | Enter a value to specify the number of characters in one horizontal inch.                               |
| <i>Columns Per Page</i>    | Enter a value to specify the number of characters in one line of text in the specified report.          |
| <i>Lines Per Inch</i>      | Enter a value to specify the number of lines of text in one vertical inch.                              |
| <i>Lines Per Page</i>      | Enter a value to specify the number of lines of text on one printed page.                               |
| <i>Printer Paper Width</i> | Displays a value that is calculated automatically based on the values entered in the Line Printers box. |

| Field                       | Description                                                                                             |
|-----------------------------|---------------------------------------------------------------------------------------------------------|
| <i>Printer Paper Height</i> | Displays a value that is calculated automatically based on the values entered in the Line Printers box. |

11. On the Details tab, the Custom option lets you specify a conversion filter to use.

When choosing the Custom option, a field appears beneath the Custom checkbox. Enter the name of the conversion filter you want to use or use the visual assist to select a filter from the Conversion Program Search and Select form.

12. If you do not want to change or add a conversion filter, skip to Step 16 in this task.

To change or add a conversion filter, from the Form menu, select Advanced, and continue with the steps in this procedure. The Advanced option is enabled only when Custom has been chosen.

The Work With Conversion Programs form appears.

13. Either click Add, or highlight one of the filters and click Copy or Select.

The Advanced Conversion Program form appears.

14. Change one or both of these fields:

| Field                     | Description                                                                                                                                                                                                                                                                                                                                                                                                                              |
|---------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>Conversion Program</i> | If you clicked Add or Copy on the previous form, the Conversion Program field is enabled. Enter the name of the conversion program that you want to add or copy. When making a copy, the Parameter String field is populated with the string that you highlighted on the previous form.                                                                                                                                                  |
| <i>Parameter String</i>   | <p>The JD Edwards EnterpriseOne system automatically enters the parameter string in native commands based on the host type from which you are printing and the type of printer (PostScript, PCL, or line).</p> <p>For example:</p> <pre>-s string_name -l library_name -f convertPDFToPS</pre> <p>where -s defines the string name, -l (the letter l, not the numeral 1) defines the library name, and -f defines the function name.</p> |

15. Click OK.

The Work with Conversion Programs form appears.

Click Close.

The Printer Setup form appears.

16. In the grid at the bottom of the Printer Setup form, double-click the row header for each paper type that your printer supports. A checkmark appears in the row header for each paper type that you select.

---

**Note:** You can add new paper types as necessary. Instructions are included later in this task.

---

17. In the Default Type column, enter the numeral 1 in the row for the paper type you want to use as the default.

select only one paper type as the default. A user can override the default paper type when a batch process is submitted.

Choose the printer definition languages(PDL) that the printer supports. If you choose the Line Printer option, also enter paper dimensions and line parameters in the Line Printers box.  
For AS400s, choose the type of encoding to use for the printer. Click the EBCDIC Encoding option if the printer is an EBCDIC line printer.

Printer Definition Language

☐ PostScript ☒ Default  
☐ PCL ☐  
☐ Line Printer ☐  
☐ Custom ☐

Double-click the row headers to select the paper types that your printer supports. Type 1 in the Default Type column for the paper type you want to use as the default.  
To Add new paper types, from the Form menu, choose New Paper Types.

|                                     | Default Type | Paper Type | Printer Paper Width | Printer Paper Height | UM |
|-------------------------------------|--------------|------------|---------------------|----------------------|----|
| <input checked="" type="checkbox"/> | 1            | LETTER     | 8.50                | 11.00                | IN |
| <input checked="" type="checkbox"/> | 0            | LEGAL      | 8.50                | 14.00                | IN |
|                                     |              | A4         | 210.00              | 297.00               | MM |
|                                     |              |            | 0.00                | 0.00                 |    |

Row 1

18. To add a new paper type, continue with these steps:

19. From the Form menu, select New Paper Type.

The Work With Paper Types form appears.

20. Click Add.

The Paper Type Revisions form appears.

21. Complete these fields:

- Paper Type
- Paper Height
- Paper Width
- Unit of Measure

The software saves the new paper type.

22. Click OK to return to the Work With Paper Types form, and then click Close to return to Printer Setup.

The new paper type is available in the grid on the Printer Setup form. All previous paper type selections are cleared and must be reselected if you want to use them again.

- 23.** When finished entering information for the printer on the Printer Setup form, click End.

Release 9.1 saves the new printer setting and returns you to the first form in the Printers application.

| Field                                | Description                                                                                                                                                                                                                                                                                                                                                                                                                                 |
|--------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>Platform Type</i>                 | Define the type of physical hardware on which the database resides.                                                                                                                                                                                                                                                                                                                                                                         |
| <i>Server Name</i>                   | Define the computer that receives documents from clients.                                                                                                                                                                                                                                                                                                                                                                                   |
| <i>Printer Name</i>                  | Enter a name that refers to a shared resource on a server. Each shared directory on a server has a share name, which is used by clients to refer to the directory.                                                                                                                                                                                                                                                                          |
| <i>Printer Model</i>                 | Define these attributes for your printer: <ul style="list-style-type: none"> <li>■ Printer Model</li> <li>■ Printer Location<br/>Designates the physical location of the printer</li> <li>■ Encoding</li> </ul>                                                                                                                                                                                                                             |
| <i>Paper Type</i>                    | Enter a user defined code (H98\PT) to define the type of printer paper, such as letter or legal. For example, LETTER, LEGAL, and A4.                                                                                                                                                                                                                                                                                                        |
| <i>Paper Width</i>                   | Define the width of the paper for this paper type. This value is in the unit of measure specified by Unit of Measure.                                                                                                                                                                                                                                                                                                                       |
| <i>Paper Height</i>                  | Define the height of the paper for this paper type. This value is in the unit of measure specified by Unit of Measure.                                                                                                                                                                                                                                                                                                                      |
| <i>Unit of Measure</i>               | Enter a user defined code (00\UM) to define the quantity in which to express an inventory item. For example, CS (case) or BX (box). Form-specific information indicates the unit of measure in which the paper height and width are entered. For example, IN = Inches and MM = Millimeters.                                                                                                                                                 |
| <i>Columns Per Page</i>              | Define the number of columns per page. For example, 80 or 132.                                                                                                                                                                                                                                                                                                                                                                              |
| <i>Characters Per Inch (CPI)</i>     | Define the horizontal printing density in characters per inch.<br>You should only define values that are supported by your printer.                                                                                                                                                                                                                                                                                                         |
| <i>Line Per Page</i>                 | Define the number of lines per page. For example, 60 or 66.                                                                                                                                                                                                                                                                                                                                                                                 |
| <i>Line Per Inch (LPI)</i>           | Define the line spacing in lines per inch.<br>You should only define values that are supported by your printer.<br>Values are:<br>4 - IBM 5219, 5224, 5225, and 3287 printers only<br>6 - IBM 5224 printer only<br>8 - IBM 5224 printer only<br>9 - IBM 5225 printer only<br><b>Note:</b> The standard computer print is 6 LPI and 10 CPI. If you are printing on 8 1/2-inch x 11-inch paper, typically you would specify 8 LPI and 15 CPI. |
| <i>Maximum Number of Output Tray</i> | Define the maximum number of paper trays available on the printer you are setting up.                                                                                                                                                                                                                                                                                                                                                       |
| <i>Output Tray Name</i>              | Define the output tray for a given batch print job.                                                                                                                                                                                                                                                                                                                                                                                         |


### 7.7.2 Defining a Default Printer

To define a default printer:

- 1. On the Printers menu (GH9013), select the Printers (P98616) program.
- 2. On the Printers form, click Define Default Printer.

The Work With Default Printers form appears.

- 3. Click Add.



- 4. On Default Printer Revisions, complete these fields and then click OK.

| Field        | Description                                                                                                                                                                                                                                          |
|--------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| User\Group   | Click the visual assist to select either a particular user for this printer or to select an entire group.                                                                                                                                            |
| Report Name  | Click the visual assist to select a specific report to print. Enter *ALL for all reports.                                                                                                                                                            |
| Version Name | Click the visual assist to select a specific report to print. If the value in the Report Name field is *ALL, the system populates the Version Name field with the default value of *ALL and makes the field unavailable for subsequent modification. |
| Environment  | JD Edwards EnterpriseOne provides a default value for this field based on the environment that you are currently logged onto. Enter *ALL for all environments. You can change this information.                                                      |
| Printer Name | Enter the name of your printer.                                                                                                                                                                                                                      |
| Host Name    | Enter the name of the host server where reports will be processed. The visual assist displays the appropriate host names based on the printer name you select. To use this printer for all hosts in your environment, enter *ALL.                    |

| Field                | Description                                                                                                                                                                                                                                                                                                                                                       |
|----------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>Object Status</i> | Define the new printer as the default printer by changing its status to active. If an error occurs, it means that another printer is currently the active default. Change the original default printer to inactive before making the new printer active. Change multiple statuses from the Work With Default Printers form, as explained at the end of this task. |

5. Click OK, and then click Cancel to access the Work With Default Printers form.
6. To change the status of a default printer, select a default record and, from the Row menu, select Change Status.

If another printer is already set as the active default, an error occurs. To change the original default printer to inactive, select it, select Change Status on the Row menu, and then select the new printer as the default.

## 7.8 Enabling Multiple Concurrent Table Conversions

If you are planning to run your Table Conversions on the Enterprise Server, you must set specific values in the JDE.INI `jde.ini` on your Enterprise Server in order to enable multiple Table Conversions to run simultaneously.

To enable multiple concurrent table conversions:

1. Open the JDE.INI `jde.ini` on your Enterprise Server using an ASCII editor compatible with the operating system.
2. Add or update the following entries and their respective values in the [JDEIPC] section:

```
[JDEIPC]
maxNumberOfResources=2000
maxNumberOfSemaphores=1000
```

---

**Note:** The above values are sufficient to run four Table Conversions at once. To run more, you may need to increase these values. The symptom of the values being set too low is that the Table Conversion will fail almost immediately on the server with this error message in its `jde.log`:

```
IPC2100004 ... maxNumberOfResources parameter (2000) exceeded on
allocation of IPCData. Please increase it in INI.
```

If you plan on running more than four concurrent Table Conversions, refer to the *JD Edwards EnterpriseOne Tools System Administration Guide* for details on calculating the correct values for the anticipated workload on your machine.

---



---

# Installing the Development Clients for Developers and System Administrators

This chapter includes these topics and tasks:

- [Section 8.1, "Understanding Development Client Installation"](#)
- [Section 8.2, "Preparing for Development Client Installation"](#)
- [Section 8.3, "Working With Development Client Installation"](#)
- [Section 8.4, "Understanding User Profiles and Languages"](#)

## 8.1 Understanding Development Client Installation

Release 9.1 software for Development Clients is first installed on the Deployment Server, and then deployed from the Deployment Server to Development Clients for developer and system administrator workstations.

The Development Clients are Microsoft Windows-based machines. Refer to the Oracle Certifications for specifically-supported versions of Microsoft Windows.

---

**Note:** The JD Edwards EnterpriseOne installation delivers pre-built packages that are ready for use as delivered.

In order for the Development Client to reflect the language installed on the Deployment Server, you must perform tasks for both the Enterprise Server and Development Clients, in addition to the procedures to verify and modify the `JDE.INI` on the Development Clients and the `JDE.INIjde.ini` on the Enterprise Server.

---

### See Also

- Refer to [Section 1.6, "Language Process Overview"](#) for more information about how you enable multilingual installations on Development Clients.
- *JD Edwards EnterpriseOne Development Client Installation and Configuration Guide*
- *JD Edwards EnterpriseOne Tools Package Management Guide*

## 8.2 Preparing for Development Client Installation

To prepare for the installation of Release 9.1 on Development Clients, you must modify the Development Client `JDE.INI` on the Deployment Server and the JD Edwards EnterpriseOne system administrator must create a user profile for every user

before that user can log on to Release 9.1. You must also copy the configured `tnsnames.ora` from the `oracle\E1local` directory to the `\client` directory on the Deployment Server, as specified in the next section of this guide entitled: [Section 8.3, "Working With Development Client Installation"](#)

---

**Note:** Refer to the *JD Edwards EnterpriseOne Development Client Installation and Configuration Guide* for additional details on installing the Development Client.

---

### Prerequisites

- Uninstall the previous software version on each Development Client before installing the new version. See [Chapter 27, "Deinstalling the Software"](#) for more information about uninstalling previous releases of JD Edwards EnterpriseOne.
- Before installing Release 9.1 on a Development Client used for development, you must install the Microsoft Visual C++ Compiler. The specific version of the compiler is detailed in the Minimum Technical Requirements (MTRs). Refer to [Section 1.3.1, "Accessing Minimum Technical Requirements \(Certifications\)"](#). Also refer to the appropriate Microsoft documents for installation information.
- The names of the Deployment Server, Enterprise Server, and the Development Client cannot exceed 15 characters in length.
- IPv4 Requirement

The Development Client requires Microsoft Windows IPv4 for connectivity. It cannot function with IPv6. Refer to the *JD Edwards EnterpriseOne Development Client Installation Guide* details.

---

**Note:** You must have full administrator privileges to install Release 9.1 on the Microsoft Windows 7-based Development Clients. For details, refer to the *JD Edwards EnterpriseOne Development Client Installation and Configuration Guide* on the Oracle Technology Network (OTN).

---

During Development Client installation, connectivity is required for:

- Read/write access to this client install directory on the primary Deployment Server in the base location:  
`\oneworld`
- Read access to the subdirectories located under this directory:  
`\pathcode\package`  
For example:  
`\\deployment_server_name\E910\PD910\package`
- Read/write access to this directory on the primary Deployment Server:  
`\client`  
For example:  
`\\deployment_server_name\E910\client`
- Refer to the *Deployment Server Reference Guide* in *Setting Up a Development Client Installer on the Deployment Server* for these topics:

- *Understanding the JD Edwards Clients (Development and Web)*
- *Understanding the Oracle Universal Installer*
- *Creating the Web Development Feature*
- *Copying JDBC Drivers and the tnsnames.ora file to the Deployment Server*
- *Updating the Database Drivers in the JDBJ.ini File*
- *Copying the JDK to the Deployment Server (OH4A Only)*
- *Updating the InstallManager.htm File*
- *Updating the oraparam.ini File*
- *Setting Up Local Database Installers*
- Refer to the *Development Client Installation Guide* for these topics:
  - *Understanding the Development Client Installation*

This section describes *Understanding Installation Steps* and *Understanding Destination Paths*.
  - *Installing WebSphere Express 7.0 or WebSphere for Developers 7.0*
  - *Installing the Local Database*
  - *Installing the Development Client*
  - *Working With SnapShot on the Development Client*
  - *Deinstalling the Development Client*
  - *Removing the Local Database*
  - *Troubleshooting the Installation Process*
  - *Installing a Development Client from the Command Line*
  - *Manual Cleanup of a Deinstalled Development Client*
  - *Manual Cleanup of a Deinstalled Oracle Database*
  - *Installing Multiple Pathcodes*

## 8.3 Working With Development Client Installation

The Development Client installation program copies all necessary components of Release 9.1 to a Development Client. During installation, the installation program verifies that enough disk space exists and, if not, you are prompted to create more space before continuing.

---

---

**Caution:** Before starting a JD Edwards EnterpriseOne Development Client installation, you must close all other applications running on that machine. The installation process may not run correctly if other applications are open.

---

---

This section discusses these topics:

- [Section 8.3.1, "Creating a Desktop Shortcut"](#)
- [Section 8.3.2, "Using a Shared Drive"](#)
- [Section 8.3.3, "Understanding Third-Party Products"](#)

### 8.3.1 Creating a Desktop Shortcut

A system administrator can create a shortcut to `InstallManager.exe` from the JD Edwards EnterpriseOne client install directory on the Deployment Server and can deploy the shortcut to the Development Client. For example, the client install directory is typically:

```
\JDEdwards\E910\OneWorld Client Install
```

To ensure that the shortcut works correctly, ensure the Start in: field contains the location of the `installmanager.htm` file.

To create a desktop shortcut:

1. To edit the Start in: field, in Microsoft Windows Explorer or on the desktop, right-click the shortcut.
2. Click Properties, and then click the Shortcut menu.
3. Double-click the Release 9.1 InstallManager shortcut to start the Release 9.1 installation manager.
4. Skip to the next task entitled: [Using a Shared Drive](#).

### 8.3.2 Using a Shared Drive

An installer can connect to the `\JDEdwards\E910` shared drive on your Deployment Server from Microsoft Windows Explorer.

To use a shared drive:

1. Double-click `InstallManager.exe` to start the Release 9.1 installation manager.

The `InstallManager.exe` file is located in this folder:

```
OneWorld Client Install
```

2. On JD Edwards EnterpriseOne Release 9.1 Installation Manager, click Workstation Install.
3. On Client Workstation Setup, click Next.

If you do not have the latest version of Microsoft Internet Explorer the Release 9.1 Client Workstation Setup Third Party Application form appears. The option to install Internet Explorer is selected. To install this application, click Next. If you do not want to install these applications at this time, clear the option for one or both of them, and click Next.

If the latest version of Internet Explorer are already installed, the Third Party Application form is not displayed.

4. On Client Workstation Setup Package Selection, select the package you want to install and click Next.

**Tip:** Click the Filters ON button to narrow the displayed list of available packages. This can help you find the package you want. Notice that a short description of each package appears below the list.

5. On Client Workstation Setup Type, complete these fields:

| Field                    | Description                                                                                                                                                                                                                                                       |
|--------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>Select Setup Type</i> | Select Development or Production objects. You should only select the Development option if you intend to develop Release 9.1 applications.<br><br><b>Note:</b> Select the Development option only if you intend to develop JD Edwards EnterpriseOne applications. |
| <i>Install Path</i>      | Select the drive and directory in which to install the package. For example, this is the typical path for Release 9.1:<br><br>c:\E910                                                                                                                             |

6. To install the package, click Finish.

InstallManager shows the status of the installation process through a series of forms.

The Congratulations form indicates that the installation finished successfully. InstallManager creates a Release 9.1 shortcut in the Programs folder of your Start menu and on your desktop.

7. Reboot if necessary.

---

**Caution:** The JD Edwards EnterpriseOne Development Client installation process verifies that several of the system DLL files are current. If they are not current, you receive a message to reboot your system. When you reboot, the system updates the DLL files in your Microsoft Windows directories.

---

### 8.3.3 Understanding Third-Party Products

A local Oracle Enterprise Edition (OEE) is required for Release 9.1 Development Clients. The OUI installer for the Development Client installs OEE and the Development client separately. Refer to the *Development Client Installation Guide*.

The use of Microsoft Internet Explorer is optional. Adobe Acrobat Reader 6.0 or greater is strongly recommended to view reports online. Neither the browser or reader applications are delivered with the JD Edwards EnterpriseOne Applications Release 9.1 installation.

Microsoft Internet Explorer provides:

- An option for a Web-like menu view within JD Edwards EnterpriseOne Explorer.
- An option for an Internet connection capability directly from the JD Edwards EnterpriseOne Explorer interface.

## 8.4 Understanding User Profiles and Languages

---

**Note:** Release 9.1 supports group preferences for user profile Development Client configuration and environment assignment.

---

For user and group profiles, you should use the preloaded users to perform the installation process. The system administrator needs to create a user profile before the user can log on to Release 9.1.

All users are assigned a language preference code within the user profile. The language preference code field specifies which language is presented on the applicable form or report. You can set up your users and groups when determining how groups are to be organized and what preferences each group shared to have.

For languages, the `JDE.INI` on the Windows-based Deployment Server are updated automatically. For multiple language usage, both the Enterprise Server and Development Client `JDE.INI` `jde.ini` need to be modified for the preferred language being installed.

Existing user profile configurations are set up after the upgrade process finishes. You should add any new environments to these users as needed.

### See Also

- *JD Edwards EnterpriseOne Tools System Administration Guide* for more detailed information about setting up group profiles and how to use them, as well as for information about defining user display preferences.

---

## Performing Merges

This chapter discusses:

- [Section 9.1, "Working with Control Table Merges"](#)
- [Section 9.2, "Working with Specification Merges"](#)

Except where noted in the text, the information in this chapter applies to upgrade and cumulative update customers only. You can run any of the merges in two ways:

- Proof mode creates merge reports, but does not update control tables. Use proof mode to examine the changes that are reported without updating your tables.
- Update mode creates merge reports and updates items in the control tables.

**Tip:** Check each merge as it finishes to make sure it completed successfully. Also, save your logs in case you have to troubleshoot problems.

*See Also*

[Chapter 24, "Major Technical Tables"](#) for more information on individual tables.

### 9.1 Working with Control Table Merges

This section describes:

- [Section 9.1.1, "Working with Customer Base Merges"](#)
- [Section 9.1.2, "Working with Language-Specific Table Merges"](#)
- [Section 9.1.3, "Working with Data Dictionary Merge"](#)
- [Section 9.1.4, "Work with Solution Explorer Merge"](#)
- [Section 9.1.5, "Working with UDC Merge"](#)
- [Section 9.1.6, "Working with Favorites Merge"](#)
- [Section 9.1.7, "Working with Report Director Templates Merge"](#)
- [Section 9.1.8, "Working with Tips of the Day Merge"](#)
- [Section 9.1.9, "Working with Workflow Merge"](#)

The basic structure of Release 9.1 software consists of control tables. These tables organize and sequence the information you put into the JD Edwards EnterpriseOne systems. In addition, these tables determine the types of operations to be performed on the input data. For example, the data dictionary tables define all specifications for any data item in JD Edwards EnterpriseOne software.

Control tables differ from transaction tables in the following ways:

- Control tables contain data that is shared between JD Edwards EnterpriseOne and the customer.
- Transaction tables can be converted, but JD Edwards EnterpriseOne data is never merged into them.

A customer can modify control tables, for example, changing a menu to better suit business needs. Because customers can modify the control tables, JD Edwards EnterpriseOne provides a safe mechanism to merge these control tables with the new data that accompanies a new release. This protects the customer-modified information.

### 9.1.1 Working with Customer Base Merges

In a customer base merge, a JD Edwards EnterpriseOne change table is merged into the customer control tables. Change tables store information related to control table data that has been changed or added into JD Edwards EnterpriseOne since the last release. This information can show detail such as how a menu has changed. The customer base merges look for changes from one base release to the next base release, for example, Release 8.9 to Release 9.1, and update the customer Release 8.9 tables with the new information from Release 9.1.

The upgrade performs these customer base merges:

- Data dictionary merges
- User-defined code merges
- Solution Explorer merges
- Favorites merges
- Report director templates merges
- Tips of the day merges
- Workflow merges

For some merges, you can also specify data selection criteria. This feature lets you choose the information to merge into the Release 9.1 control tables. The ability to limit the information merged reduces the total merge time required.

### 9.1.2 Working with Language-Specific Table Merges

This information is only for users who are installing an alternate language. The distributed language tables consist of control tables, system tables, and data dictionary tables.

- The F91100D table must be loaded to display the text from these tables in the desired language
- The F98800D and F98810D tables must be loaded to display text from these tables in the desired language.
- The F83100 and F83110 tables must be loaded to display soft code text in reports

### 9.1.3 Working with Data Dictionary Merge

---

---

**Note:** This merge is for upgrades and cumulative updates.

---

---



The Data Dictionary Merge (R989200P) program updates the customer-specific data dictionary tables by using a combination of information from the new Release 9.1 data dictionary tables and the change tables in the planner database. It runs during the Installation Workbench phase.

For installation customers only, the Data Dictionary Merge program copies changes made to IBM i data dictionary items into the Release 9.1 data dictionary tables. After you run the Installation Workbench, you run a specification update program to convert the relational database records into the System Local replicated objects. This process includes the Data Dictionary Specification merge (R98722C) and Data Dictionary Text merge (R98722T) programs. You should run these programs to merge your modified IBM i data dictionary files with the Release 9.1 relational database tables, and then into the replicated tables that will be used by each workstation and logic server.

The Release 9.1 data dictionary tables are stored as follows:

- The following pristine data dictionary tables are stored in a relational database.

Changes made to the data dictionary items that will be replicated to other workstations must be made here.

- F9200
- F9202
- F9203
- F9207
- F9210
- F9211
- F9212
- F00165

- Replicated data dictionary items are stored in specification tables on each workstation.

These tables are the .ddb and .xdb versions of the DDDICT and DDTEXT tables that are located in the \Spec directory.

For installations, upgrades, and cumulative updates that include an alternate language, the Data Dictionary Text tables (GT92002, F9202, and F9203) must be loaded to display the text from these files in the desired language. The data dictionary files add the alternate language on top of the installed English records.

### 9.1.4 Work with Solution Explorer Merge

---

**Note:** This merge is for upgrades and cumulative updates.

---

The Solution Explorer Merge (R9690002) program updates the customer-specific Solution Explorer tables using a combination of information from the new Solution Explorer tables and the change tables in the planner database. The merge runs when you run the Installation Workbench. The menu tables are F9000, F9001, F9002, F9005, F9006, F9020, F9022, and F9050.

For users installing an alternate language, the Text Alternate Description table (F9002) contains the language records to display Solution Explorer in the desired language. This process adds the desired language on top of the already installed English records.

### 9.1.5 Working with UDC Merge

---

---

**Note:** This merge is for upgrades and cumulative updates.

---

---

The User-Defined Codes Merge (R9600042) program updates the customer-specific user defined codes (UDC) tables by using a combination of information from the new UDC tables and the change tables in the planner database. This merge runs when you run the Installation Workbench. The UDC tables are F0004 and F0005.

During the installation process, this merge is used only for users who are installing an alternate language.

For upgrade and cumulative update customers who are installing an alternate language, the User-Defined Codes Merge (R9600042) program merges the language UDC text. When the merge business function is run, any time a UDC Header record in the F0004 table or a UDC Detail record in the F0005 table is added, the corresponding language records are added to your UDC language tables F0004D or F0005D.

A report interconnect to run the language UDC merge is provided with this merge.

### 9.1.6 Working with Favorites Merge

---

---

**Note:** This merge is for upgrades and cumulative updates only.

---

---

The Favorites Merge (R96911002) program updates the customer-specific favorites table by using a combination of information from the new favorites table and change tables in the planner database. It runs during the Installation Workbench phase. The favorites table is F91100.

### 9.1.7 Working with Report Director Templates Merge

---

---

**Note:** This merge is for upgrades and cumulative updates only.

---

---

The Report Director Templates Merge (R96914002) program updates the customer-specific report director templates tables using a combination of information from the new report director templates tables and the change tables in the planner database. The merge runs during the Installation Workbench phase. The report director templates tables are F91400, F91410, F91420, and F91430.

### 9.1.8 Working with Tips of the Day Merge

---

---

**Note:** This merge is for upgrades and cumulative updates only.

---

---

The Tips of the Day Merge (R96915002) program updates the customer-specific tips of the day tables using a combination of information from the new tips of the day tables

and change tables in the planner database. The merge runs during the Installation Workbench phase. The tips of the day tables are F91500 and F91510.

### 9.1.9 Working with Workflow Merge

---

---

**Note:** This merge is for cumulative updates only.

---

---

The Workflow Merge (R98800) program merges the JD Edwards EnterpriseOne workflow data shipped with a new release with the customer workflow data. The merge runs during the Installation Workbench phase.

The following list shows the workflow tables:

- F98800
- F98800D
- F98800T
- F98810
- F98810D
- F98811
- F98830
- F98840
- F98845

---

---

**Note:** The workflow merge may overwrite your customer-defined data, as follows:

- If you have modified a JD Edwards EnterpriseOne workflow process, and the new JD Edwards EnterpriseOne workflow process has been changed, the updated new JD Edwards EnterpriseOne workflow process overwrites the customer-modified workflow process.
  - If the customer has created a new workflow process, and used a name that is the same as the JD Edwards EnterpriseOne workflow process that has been updated, the updated JD Edwards EnterpriseOne workflow process overwrites the customer-created workflow process with the same name.
- 
- 

If any customer-defined processes are in danger of being overwritten, you should copy the existing process and rename it with another version number before performing the merge.

You can check for processes to be overwritten by using proof mode with the merge.

## 9.2 Working with Specification Merges

This section discusses:

- [Section 9.3, "Working with Object Librarian Merge"](#)
- [Section 9.4, "Working with Versions List Merge"](#)

- [Section 9.5, "Working with Central Objects Merge"](#)
- [Section 9.6, "Working with Update Language Text Merge"](#)

This table explains what happens to the following types of objects if they have been modified by the customer when the specification merge programs run during an upgrade or a cumulative update. The table assumes the JD Edwards EnterpriseOne action and the customer action are on the same object.

| JD Edwards EnterpriseOne action | Customer action              | Upgrade                                                        | Update                                                                                      |
|---------------------------------|------------------------------|----------------------------------------------------------------|---------------------------------------------------------------------------------------------|
| An object is modified.          | No action.                   | No action.                                                     | Add or replace.                                                                             |
| An object is modified.          | The same object is modified. | Merge (replaces data structures and applications).             | Merge (replaces data structures and applications).                                          |
| An object is added.             | No action.                   | No action.                                                     | Add.                                                                                        |
| No action.                      | A new object is added.       | Add.                                                           | No action.                                                                                  |
| No action.                      | No action.                   | No action.                                                     | No action.                                                                                  |
| No action.                      | The same object is modified. | Merge.                                                         | No action.                                                                                  |
| An object is deleted.           | No action.                   | No action.                                                     | The report should contain a warning. Object Librarian should be updated to product code 88. |
| An object is deleted            | An object is modified        | The report should contain a warning, and the object is merged. | The report should contain a warning and the object is not deleted.                          |

#### See Also

[Section 25.8, "Object Specification Merge Report \(R98700\)"](#) in [Chapter 25, "Working with Reports"](#) in this guide for more information about the reports.

For users who are upgrading an alternate language, the merge copies all text for custom objects. For modified JD Edwards EnterpriseOne objects, all changed or added text is copied forward to the new release.

For users who are updating an alternate language, the TAM package contains only base text. The merge replaces central objects base text with base text from the package. Translated text is not removed.

## 9.3 Working with Object Librarian Merge

---

**Note:** This merge is for upgrades and cumulative updates only.

---

During an upgrade, the Specification Merge (R98700) program carries over any previous release Object Librarian changes you have made, such as added objects and modification flags, and changed category codes, to the new Object Librarian.

During a cumulative update, the Specification Merge (R98700) program adds any Object Librarian changes, such as added objects and changed category codes, to the existing Object Librarian.

## 9.4 Working with Versions List Merge

---

---

**Note:** This merge is for upgrades and cumulative updates only.

---

---

During an upgrade, the Versions List merge (R98700) program preserves any non-XJDE and non-ZJDE (customer versions) version specifications for objects that are valid in the new release and their processing options data. This process also preserves the processing options data of ZJDE and ZJDEC version (customer versions).

During a cumulative update, the Versions List merge preserves any non-XJDE and non-ZJDE (customer versions) version specifications for objects that are valid in the new release. It also preserves their processing options data and adds new XJDE and ZJDE versions. This process also preserves the processing options data of ZJDE and ZJDEC version (customer versions) for objects that are changed.

## 9.5 Working with Central Objects Merge

---

---

**Note:** This merge is for upgrades and cumulative updates only.

---

---

Use this information only if you are installing an alternate language.

When you load an alternate language with the installation, you must load language records into the central objects tables to enable that language. The central objects tables contain the alternate language records needed for displaying text in the selected language.

Language-enabled tables include the processing text (F98306), report text (F98760) and form text (F98750). Depending upon the environment choices during the English installation, you may have several sets of central objects, for example, one set for each environment loaded during the English language installation.

## 9.6 Working with Update Language Text Merge

This merge is for customers who have an alternate language and are installing a cumulative update release only.

The Update Language Text Merge () program runs automatically during the Specification Table Merge Workbench. This program copies text from the language database to the central objects database. Any language text records that do not exist are added. Records that already exist are updated if the text has changed. Custom text in JD Edwards EnterpriseOne objects is preserved if the merge flags are set correctly in Object Librarian. This process is called automatically from the Specification Table Merge Workbench or run as a standalone option from R98700. If it is run from the workbench, the Language Plan (F\_) table is used to merge each language, data source, and environment selected in the plan.



---

## Understanding Media Object Queues

This chapter discusses these topics:

- [Section 10.1, "Overview"](#)
- [Section 10.2, "Modifying Media Object Queues"](#)
- [Section 10.3, "Specifying the Help Location Used by the Web Client and Development Client"](#)

### 10.1 Overview

Media objects enable the attachment of information to Release 9.1 applications. Media Object Queues enable you to specify the storage location of media objects to be tracked by reference as opposed to physical network location. This enables easier administration of media locations.

Media object queues provide the system administrator the ability to easily manage the storage of media objects and helps in a Release 9.1 configuration. Within Release 9.1, set up media object queues in order to use images that are outside the domain of the imaging product (for example, scanned images).

Define a media object queue to identify the pointer to the location where the actual image files or Object Linking and Embedding (OLE) objects reside. For OLE objects, the name of the queue must be OLEQUE. The media object queues must reside on a Microsoft Windows-based machine. A valid network-qualified path must exist for this machine. Use the Deployment Server or any other Microsoft Windows-based machine.

If you modify the OLEQUE path, make sure to copy the image files and OLE objects to the new location.

When using the Deployment Server to store media object queues, remember to make the machine available for use daily by Release 9.1 applications.

Media object queue paths are shipped with generic server names. To enable media object queues at the customer site, enter the Deployment Server name in the media object queue path.

#### See Also


*Media Objects and Imaging* in the *JD Edwards EnterpriseOne Tools System Administration Guide* for more information about the use of media objects.

### 10.2 Modifying Media Object Queues

To modify your media object queues:

1. Log into Release 9.1 as JDE in the DEP910 environment.
2. From System Administration Tools (GH9011), select Media Object Queues (P98MOQUE).
3. To define the location for a new OLE queue, click Add.
4. Complete these fields:
  - *Name*  
Enter a valid value for your queue.
  - *Path*  
Generally the queue paths include *server\_name* and *queue\_name*. Replace *server\_name* with the name of the Deployment Server or the location of the media object queue. A valid queue path for a network location might be:  
`\\server_name\E910\queue_name`  
where *server\_name* is your Deployment Server and *queue\_name* is the name of the media object queue.  
  
When using ComposerCBT, the media object queue path does not require `\\` or *server\_name*. ComposerCBT is shipped with an *x* for the drive name. To enable the Composer CBT queue, replace the *x* with the drive letter that the workstation uses to access the server where the media object queues reside. For example: `N:\Mediaobj\ComposerCBT`.
5. To change an existing media object queue, click Find to display a list of queue names and their paths.
6. On Work With Media Object Queues, select the queue name you want to modify.






7. On Media Object Queues, change the information in the Queue Path On-Line field to reflect the new location.
8. Copy the image files and OLE objects to the new location.
9. Exit Release 9.1 and log back on to enable the changes.

### 10.3 Specifying the Help Location Used by the Web Client and Development Client

To specify the help location used by the Web Client and Development Client:

1. From System Administration Tools (GH9011), select Media Object Queues (P98MOQUE).
2. To define the location for the Help file that is used by the Web Client, on Media Object Queues, enter **Help** in the Name field and click Find.



Home Navigator Open Applications Recent Reports Favorites

### Media Object Queue Revisions

Tools

Queue Name \* Help

Queue Path On-Line \* <http://www.oracle.com/technetwork/documentation/jdedent-098>

Queue Path Off-line <http://www.oracle.com/technetwork/documentation/jdedent-098>

Type 09 *PeopleBooks Help Queue*

On-Line Access Type Read / Write

Off-Line Access Type Read / Write

3. On Media Object Queue Revisions, complete these fields:
  - *Queue Path On-Line*  
Enter this value  
<http://www.oracle.com/technetwork/documentation/jdedent-098169.html>
  - *Queue Path Off-line*  
Enter the same value as the preceding field, which is:  
<http://www.oracle.com/technetwork/documentation/jdedent-098169.html>
  - *Type*  
Enter the value 09. The Type field description changes to **PeopleBooks Help Queue**.
4. Click OK to return to the Work With Media Objects form.
5. To define the location for the Help Content Queue that is used by the Development Client, on Media Object Queues, enter **Help Content** in the Name field and click Find.

Home Navigator Open Applications Recent Reports Favorites

### Media Object Queue Revisions

Save Delete Tools

Queue Name \* Help Content

Queue Path On-Line \* <http://www.oracle.com/technetwork/documentation/jdedent-098>

Queue Path Off-line <http://www.oracle.com/technetwork/documentation/jdedent-098>

Type 09 PeopleBooks Help Queue

On-Line Access Type Read / Write

Off-Line Access Type Read / Write

6. On Media Object Queue Revisions, complete these fields:

- Queue Path On-Line

Enter this value

<http://www.oracle.com/technetwork/documentation/jdedent-098169.html>

- Queue Path Off-line

Enter the same value as the preceding field, which is:

<http://www.oracle.com/technetwork/documentation/jdedent-098169.html>

- Type

Enter the value 09. The Type field description changes to **PeopleBooks Help Queue**.

Home Navigator Open Applications Recent Reports Favorites Fast Path: P98moque

### Work With Media Object Queues

Query: All Records

Records 1 - 2

| Queue Name   | Queue path On-Line                                                                                                                                    | Queue Path Off-line                                                                                                                                   | Type | Description            | On-Line Access |
|--------------|-------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------|------|------------------------|----------------|
| Help         | <a href="http://www.oracle.com/technetwork/documentation/jdedent-098169.html">http://www.oracle.com/technetwork/documentation/jdedent-098169.html</a> | <a href="http://www.oracle.com/technetwork/documentation/jdedent-098169.html">http://www.oracle.com/technetwork/documentation/jdedent-098169.html</a> | 09   | PeopleBooks Help Queue | Read / Write   |
| Help Content | <a href="http://www.oracle.com/technetwork/documentation/jdedent-098169.html">http://www.oracle.com/technetwork/documentation/jdedent-098169.html</a> | <a href="http://www.oracle.com/technetwork/documentation/jdedent-098169.html">http://www.oracle.com/technetwork/documentation/jdedent-098169.html</a> | 09   | PeopleBooks Help Queue | Read / Write   |

7. On Work With Media Object Queues, enter Help\* in the QBE for Queue Name and verify the two help queues are added.

8. Exit Release 9.1 and log back on to enable the changes.



---

## Performing Post Upgrade Tasks

This section contains these tasks:

- [Section 11.1, "Setting Up Microsoft Windows Security on Release 9.1 Directories"](#)
- [Section 11.2, "Using the Adobe SVG Viewer on Web Clients"](#)
- [Section 11.3, "Setting Up Solution Explorer"](#)
- [Section 11.4, "Configuring JD Edwards EnterpriseOne for Use with Vertex Quantum Tax Applications"](#)
- [Section 11.5, "Enabling CRM Functionality"](#)
- [Section 11.6, "Enabling Verity Enhanced Search Capability"](#)
- [Section 11.7, "Working with the Data Dictionary"](#)
- [Section 11.8, "Working with SETOWAUT"](#)
- [Section 11.9, "UBE Performance ' SQL Package Location"](#)

### 11.1 Setting Up Microsoft Windows Security on Release 9.1 Directories

To set up Microsoft Windows security on the Release 9.1 directories and files on your Deployment Server. Use these charts to determine what permissions are required for the various types of Release 9.1 users and perform these tasks to set permissions on the Security tab:

- [Section 11.1.1, "Setting Security on the Pathcode Directory"](#)
- [Section 11.1.2, "Setting Security on the Database Directory"](#)
- [Section 11.1.3, "Setting Security on the Data Dictionary Directory"](#)
- [Section 11.1.4, "Setting Security on the Helps Directory"](#)
- [Section 11.1.5, "Setting Security on the Media Object Directory"](#)
- [Section 11.1.6, "Setting Security on the Planner Directory"](#)
- [Section 11.1.7, "Setting Security on the Print Queue Directory"](#)
- [Section 11.1.8, "Setting Security on the System Directory"](#)

---

**Note:** Not all directories are available. The directory names listed in the table below are subdirectories of the \JDEdwards\E910 directory structure. You can apply the indicated permissions to all subdirectories and files except where noted.

---

### 11.1.1 Setting Security on the Pathcode Directory

This table lists the settings to set security on the pathcode directory:

| User Type                                          | Permissions |
|----------------------------------------------------|-------------|
| JDE                                                | Change      |
| (all subdirectories except \pathcode and \package) | Change      |
| Production users                                   | Read Only   |
| (all subdirectories except \pathcode and \package) | Change      |
| Development users                                  | Change      |
| (all subdirectories except \pathcode and \package) | Change      |
| CNC administrators and application leads           | Change      |
| (all subdirectories except \pathcode and \package) | Change      |

### 11.1.2 Setting Security on the Database Directory

This table lists the settings to set security on the database directory:

| User Type                                | Permissions |
|------------------------------------------|-------------|
| JDE                                      | Change      |
| Production users                         | No Access   |
| Development users                        | No Access   |
| CNC administrators and application leads | No Access   |

### 11.1.3 Setting Security on the Data Dictionary Directory

This table lists the settings to set security on the data dictionary directory:

| User Type                                | Permissions |
|------------------------------------------|-------------|
| JDE                                      | Change      |
| Production users                         | No Access   |
| Development users                        | No Access   |
| CNC administrators and application leads | Change      |

### 11.1.4 Setting Security on the Helps Directory

This table lists the settings to set security on the Helps directory:

| User Type                                | Permissions |
|------------------------------------------|-------------|
| JDE                                      | Change      |
| Production users                         | Read Only   |
| Development users                        | Read Only   |
| CNC administrators and application leads | Read Only   |

### 11.1.5 Setting Security on the Media Object Directory

This table lists the settings to set security on the media object (literal name is mediaobj) directory:

| User Type                                | Permissions |
|------------------------------------------|-------------|
| JDE                                      | Change      |
| Production users                         | Read Only   |
| Development users                        | Read Only   |
| CNC administrators and application leads | Change      |

### 11.1.6 Setting Security on the Planner Directory

This table lists the settings to set security on the planner directory:

| User Type                                | Permissions |
|------------------------------------------|-------------|
| JDE                                      | Change      |
| Production users                         | No Access   |
| Development users                        | No Access   |
| CNC administrators and application leads | No Access   |

### 11.1.7 Setting Security on the Print Queue Directory

This table lists the settings to set security on the print queue (literal name is printqueue) directory:

| User Type                                | Permissions |
|------------------------------------------|-------------|
| JDE                                      | Change      |
| Production users                         | No Access   |
| Development users                        | No Access   |
| CNC administrators and application leads | No Access   |

### 11.1.8 Setting Security on the System Directory

This table lists the settings to set security on the system directory:

| User Type                                | Permissions |
|------------------------------------------|-------------|
| JDE                                      | Change      |
| Production users                         | Read Only   |
| Development users                        | Read Only   |
| CNC administrators and application leads | Change      |

## 11.2 Using the Adobe SVG Viewer on Web Clients

Per the Minimum Technical Requirements (MTRs) for JD Edwards EnterpriseOne web clients (refer to [Section 1.3.1, "Accessing Minimum Technical Requirements \(Certifications\)"](#)), you must have the Adobe Scalable Vector Graphics (SVG) viewer installed on your web clients in order to use specific JD Edwards EnterpriseOne applications, such as Demand Flow Manufacturing.

Within such JD Edwards EnterpriseOne applications, the Graphical Product Synchronization uses the Adobe SVG viewer for displaying the graphics associated with the product synchronization. The JD Edwards EnterpriseOne application automatically detects the Adobe viewer if it is already installed for the browser. If the viewer is not installed for the browser, the system displays a link that you can use to install the viewer from the Adobe web site. The URL for this link is:

<http://www.adobe.com/svg/viewer/install/main.html>

---

**Note:** SVG is a graphics file format and web development language based on XML that enables dynamic creation of high-quality graphics with precise structural and visual control. It is based on standards defined by the World Wide Web Consortium (<http://www.w3.org/TR/SVG/>).

---

**Tip:** The installation of the SVG viewer may require administrator authority on your client machine.

## 11.3 Setting Up Solution Explorer

Solution Explorer is the Microsoft Windows-based interface that provides access to Release 9.1 applications, role-based menus, implementation and configuration options, documentation, and training materials. Solution Explorer is a convenient window into Release 9.1.

Users can access Solution Explorer to search and navigate quickly through Release 9.1 applications. Users also can customize Solution Explorer to create their own tasks and link tasks to other Web-based information.

### 11.3.1 Setting Up Solution Explorer HTML Documentation Path

When Release 9.1 is installed, the system automatically stores HTML documentation hierarchically in folders located in a common documentation directory. Using Media Object Queues, Solution Explorer locates these files and displays the associated documentation in its own window whenever a user selects a task.

The file path from Solution Explorer to the HTML documentation files is defined in the F98MOQUE table; it must be configured by accessing the corresponding program, called the Work with Media Object Queues (P98MOQUE) program. When JD Edwards EnterpriseOne installs the documentation files, it creates an entry in the Media Object Queue table that associates the Queue Name, called *ActivEraData*, with a generic path to the documentation. For Solution Explorer to link each HTML file with the correct task, you must open this program and change the server name for the directory path associated with the Queue Name *ActivEraData*. The directory path has this structure:

`\\Server_Name\E910\SolutionExplorder\Data`

where *Server\_Name* is the name of your Deployment Server.



When the queue name `ActivEraData` is correctly mapped to the main HTML documentation directory, Solution Explorer locates and displays the associated documentation when a user accesses a Task Location or Task View Location. For example, if a task named `JDE001234` exists, the path to the HTML file of the summary document for the task is:

```
\\Server_Name\PY910\SolutionExplorer\Data\JDE001234\summary.html
```

where *Server\_Name* is the name of the Deployment Server

For more information on setting up the documentation path, refer to [Section 10.2, "Modifying Media Object Queues"](#).

### 11.3.2 Setting Up the Home Page for Solution Explorer

The home page is generally the first screen a user sees when logging on to Solution Explorer. This screen can be used to display information that is relevant to end users in the enterprise. It can be an external Web site, an intranet site, or even HTML files stored on any server on the network.

During the installation process, a directory called `PortalLite` is created when the Deployment Server is installed. This directory resides in this path:

```
x:\base_installation_directory\SolutionExplorer\PortalLite
```

where *x:\base\_installation\_directory* is the drive and directory where you installed Release 9.1 on your Deployment Server.

The `PortalLite` directory includes a set of HTML files that make up the default Home Page. Even though this directory is on the Deployment Server by default, the directory could reside anywhere on the network, such as on a HTML Web Server or on a local workstation.

When the Release 9.1 client is installed, the system updates the client `JDE.INI` to point to the location of the `PortalLite` directory. For example, if the name of the Deployment Server is `DepServer1` and the share name is `E910`, the `[Explorer]` section of the `JDE.INI` is updated as follows:

```
[Explorer]
ExplorerHomeURL="\\DepServer1\E910\SolutionExplorer\portallite\index.html"
ExplorerStart=INTERNET
```

You can change the above parameters in the `JDE.INI` to display any HTML file or URL as the default Home Page. This table describes these parameters:

| <b>[Explorer] Parameter</b>   | <b>Description</b>                                                                                                                                                                   |
|-------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>ExplorerHomeURL=</code> | Defines the URL or filename of the Home Page that is displayed when the user logs on. The default value is:<br><code>\\Depserver1\E910\SolutionExplorer\portallite\index.html</code> |

| [Explorer] Parameter | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
|----------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| ExplorerStart=       | <p>Defines the Explorer start mode. Values are:</p> <ul style="list-style-type: none"> <li>INTERNET<br/>This is the default value. When you start Solution Explorer, the system displays the Internet view first.</li> <li>TASK<br/>When you start Solution Explorer, the system displays the last task view the user viewed.<br/>To display a specific task view, use this syntax:<br/>ExplorerStart=TASK:xx<br/>where xx is the task ID of the task view.</li> </ul> |

## 11.4 Configuring JD Edwards EnterpriseOne for Use with Vertex Quantum Tax Applications

This topic describes how to configure JD Edwards EnterpriseOne to use the Vertex Quantum tax applications. If you do not use these applications with JD Edwards EnterpriseOne, skip this section.

Release 9.1 can be used with the following Vertex Quantum tax applications:

- Vertex Quantum for Payroll Tax
- Vertex Quantum for Sales and Use Tax

The Vertex Quantum applications should be installed on your system before starting the configuration tasks.

---

**Note:** The Vertex Quantum applications can be used with the Indexed Sequential Access Method (ISAM) database or Oracle database (for either of the Vertex Quantum applications) or the SQL Server database (for Vertex Quantum for Sales and Use Tax). The ISAM database is installed as part of the Vertex Quantum application installation.

---

### See Also

*Vertex Quantum for Payroll Tax - Administrator's Guide*

*Vertex Quantum for Sales and Use Tax - Administrator's Guide*

Before configuring Release 9.1 for use with Vertex Quantum applications, install Vertex Quantum for Payroll Tax, Vertex Quantum for Sales and Use Tax, or both on the Enterprise Server. For information about installing the Vertex Quantum applications, refer to the Vertex Quantum administration guides listed above. When installing the Vertex Quantum applications, note the following:

- Note the directory path on the Enterprise Server for the directory in which the Vertex Quantum applications are stored.

This information is needed when copying the Vertex libraries into the Release 9.1 directory structure.

- For Vertex Quantum for Sales and Use Tax, you can install the ISAM database version of the Vertex Quantum application, or you can use the SQL Server or Oracle database.

- For Vertex Quantum for Payroll Tax, you can install the ISAM database version of the Vertex Quantum application, or you can use the Oracle database.

You cannot use SQL Server with Vertex Quantum for Payroll Tax.

- When using the Vertex ISAM database, note the directory path on the Enterprise Server for the directory or directories in which the Vertex Quantum application databases are created.

This information is needed for establishing Release 9.1 database connectivity.

### 11.4.1 Adding Vertex Quantum Directory Information to the Microsoft Windows Server Path

To add the Vertex Quantum application directory information to the Microsoft Windows server path:

1. From the Microsoft Windows Enterprise Server, access the Control Panel.
2. On Control Panel, click the System icon.
3. In System, select the Advanced tab.
4. On the Advanced tab, click the Environment Variables button.
5. In the System Variables window, scroll down until the keyword Path appears in the Variable column.
6. Click Edit to display the current path in the Variable Value field.
7. Search the current path (as shown in the Value field) for the Vertex Quantum application directory.

If the directory does not appear, you must add it to the path, as described in the following step. If the directory appears in the path, skip to step 9 in this task.



8. Place the cursor in the Value field, and use the right arrow to scroll to the end of the field and enter this path: `x:\vertexDirectoryPath\vertex\utils` where `x:\vertexDirectoryPath` is the drive and path for the directory in which the Vertex Quantum applications are stored.

---

**Note:** You might need to include a semicolon to separate this entry from previous entries.

---

9. Click Set.  
The new value is saved.
10. After you finish setting the Environment Variables, repeat this task for User Variables, starting from Step 5 in this task.

11. Click OK and reboot the server.

The new path takes effect.

## 11.4.2 Configuring the Release 9.1 Database Connections for Vertex Quantum Tax Applications

To configure Release 9.1 database connections to use the Vertex Quantum applications:

1. In the Fast Path field, enter G731 to access Vertex Quantum Tax Processing.

The Vertex Quantum Tax Processing panel appears.

2. Highlight and right-click the Database Connections (P7308) program.

A context menu appears.

3. On the context menu, select Prompt for Values.

The Processing Options dialog appears.

4. On Processing Options, click the Quantum tab and enter the following information:

*Option #1:* Enter which Vertex Quantum applications are installed:

| Value   | Action                                                        |
|---------|---------------------------------------------------------------|
| [blank] | Install both Vertex Quantum tax applications.                 |
| 1       | Install the Vertex Quantum for Sales and Use Tax application. |
| 2       | Install the Vertex Quantum for Payroll Tax application.       |

*Option #2:* Enter location information for the databases:

| Value   | Action                                                                                                                                                                                                                                      |
|---------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| [blank] | Define databases for both Vertex Quantum tax applications in the same location.                                                                                                                                                             |
| 1       | Define databases for the Vertex Quantum for Payroll Tax and Vertex Quantum for Sales and Use Tax applications in separate locations.                                                                                                        |
| 2       | Define databases for the Vertex Quantum for Payroll Tax and Vertex Quantum for Sales and Use Tax applications in separate locations, and the four databases for the Vertex Quantum for Sales and Use Tax application in separate locations. |

*Option #3:* If processing option #2 is set to 1 or 2 (that is, if the Vertex databases are in separate locations), specify the GeoCode database location information:

| Value   | Action                                                                                                                                             |
|---------|----------------------------------------------------------------------------------------------------------------------------------------------------|
| [blank] | Define the Vertex Quantum Payroll Tax and Sales and Use Tax applications to use the same GeoCode database.                                         |
| 1       | Define each of the Vertex applications to use a separate copy of the GeoCode database, and that the two copies are expected in separate locations. |

5. Click OK.

The Vertex Quantum Database Connection panel is displayed. The Database Connection panel contains one or more tabs that correspond to the database connections that must be defined. The displayed tabs are determined by the values you entered in the processing options, in Step 4 of this task.

---

**Note:** The GeoCode database is the only Vertex Quantum database that can be shared between the Vertex Quantum Payroll Tax and Sales and Use Tax applications. However, all of the Vertex Quantum databases can be installed in the same location or in different locations.

---

One or more of the following tabs appears on the Database Connection panel:

| Tab                   | Description                                                                                                                                                                                                  |
|-----------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| All                   | All Vertex Quantum application databases for both applications are located on the same server and in the same location.                                                                                      |
| GeoCode               | The same GeoCode database is used by both applications.                                                                                                                                                      |
| GeoCode-Sales and Use | The GeoCode database used by the Sales and Use Tax application is located on this server and location. A separate copy of the GeoCode database, at another location, is used by the Payroll Tax application. |
| GeoCode-Payroll       | The GeoCode database used by the Payroll Tax application is located on this server and location. A separate copy of the GeoCode database, at another location, is used by the Sales and Use Tax application. |
| Sales and Use         | The four databases used by the Sales and Use Tax application are located together, on this server and location.                                                                                              |
| TDM                   | The Test Data Management (TDM) database, used by the Sales and Use Tax application, is located on this server and location.                                                                                  |
| Register              | The Register database, used by the Sales and Use Tax application, is located on this server and location.                                                                                                    |
| Rate                  | The Rate database, used by the Sales and Use Tax application, is located on this server and location.                                                                                                        |
| Payroll               | The databases used by the Payroll Tax application are located on this server and location.                                                                                                                   |

**6.** On the Database Connection panel, select each tab and enter the following information:

- *Data Source*

Enter the name of the library where the Vertex Quantum tables are located. The location you enter should be the location on the server used for the database when the Vertex applications were installed as previously described in this step.

- *Server*

Enter the name of the IBM i machine where the Vertex Quantum tables are located.

- *User ID*

Enter a user ID that can access the database.

- *Password*

Enter the password for the user ID specified above.

7. Click OK.

The changes do not take effect until you have logged off of your system and logged back on.

8. On the Form menu, use IBM i Library to specify the Vertex Quantum library that contains the Vertex Quantum APIs.

For Vertex Quantum for Sales and Use Tax, this library is typically called VERQSU. For Vertex Quantum for Payroll Tax, this library is typically called VERQPRT.

### 11.4.3 Mapping Objects to the Enterprise Server

Objects that call the Vertex Quantum APIs must execute on the server on which the Vertex Quantum APIs reside. Check that the following Release 9.1 objects are configured in the system OCM to execute on the server. Do not change the mappings.

For Vertex Quantum for Payroll Tax:

- R07200 (Pre-payroll Driver)
- B0700058

For Vertex Quantum for Sales and Use Tax:

- X00TAX.c (Tax Calculator)
- B7300002 (Validate Quantum GeoCodes)
- B7300004 (Retrieve Quantum GeoCodes)
- B7300012 (Validate Quantum Software Information)
- B0000182
- B0000183

### 11.4.4 Testing the Vertex Quantum Connection from Release 9.1

Use the following procedures to test the Vertex Quantum connection from Release 9.1.

To test the Vertex Quantum for Payroll Tax interface:

1. Access the Payroll Workbench menu (G07BUSP11), and select Pay Cycle Workbench.

The Work with Payroll Cycle Workbench panel appears.

2. Specify pre-payroll information and submit the pre-payroll.

For information about the Payroll Workbench and submitting pre-payroll, see *Processing Pre-Payroll* in the *Release 9.1 Payroll Implementation Guide*.

3. If no taxes are being calculated, there may be a setup or configuration problem.

Verify the following to make sure setup is correct:

- UBE R07200 is being executed on the server where the Vertex Quantum for Payroll Tax APIs reside.
- Correct values are assigned to the Data Source, Server, User ID, and Password fields on the Database Connection panel, as specified in [Configuring the Release 9.1 Database Connections for Vertex Quantum Tax Applications](#).

4. For the Vertex Quantum for Sales and Use Tax interface:

In the Fast Path field, enter P73GEO.

The Retrieve GeoCode panel appears.

5. On the Retrieve GeoCode panel, enter *CO* in the State field and *DENVER* in the City field, and click Find.

The code 060310140 should appear in the grid.

6. If nothing appears in the grid, a setup or configuration problem might exist.

Verify the following to make sure setup is correct:

- These values are set in the Work with Quantum Constants Revision table, accessed by the Constants application (P7306) on menu G731:

Quantum Active: Y

Canada Country Code: CA

---

**Note:** Changes to the Work with Quantum Constants Revision table do not take effect until you have logged off of your system and logged back on.

---

- Required Release 9.1 objects are mapped to the server where the Vertex Quantum for Sales and Use Tax APIs reside.

Also ensure that correct values are assigned to the `Data Source`, `Server`, `User ID`, and `Password` fields on the Database Connection panel. Instructions for both procedures are specified in this guide in the section entitled *Mapping Objects to the Enterprise Server*.

#### 11.4.4.1 Adding an Entry for a Remote Database Directory for Vertex

To add an entry for a remote database directory:

1. Log on to the IBM i as QSECOFR.
2. On the command line, enter:  
  
WRKRDBDIRE
3. Look for an entry on your IBM i for Remote Location \*LOCAL. This entry must have the same name as your machine.
4. If you do not have an entry like this, enter 1 in the Option column and enter the machine name in the Relational Database column, and press enter.

In the Remote Location Name or Address enter \*LOCAL and press Enter. If you already have a \*LOCAL entry and the Relational database name is NOT the same as your machine name, you must remove the entry that you have and add a new entry as above.

## 11.5 Enabling CRM Functionality

To enable CRM functionality after the upgrade is complete, you must perform these procedures on the CRM Enterprise Server and the CRM client:

- [Section 11.5.1, "Enabling CRM on the CRM Mobile Client"](#)

- [Section 11.5.2, "Enabling CRM on the Enterprise Server"](#)

### 11.5.1 Enabling CRM on the CRM Mobile Client

To enable CRM functionality in JD Edwards EnterpriseOne and the JD Edwards EnterpriseOne mobile client, make sure that the F99410 table has records that contain the following system codes:

- SY90CA
- CRMMSL
- SY49

On your Enterprise Server, access the P99410 application and complete this procedure to enable CRM functionality:

1. On Work with EnterpriseOne System Control, click Add.
2. On EnterpriseOne System Control Revisions, enter each of these system codes, one at a time, in the Data Item field:
  - 90CA  
This code enables CRM functionality in JD Edwards EnterpriseOne.
  - MMSL  
With SY49, this system code enables CRM functionality in the mobile client.
  - SY49  
With CRMMSL, this system code enables CRM functionality in the mobile client.
3. Click Yes.
4. Click OK.
5. Repeat these steps to add each system code.

### 11.5.2 Enabling CRM on the Enterprise Server

Using an ASCII editor, you must modify the `JDE.INIjde.ini` on your Enterprise Server to add this section and setting:

```
[MAILMERGE]
FileLocation=location
```

where *location* is a temporary location that you specify for the CRM-related mail merge files that are generated on your Enterprise Server, for example:

```
\TEMP
```

## 11.6 Enabling Verity Enhanced Search Capability

If you are using the enhanced search capability with JD Edwards EnterpriseOne, you must download and install the Verity Software from the Oracle Software Cloud Web site at this link:

<http://edelivery.oracle.com/>



## 11.7 Working with the Data Dictionary

This chapter describes a scenario where you might be modifying your data dictionary on a machine other than your IBM i-based Enterprise Server or if you are modifying your Data Dictionary and not planning on building a package to reflect those changes. In such cases you need to use this mechanism to move the changes to your Enterprise Server.

Additionally, you might find this procedure useful for performance reasons if you do not want your Enterprise Server to JITI data dictionary specifications in real time.

This process is also useful to move generated serialized objects (required for web-enabled applications) from the Microsoft Windows web development workstation on which they were generated to the Enterprise Server.

### 11.7.1 Recreating Replicated Data Dictionary Files

To recreate replicated data dictionary files:

1. From the Data Dictionary Design menu (GH951), select Recreate Replicated Data Dictionary (R92TAM).
2. On Work with Batch Versions, select version XJDE0001.
3. On Version Prompting, from the Row menu, select Processing Options and enter the following information:
  - Language Preference  
Use the visual assist button to select the correct value for your language.
  - All Languages  
Enter the value 1.
4. Click OK.
5. Select version XJDE0001.
6. On Version Prompting, select Advanced from the Form menu.
7. On Advanced Version Prompting, activate the Override Location option.
8. Click OK.
9. On Version Prompting, click Submit.
10. After the job is completed, log off Release 9.1.

## 11.8 Working with SETOWAUT

SETOWAUT is a set of tools you can use to secure JD Edwards EnterpriseOne objects on your IBM i Enterprise Server. The SETOWAUT objects are delivered in a SAVF by the same name in the JDEOW library. However, it is recommended that you download the latest version of SETOWAUT from the Update Center.

This file can be restored using the RSTLIB command. It should be restored to a library called SETOWAUT. Instructions for using SETOWAUT are found in the JD Edwards EnterpriseOne Tools Server and Workstation Administration Guide.

## 11.9 UBE Performance ' SQL Package Location

Once the Table Conversions are completed, change the jde.ini setting on the Enterprise Server that controls where SQL Packages are created. The applicable setting is:

```
[DB SYSTEM SETTINGS]
sqlPackageLibrary=value
```

where value controls the location where JD Edwards EnterpriseOne will place SQL packages on your IBM i-based Enterprise Server.

This is shipped with a value of 2 in order for Table Conversions to work correctly. You must change this value to 0 or 1 otherwise you will see a negative performance impact on UBEs. Values are listed in this table:

| Value | Action                                                                                                                                                                                                                                                                                                                                                                                    |
|-------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 0     | <p>Indicates the system to create packages in the library defined in this jde.ini section:</p> <pre>[INSTALL] DefaultSystem=e1_system</pre> <p>where for JD Edwards EnterpriseOne Release 9.1 the default value for e1_system is E910SYS.</p>                                                                                                                                             |
| 1     | <p>Indicates the system will create packages in QRECOVERY and that UBE packages will be named Rnnnnn.</p> <p><b>Caution:</b> You will need to delete any old UBE SQL packages in QRECOVERY. Please note that no UBEs can be running on the server while you are deleting these packages.</p>                                                                                              |
| 2     | <p>Indicates the system will create packages in QRECOVERY and that UBEs are assigned unique names (job number). For example, a UBE name will be in the format T123456.</p> <p><b>Note:</b> You can use this setting for normal daily operations. However it will make the startup for your frequently run UBEs a little slower as they will not be able to use existing SQL packages.</p> |

---

## Working With Signon Security

---

For initial installations of JD Edwards EnterpriseOne, you must setup system user(s) using the Work With System Users (P980001) program to populate the F98OWPU table. You must set up system users before you can add and associate a JD Edwards EnterpriseOne user to a system user using EnterpriseOne Security (P98OWSEC).

---

**Caution:** If you attempt to add a user with the P98OWSEC program before you add the system user through the P980001 program, the system may add an invalid record to the F98OWPU table. You might have to delete the invalid record from F98OWPU using the SQL Query tool.

You must perform security setup signed on to JD Edwards EnterpriseOne from a deployed client. If you perform the steps signed on to the deployment server, you will not be updating the correct security tables for your JD Edwards EnterpriseOne system.

---


This chapter contains the following tasks:

- [Section 12.1, "Setting Up Signon Security"](#)
- [Section 12.2, "Enabling Server-Side Signon Security"](#)
- [Section 12.3, "Enabling Client-Side Signon Security"](#)
- [Section 12.4, "Setting Up JD Edwards EnterpriseOne Single Sign-on"](#)


### 12.1 Setting Up Signon Security

To set up signon security:

1. On P980001 [Work With System Users], click Add.



2. On System User Revisions, complete the following fields:
  - *System User*  
JDE
  - *Data Source*  
DEFAULT
  - *Password*  
Enter a valid password for your installation.
  - *Password Verify*  
Enter the same password that you entered in the password field.
3. Click OK.
4. Click Find to verify the new record was added.



5. On P98OWSEC [Work With User Security], complete the following field:

- *User ID \ Role*

JDE

6. Click Find.

7. Click Add.

8. On Security Revisions, complete the following fields:

- *User ID*  
JDE
- *Data Source*  
DEFAULT
- *System User*  
JDE
- *Password*  
Enter a valid password for your installation.
- *User Status*  
Ensure the Enabled radio button is selected.
- *Allowed password attempts*  
Enter a value applicable to your installation.
- *Password change frequency*  
Enter a value applicable to your installation.

9. Click OK.

10. Click Find to verify that the record was added.

## 12.2 Enabling Server-Side Signon Security

Ensure the `jde.ini` on the Enterprise Server has these settings to support signon security:

```
[SECURITY]
SecurityServer=server_name
User=JDE
Password=JDE
Default Role=*ALL
DefaultEnvironment=PD910
DataSource=System - 910
History=0
```

After you modify the `jde.ini` on the Enterprise Server, you must restart the JD Edwards EnterpriseOne Services so the settings can take effect.

---

---

**Caution:** If you have changed the password for the JDE user, the password you specify on Enterprise Server in `jde.ini` must be the new password.

---

---

## 12.3 Enabling Client-Side Signon Security

Locate the JD Edwards EnterpriseOne client `JDE.INI` that is deployed from the Deployment Server. Typically the file can be found at the following location:

```
x:\JDEdwards\E910\OneWorld Client Install\Misc\JDE.INI
```

where x: is the drive on which JD Edwards EnterpriseOne is installed.

Ensure that JD Edwards EnterpriseOne client `JDE.INI` has these settings:

```
[SECURITY]
SecurityServer=server_name
DataSource=System - 910
DefaultEnvironment=DV910
Default Role=*ALL
Row Security=NO_DEFAULT
```

## 12.4 Setting Up JD Edwards EnterpriseOne Single Sign-on

You must set up JD Edwards EnterpriseOne Single Signon Security using the procedures described in *Chapter 13, Setting Up EnterpriseOne Single Sign-On* of the *JD Edwards EnterpriseOne Tools Security Administration Guide*.

---

---

**Caution:** Using default settings may expose a potential security risk. Thus, it is highly recommended to overwrite the single sign-on settings using the single sign-on configuration applications discussed in *Chapter 13, Setting Up EnterpriseOne Single Sign-On* of the *JD Edwards EnterpriseOne Tools Security Administration Guide*.

---

---





---

## Manual Table Conversions

---

This section contains the manual table conversions that are required to finish the upgrade process if you are upgrading from previous releases.

---

**Note:** Whenever you submit a Manual Table Conversion from Batch Versions, check on the Properties box to ensure you specify the correct Source and Target environments. You must also override the location to Local as the Previous Release environment is not defined on the Enterprise Server.

---

This chapter describes these tasks:

- [Section 13.1, "Running Post Installation Tasks"](#)
- [Section 13.3, "Upgrading from 8.9 or Below"](#)
- [Section 13.4, "Upgrading from 8.10 or Below"](#)
- [Section 13.5, "Upgrading from 8.11 or Below"](#)
- [Section 13.6, "Upgrading from 8.11 SP1 or Below"](#)
- [Section 13.7, "Upgrading from 8.12 or Below"](#)
- [Section 13.8, "Upgrading from 9.0 or Below"](#)
- [Section 13.9, "Processing Options for R31P40039"](#)
- [Section 13.10, "Upgrading E1PAGE from Release 9.0 to Release 9.1"](#)

### 13.1 Running Post Installation Tasks

You must run post installation Universal Batch Engine (UBE) reports to successfully use your previous data. Unless noted otherwise, you should run these conversions from a client workstation in the environment that you are upgrading. When running against SQL Server, Oracle, or DB2\UDB, sign on as the data source owner if any of the post installation jobs are TCs which create temp tables.

Run these post installation UBEs after the automatic table conversion programs have completed successfully.

*See Also*

*JD Edwards EnterpriseOne Programmer's Guide* and the *JD Edwards EnterpriseOne Database Changes Guide* for detailed information, notes, and verification procedures regarding the following UBEs.

You must use the Fast Path field to navigate to the Post Install Menu (GH9619) where you run the UBEs listed in this table.

**Note:** If you do not use the Fast Path field to navigate to the Post Install Menu (GH9619), the menu selections may not display properly.

All Conversion Programs marked with \* must be run on the Deployment Server.

## 13.2 Upgrading from XE \ ERP 8.0

This section contains a list of all the Table Conversions required when upgrading from XE \ ERP 8.0.

### Upgrading from XE \ ERP 8.0

| Conversion Program | Run this Job                                                                                   | Requirements                                                                                                                                                                                                                                                                                                                                       | Purpose                                                                                                                                                                                                       | Notes                                                                                                                                                                                                                                                                                                                                                                                                              |
|--------------------|------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R890030B           | Only if you have taken the ESU in XE/ERP8.0 and are using F0031 Bank Transit Master Tag Table. | None                                                                                                                                                                                                                                                                                                                                               | To merge the F0031 Bank Transit Master Tag Table into the F0030 Bank Transit Master. The conversion will copy the data from the bank address number AN8BK in F0031 to the bank address number AN8BK in F0031. | None                                                                                                                                                                                                                                                                                                                                                                                                               |
| R8903B11P1         | To convert F03B11 from XE\ERP 8.0.                                                             | This is to be run after the A\R ledger has been successfully upgraded in the automatic Upgrade Plan. The basic F03B11 table conversion must have successfully run in your plan prior to running this Post Install job. Suspend all Invoicing and Sales Update activity from the time of the upgrade through the successful completion of this job. | Critical A\R features in invoicing will malfunction if this job is not run.                                                                                                                                   | Over a dozen new fields were introduced to the F03B11 table. The standard table conversion, which is run through the Table Conversion Scheduler application (P98430), initializes all of the new fields to default or blank values. Limitations in the table conversion tool prevent it from calculating values for some of the new fields in the F03B11 table. This post-install conversion supplements R8903B11. |

**Upgrading from XE \ ERP 8.0**

| <b>Conversion Program</b> | <b>Run this Job</b>                | <b>Requirements</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                            | <b>Purpose</b>                                                                                                                                                                                                                                                                                                                                                     | <b>Notes</b>                                                                                                                                                                                                                                                                                                              |
|---------------------------|------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R890411P1                 | To convert F0411 from XE\ERP 8.0.  | This is to be run after the A\P Ledger has been successfully upgraded in the automatic Upgrade Plan. Suspend all Vouchering and Voucher Match activity from the time of the upgrade through successful completion of this job.                                                                                                                                                                                                                                                 | Critical A\P features in invoicing will malfunction if this job is not run.                                                                                                                                                                                                                                                                                        | New fields have been added to F0411. This updates the domestic amount to distribute (ATAD), foreign amount to distribute (CTAD), domestic non recoverable tax amount (NRTA), foreign non recoverable tax amount (FNRT) and base company currency code (BCRC). The Purchase Order number (RPPO) is left padded with zeros. |
| R89069116                 | To convert F069116 from XE         | None.                                                                                                                                                                                                                                                                                                                                                                                                                                                                          | This table conversion populates the new field PHISH.                                                                                                                                                                                                                                                                                                               | The following fields were added to F069116: LVPT and PHISH. After this program is run, PHISH will contain "1 ". LVPT will remain blank.                                                                                                                                                                                   |
| R8908601C                 | To convert F08601 from XE\ERP 8.0. | The processing option of this job should be set based on whether only JD Edwards World was used to enter Health and Safety information from the source environment. A processing option value of 1 indicates that JD Edwards World was used, while a processing option value of 0 or Blank indicates that JD Edwards World was not used exclusively for information entry and JD Edwards EnterpriseOne applications may have been used to enter Health and Safety information. | This table conversion checks for and handles the following scenarios:<br><br>1. Processing option is set to 1 (indicates that yes, only JD Edwards World was used to enter Health and Safety information).<br><br>2. Processing option is set to 0 or Blank (indicates that no, JD Edwards World was not used exclusively to enter Health and Safety Information). | Country (CTR) and Incident Occurred on Employer's Premises (ONPRM) columns were added to F08601.                                                                                                                                                                                                                          |

**Upgrading from XE \ ERP 8.0**

| <b>Conversion Program</b> | <b>Run this Job</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              | <b>Requirements</b>                                                                                                                                                                                                                                                                                                                                                                                                                        | <b>Purpose</b>                                                                                                                                                                                                                                                                                   | <b>Notes</b>                                                                                                                                                                                                                                                                                                                                                                                                                                           |
|---------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R890015B                  | To convert F0015 from XE\ERP 8.0 for Triangulation Exchange Rates.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               | This program must run after R891015A - F0015\F00151 Exchange Rate table conversion has completed successfully and the F0015 Currency Exchange Rate table has been upgraded successfully in the automatic Upgrade Plan. Suspend any processes requiring exchange rates from the time of the upgrade through the successful completion of the job. The following objects are required:<br><br>F0015<br><br>R891015B<br><br>R891015B\XJDE0001 | Triangulation exchange rates have values of zero if this job is not run.                                                                                                                                                                                                                         | After running the R891015A - F0015\F00151 Exchange Rate table conversion the triangulation records have rates that are blank or zero. This selects records from the converted F0015 table where the calculation method is triangulation (CLMETH=3). The rates for the triangulation records are retrieved from the corresponding rates in the F0015 table for both multiplier (CRR) and divisor (CRRD) rates and updated to the triangulation records. |
| R891216                   | To convert F1216 when upgrading from XE\ERP 8.0 and requires special attention for whether or not SAR 5685791 has been applied to JD Edwards EnterpriseOne Xe. If this SAR has been applied to Xe before upgrading, then there is no need for F1216 data conversion because the data has already been corrected when the SAR was applied. Otherwise, the F1216 data needs to be corrected to fix the data that has been entered from JD Edwards EnterpriseOne before.<br><br>Migrating from JD Edwards World does not require the F1216 data conversion because the data entered from JD Edwards World is in the correct format. | None                                                                                                                                                                                                                                                                                                                                                                                                                                       | This conversion program corrects existing data in the F1216 table that has been entered using JD Edwards EnterpriseOne Xe. The conversion program only modifies data that is stored incorrectly in the table. The conversion program reformats data in the F1216 table and corrects the mapping. | When upgrading from Xe/ERP 8.0, the F1216 table may need a data conversion to correct the data that has previously been entered from JD Edwards EnterpriseOne. Please, also refer to the Breaking News message that has been published with regard to these issues and the data conversion for JD Edwards EnterpriseOne Xe.                                                                                                                            |

**Upgrading from XE \ ERP 8.0**

| <b>Conversion Program</b> | <b>Run this Job</b>                                                                                                                                                                                   | <b>Requirements</b>                                                                                                                                                                                                   | <b>Purpose</b>                                                                                                                                                                                                                                | <b>Notes</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|---------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R894801P                  | To convert F4801 \ F4801T \ F4817 from XE\ERP 8.0 when working with configured items, serialized components, or generating orders through Customer Service and Warranty or Equipment and Maintenance. | Two processing options exist for this report:<br>Convert URCD<br>Convert PARS<br><br>If the client does not use serialized components or work with configured items, these processing options should be set as blank. | This report must run to consolidate the F4817 table records into the F4801T tables, set the SRCN field, and reset the configured work order's parent number to the immediate higher related work order in the configured item's construction. | This report consolidates the F4801T and F4817 tables, properly sets the new serialized component field in F4801T, and reassigns the parent work order numbers for the configured item work orders.                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| R8948164A                 | To convert F48164 Media Objects from XE\ERP 8.0 for old Knowledge Base.                                                                                                                               | Requires that table conversions for F00165 and F48164 completed successfully.                                                                                                                                         | To properly convert old Knowledge Base media objects. If this is not run, that information is not available for use by the new Failure Analysis applications.                                                                                 | The media object structure for Failure Analysis has changed. Previously, the media objects were stored in one structure. Now, the media object structure is split into three separate structures.                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| R8930006D                 | To convert F30006 Work Center Master from XE\ERP 8.0.                                                                                                                                                 | R8930006C must have completed successfully                                                                                                                                                                            | Blank values in the work center branch plant field are no longer supported because application P3003 and P3112 validate the work center and the branch plant being used.                                                                      | The primary key of the F30006 table was changed from Work Center (MCU) to Branch/Plant (MMCU) and Work Center in order to support the concept of the work center branch plant. R8930006C is responsible for placing each work center into the respective branch plants based on records found in the F3003 table. However, in the event that the work center is not used in F3003, the branch plant remains blank in the F30006 table. R8930006D assigns these work centers with a default branch plant value, and selects all records with a Branch/Plant of blank and sets the field equal to the default Branch/Plant in the processing option. |

**Upgrading from XE \ ERP 8.0**

| <b>Conversion Program</b> | <b>Run this Job</b>                                                                 | <b>Requirements</b>                                                                                                                                                                                                                                              | <b>Purpose</b>                                       | <b>Notes</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|---------------------------|-------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R3365                     | To regenerate the Resource Profile in Capacity Planning.                            | Run the batch application R3365 to populate F3303 Capacity Resource Profile. Make sure F4101, F4102, F3002, F3003, F30006, F3007 and F0007 tables have converted for existing data. Data for F3460 is already available since the table has not been changed.    | Populates the F3303 Capacity Resource Profile table. | A new field was introduced to the F3303 table. A table conversion was not created for this table due to the complexities of the logic in conversion and the existing solution of running this batch application to create the Resource Profile.                                                                                                                                                                                                                                                                                                                                                                                                                 |
| R3380                     | To convert F3311 \ F3312 \ F3313 from XE\ERP 8.0 for Resource Requirement Planning. | Run the batch application R3380 to populate F3311, F3312, F3313. Make sure F4101, F4102, F3002, F3003, F30006, F3007, F0007, F3411 and F33133 tables have converted for existing data. Data for F3460 is already available since the table has not been changed. | Populates the F3311, F3312, and F3313 tables.        | A new field was introduced to the F3311, F3312, and F3313 tables. Table conversions were not created for these tables because of the complexities of the logic in conversion and the existing solution of running batch applications to create Capacity Message, Capacity Pegging and Capacity Load. The R3380 or R3382 programs are the existing batch applications. User has to select either Resource Requirements Planning (R3380) or Rough Cut Capacity Planning\Capacity Requirements Planning (R3382) depending on whether they are using Resource Requirements Planning (RRP) or Rough Cut Capacity Planning\Capacity Requirements Planning (RCCP\CRP). |

---

**Upgrading from XE \ ERP 8.0**


---

| <b>Conversion Program</b> | <b>Run this Job</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       | <b>Requirements</b>                                                                                                                                                                                                                                                             | <b>Purpose</b>                                                                                                                                                                                                                                                                                                                                                      | <b>Notes</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|---------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R3382                     | To convert F3311 \ F3312 \ F3313 from XE\ERP 8.0 for Rough Cut Capacity Planning\Capacity Requirements Planning.                                                                                                                                                                                                                                                                                                                                                                                                                                          | Run the batch application R3382 to populate F3311, F3312, F3313. Make sure F4101, F4102, F3002, F3003, F30006, F3007, F0007, F3411 and F33133 tables have converted for existing data. Data for F3460 is already available since the table has not been changed.                | Populates the F3311, F3312, and 3313 tables.                                                                                                                                                                                                                                                                                                                        | A new field was introduced to the F331, F3312, and F3313 tables. Table conversions were not created for these tables because of the complexities of the logic in conversion and the existing solution of running batch applications to create Capacity Message, Capacity Pegging and Capacity Load. R3380 or R3382 is the existing batch application. User has to select either Resource Requirements Planning (R3380) or Rough Cut Capacity Planning\Capacity Requirements Planning (R3382) depending on whether they are using Resource Requirements Planning (RRP) or Rough Cut Capacity Planning\Capacity Requirements Planning (RCCP\CRP). |
| R31P40039                 | <p>To convert F40039 when upgrading from XE\ERP 8.0.</p> <p>If you have chosen a new document type for some work orders, which is different from the document type you used in the past for those work orders, you must run R48803 in order to correct that document type in your tables. See the Setup instructions in the Enterprise Asset Management, Shop Floor and the Engineering Project Management Guides for more details.</p> <p><b>Note:</b> See the table below for information regarding the values to enter for the processing options.</p> | This is to be run immediately after upgrading to validate all programs using F4801\F4801T Order Type prior to database output. Make sure all order types in the 00\DT have been set up in the Document Type Revisions (P40040) before running R31P40039 to convert work orders. | If different types of work orders have been mixed in a single Order Type value, they must convert the F4801 work orders to separate the records by order type. If this job is not run, none of the programs that enter data into F4801\F4801T (for example, Manufacturing Work Order Entry, Equipment Order Entry, Service Order Entry, etc.) are able to function. | It is necessary that all Work Order Types be unique, which is set up in the Document Type Master. For example, an order type of "WO" needs to be set equal to "02" (Manufacturing Work Order). This is set up manually using Document Type Revisions (P40040), or by running F40039 Conversion from Xe (R31P40039). If there are a large number of order types to set up, the UBE may be more efficient. This should be set up once, prior to the following steps.                                                                                                                                                                              |

---

**Upgrading from XE \ ERP 8.0**

| <b>Conversion Program</b> | <b>Run this Job</b>                                                                                                                                                                       | <b>Requirements</b>                                                                                                                                           | <b>Purpose</b>                                                                                                                                                   | <b>Notes</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|---------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R8903B571A                | To set next unique key id for F03B571 when upgrading from XE\ERP 8.0.                                                                                                                     | The table upgrade plan should be successfully completed. Suspend all Automatic Debit processing until this UBE completes successfully.                        | This job must be run for Autodebit processing to function correctly.                                                                                             | This report adds\updates an entry in the F00022 table for the F03B571 table and sets the next unique key ID equal to the next auto debit batch control number.                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| R8900165K                 | To change GT0411S Key to use KCO when upgrading from XE\ERP 8.0 and have not yet taken SAR 5848035. Also this UBE is only required for users using Media Object Attachments for vouchers. | This is to be run after the F00165 table has been successfully upgraded in the automatic Upgrade Plan. Objects required: Change GT0411S Key to use KCO not CO | After running this job existing Media Objects Attachments for Vouchers are accessible from the Voucher Entry Program (P0411) and Speed Status Change (P0411S).   | This conversion program takes records from the F00165 with object name (OBNM) equal to GT0411S and ensures that the Generic Text Key (TXKY) is written in the format KCO DCT DOC SFX. Where records are written with TXKY format equal to CO DCT DOC SFX it replaces the generic text key field with KCO instead of CO and preserves the rest of the key.                                                                                                                                                                                                                                       |
| R8900165JA                | To convert F00165 JEDTLGT to GT0911A when upgrading from XE\ERP 8.0.                                                                                                                      | This is to be run after the F00165 table has been successfully upgraded in the automatic Upgrade Plan. Requires objects: F00165 Convert JEDTLGT to GT0911A    | After running this job, existing Media Objects attachments for voucher G\L distributions are accessible from the Voucher G\L Distribution form (P0411   W0411K). | This process converts all voucher G\L distribution attachment records in the F00165 table to be coexistent with JD Edwards World and with JD Edwards EnterpriseOne A\R and G\L systems. Attachments entered for voucher G\L distribution records were written to F00165 with Object Name (OBNM) equal to JEDTLGT. Instead, these should have been written with Object Name equal to GT0911A. For each record in F00165 with Object Name (OBNM) equal to JEDTLGT, this conversion changes the Object Name to GT0911A and modifies the Generic Text Key (TXKY) to match the structure of GT0911A. |



---

**Upgrading from XE \ ERP 8.0**


---

| <b>Conversion Program</b> | <b>Run this Job</b>                                                                                     | <b>Requirements</b>                                                                                                                                        | <b>Purpose</b>                                                                                                                                                       | <b>Notes</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
|---------------------------|---------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R8900165JB                | To convert JEDOCGT to GT0911 when upgrading from XE\ERP 8.0.                                            | This is to be run after the F00165 table has been successfully upgraded in the automatic Upgrade Plan. Requires objects:F00165 Convert JEDOCGT to GT0911A. | After running this job, existing Media Objects attachments for Journal Entry document levels are accessible from the Account Ledger Inquiry form (P09200   W09200A). | This process converts all journal entry document level attachment records in the F00165 table to be coexistent with JD Edwards World and with JD Edwards EnterpriseOne A\R and G\L systems. Attachments entered for journal entry document levels were written to F00165 with Object Name (OBNM) equal to JEDOCGT. Instead, these should have been written with Object Name equal to GT0911A. For each record in F00165 with Object Name (OBNM) equal to JEDOCGT, this conversion changes the Object Name to GT0911A and modifies the Generic Text Key (TXKY) to match GT0911A's structure. |
| R89060117A                | To populate F060117A when upgrading from XE\ERP 8.0 and this job has not been run previously in an ESU. | None                                                                                                                                                       | Transfers any values that were stored in the F060117 table to the replacement field ALRN15 in the F060117A.                                                          | The original F060117 table contains a field to store the Alien Registration Number (ALRN). However, this field is not long enough to store an Admissions Number, which is an acceptable value for this field. The F060117A tag table was created with an appropriate length field (ALRN15) that replaces the one in the original table.                                                                                                                                                                                                                                                     |
| R89060117                 | To populate Employee Master Tag Tables when upgrading from XE\ERP 8.0.                                  | None.                                                                                                                                                      | This TC populates the F060117 record for every existing F060116 record.                                                                                              | Prior to 8.9 the F060117 table was treated as a tag to F060116, in that it may or may not have a corresponding record in F060117 if a record existed in F060116. After 8.9 the application was changed so that if there was no F060117 record an error would be issued. This TC populates the F060117 record for every F060116 record, so that the application will not error automatically.                                                                                                                                                                                                |

---

**Upgrading from XE \ ERP 8.0**

| <b>Conversion Program</b> | <b>Run this Job</b>                                                                                     | <b>Requirements</b>                                                                                                                                    | <b>Purpose</b>                                                                                                                                                     | <b>Notes</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
|---------------------------|---------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R890912                   | To format OBJ and SUB in F0912 when upgrading from XE\ERP 8.0.                                          | F0912, R890912 and R890912 \ XJDE0001 are required. The data stored in F0912 from a prior release is required. Suspend activity during the conversion. | Programs and applications requiring access to RJFROM and RJTHRU will not perform properly if the data has not been concatenated.                                   | In JD Edwards World, application P0912 Recurring Journal Entry stored data for object and sub in separate fields. In EnterpriseOne, RJFROM and RJTHRU are used to store a combined object and sub. The table conversion concatenates OBJF and FSUB to form RJFROM, and OBJT and SUBT to form RJTHRU. This prevents the trouble of combining object and sub every time the fields are read and displayed. The table conversion retrieves the account separator from the General Accounting Constants for use when combining the two fields. |
| R891201A                  | To update WOYN in F1201 when upgrading from XE\ERP 8.0 to create Work Orders against equipment records. | Run after the table conversions have completed.                                                                                                        | Work Orders cannot be created against any equipment record that does not have this flag turned on.                                                                 | Logic was added to reference the Work Order Allowed Flag (WOYN) located in the F1201 table. This flag indicates whether a piece of equipment is allowed to have a Work Order entered against it. Previously WOYN existed in F1201 but was not referenced in the Work Order creation logic.                                                                                                                                                                                                                                                 |
| R8948SINV                 | To convert INV to Uppercase when upgrading from XE\ERP 8.0.                                             | None.                                                                                                                                                  | This job should be run to ensure all Invoice Format Codes within Service and Contract Billing are uppercase and consistent across all tables that store this code. | The Data Item is modified for Invoice Format Code(INV) to be uppercase only.                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| R8908601                  | To update HH05 in F08601 when upgrading from XE\ERP 8.0.                                                | None.                                                                                                                                                  | The table conversion R8908601 changes the data for HH05 in F08601 (Injury\Illness Case Master) from 1-7 to 01-05.                                                  | The OSHA 300 is now consistent with the one on the OSHA website. The number of injury\illness types has been reduced to 5 from 7. This is a legislative change.                                                                                                                                                                                                                                                                                                                                                                            |

**Upgrading from XE \ ERP 8.0**

| <b>Conversion Program</b> | <b>Run this Job</b>                                                                                    | <b>Requirements</b>                                                                               | <b>Purpose</b>                                                                                                                    | <b>Notes</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
|---------------------------|--------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R080101                   | To set Address Book AT3 and synchronize ALPH and SSN for HR related Address Book records.              | None.                                                                                             | This job should be run to ensure synchronization of the ALPH and SSN fields between the F0101 and the F060116, F08401 and F08901. | Many tables used in the workforce management suite have ALPH and SSN fields. The address book table also has these two fields. In an effort to keep the duplicate data consistent across the database a flag in the F0101 (AT3) is set to a Y to indicate that changes should be updated to these additional tables. Previously the synchronization was based solely on search type, this method was deemed inadequate because search type is somewhat user defined and hard coding is not appropriate. This UBE takes existing records in the F0101 and if a matching record exists in one of three tables (F060116, F08401 and F08901) the AT3 flag is updated to a Y. If either the ALPH or SSN is out of sync the F0101 values are updated to the corresponding table. |
| R7611B                    | To update BSTT in F7611B when upgrading from XE\ERP8.0, and have not taken ESU #4937298.               | Requires clear understanding of the Brazil process on how to populate the F7611B table correctly. | The ICMS Tax Situation Code (BSTT) contains incorrect values if this job is not run.                                              | This is a data conversion UBE that converts the ICMS Tax Situation Code (BSTT) field based on an algorithm.<br><br>Do not execute for a World A9.2 migration.<br><br>Do not re-run from the Xe/E80 Post Install menu for World A7.3 migration.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| R897611B                  | To populate BST1 in F7611B when upgrading from XE\ERP 8.0, and have run the pre-requisite R7611B once. | Requires clear understanding of the Brazil process on how to populate the F7611B table correctly. | The new ICMS Tax Situation Code (BST1) has incorrect values if this job is not run.                                               | Populates a new ICMS Tax Situation code field (BST1) in table F7611B with the concatenated value of Item Origin (BORI) and old ICMS Tax Situation Code (BSTT). This new BST1 field is now of size=3 as compared to size=2 for prior releases.<br><br>Do not execute for a World A9.2 migration.<br><br>Do not re-run from the Xe/E80 Post Install menu for World A7.3 migration                                                                                                                                                                                                                                                                                                                                                                                            |

**Upgrading from XE \ ERP 8.0**

| <b>Conversion Program</b>                                                | <b>Run this Job</b>                                                                                                             | <b>Requirements</b>                                                                                                                                                                                                                                                                                                        | <b>Purpose</b>                                                                                                                   | <b>Notes</b>                                                                                 |
|--------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------|
| R98403A<br> XJDE0001<br><br>* Must Run<br>on the<br>Deployment<br>Server | All customers                                                                                                                   | Run after all table conversions have been completed. Do not alter the Data Selection for this table conversion. Set processing options to copy the tables from Source Environment JDEPLAN to the Target Environment you are upgrading to, for example, DV9.                                                                | Errors due to missing vital data occur if this job is not run. For example, writing to certain accounts could generate an error. | Copies the data contained in demo data on the installation image to the customer's database. |
| R9500165                                                                 | To remove RTF formatting. Run if you cannot see any customized dictionary glossaries when viewing them through the application. | Run after table conversion process. Most customers do not need to run the UBE. Check your customized data dictionary glossaries. If they appear to have disappeared, schedule this UBE to run at a convenient time. There is no loss of data. Once the UBE has run, the glossaries are visible. It runs for several hours. | Rerun if glossary items are missing (most likely for Korean and Japanese glossary items).                                        |                                                                                              |

---

**Upgrading from XE \ ERP 8.0**


---

| <b>Conversion Program</b> | <b>Run this Job</b>                                          | <b>Requirements</b>                                                                                                                      | <b>Purpose</b>                    | <b>Notes</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|---------------------------|--------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R8991300                  | To upgrade Scheduler Job Master when upgrading from Xe\ERP8. | This conversion must be run before the F0092 series of conversions is complete. That series includes R89959212, R89959211, and R8995921. | Run from the JDEPLAN environment. | <p>The conversion reads over the F91300 table row by row. Except for the *Scheduler record it fetches the user group out of F0092 based on the user id stored in SCHUSER in F91300. The user group from F0092 is then stored in SCHROLE.</p> <p>It is important that customers designate the Properties of the table conversion to input the source environment (for example, DV7333) and the target environment (for example, DV910) so that the records are properly located and updated. If you do not check the Properties box in the Table Conversion Prompting screen, the UBE is submitted with whatever has been previously designated in the options (if anything). Also, because no PDF is created, you should check the TC log in the Print Queue directory to determine if there were errors or any problems during the execution.</p> |
| R8991320                  | To upgrade Job Schedule when upgrading from Xe\ERP8.         | This conversion must be run before the F0092 series of conversions is complete. That series includes R89959212, R89959211, and R8995921. | Run from the JDEPLAN environment. | <p>The conversion reads over the F91320 table row by row. It fetches the user group out of F0092 based on the user id stored in SCHUSER in F91320. The user group from F0092 is then stored in SCHROLE.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |

---

**Upgrading from XE \ ERP 8.0**

| <b>Conversion Program</b> | <b>Run this Job</b>                                                                                                                                                                                                                   | <b>Requirements</b>                                                                                                                                                                                                                 | <b>Purpose</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            | <b>Notes</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
|---------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R89959212                 | This UBE populates the F0092 (User Profiles) table and the F00926 (Role Descriptions) from the Roles and Descriptions that may have been previously set up in the UDC H95\RL. This UDC was used for Phase I and is now being removed. | <p>Only required if the customer is upgrading from a release prior to 8.9.</p> <p>If applicable to your upgrade, this UBE should be run as the first in this 3-part sequence:</p> <p>R89959212</p> <p>R89959211</p> <p>R8995921</p> | <p>The UBE uses each Role from the UDC H95\RL (the role is stored in the data item column KY in the F0005 table). The UBE populates the UGRP field in the F0092 table with this Role. It also populates the F00926 table with the Role Description, previously in the DL01 and DL02 columns of the F0005 table, the values in these columns are concatenated and inserted into the F00926 table, column ROLEDESC. If the insert to the F0092 table is successful, the F0005D table is then fetched upon to retrieve all of the possible language descriptions for the Role Descriptions. Those, as well, are populated in the F00926 table. Each Domestic Language Record in the F00926 table contains a Sequence Number. When running this UBE, the sequence numbers begin at 500 and increase by 5.</p> | <p>The 8.9 release introduces Roles. If upgrading from a release prior to 8.9, you must run a sequence of UBEs to convert Groups (as listed in the F0092) table to Roles. This creates a sequence number for each role and inserts role relationships based upon users\group records in the F0092 table. If you are running ERP 8.9 or later and wish to upgrade, you do not need to run these UBEs as the F0092, F00926 and F95921 tables already contain the necessary records.</p> |

---

**Upgrading from XE \ ERP 8.0**


---

| <b>Conversion Program</b> | <b>Run this Job</b>                                                                                                                                                                                                                                                                                                                                                                                | <b>Requirements</b>                                                                                                                                                                                                                                                                                                                                                    | <b>Purpose</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        | <b>Notes</b>                       |
|---------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------|
| R89959211                 | This TC takes all current Groups in the UGRP field in the F0092 table and adds a Description record for them in the F00926 table. The Role is the Group name (Ex: OWTOOL), the description is also the Group Name as a description is required. A sequence Number is added to the F00926 record as well. This sequence number begins at 1000 and increments by 5 with each record written.         | <p>Only required if the customer is upgrading from a release prior to 8.9.</p> <p>If applicable to your upgrade, this UBE should be run as the second in this 3-part sequence:</p> <p>R89959212<br/>R89959211<br/>R8995921</p>                                                                                                                                         | The UBE retrieves each Group from the F0092 table. It populates the USER field in the F00926 table with this Role. It also populates the F00926 table with the Role Description which is also the Group value from the F0092 table. This value is inserted into the F00926 table, column ROLEDESC. Each Domestic Language Record in the F00926 table contains a Sequence Number. When running this UBE, the sequence numbers begin at 1500 and increase by 5.                                                                                                         | Refer to Notes in R89959212 above. |
| R8995921                  | This TC takes all current User Profiles records in the F0092 table and inserts a User\Role Relationship Record based on the F0092.USER and F0092.UGRP tables. The record that is added to the F95921 table contains the User, Role (formerly the Group for this user in the F0092 table), Effective and Expiration Dates. Some of these values are based upon the values in the processing option. | <p>Only required if the customer is upgrading from a release prior to 8.9.</p> <p>If applicable to your upgrade, this UBE should be run as the third in this 3-part sequence:</p> <p>R89959212<br/>R89959211<br/>R8995921</p> <p>Values in the records inserted into the F95921 table are based upon those inserted into the processing option at submission time.</p> | The UBE retrieves each User Record from the F0092 (User Profiles) table. It populates the following output fields:<br>F95921.RLFRROLE - F0092.USERF95921.<br>RLTOROLE - F0092.UGRPF95921.<br>RLEFFDATE - PO EffectiveDateF95921.<br>RLEXPDATE - PO ExpirationDateF95921.<br>1.RLFUROLE1 - PO cIncludedInAllF95921.<br>1.RLROLETYP - "0"<br>And Audit Info. The F95921 table is inserted with the information above. One Record per user in the F0092 table. If the Mode of the version is Final, the F0092.UGRP field is left blank for all users in the F0092 table. | Refer to Notes in R89959212 above. |

---

## 13.3 Upgrading from 8.9 or Below

This section contains a list of all the Table Conversions required when upgrading from 8.9 or below.

| Upgrading from 8.9 or Below |                                                                                                                                                                                      |                                                                                                                                                                   |                                                                                                                                                                                                          |                                                                                                                                                                                                                                                                                                                                                                                                                            |
|-----------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Conversion Program          | Run this Job                                                                                                                                                                         | Requirements                                                                                                                                                      | Purpose                                                                                                                                                                                                  | Notes                                                                                                                                                                                                                                                                                                                                                                                                                      |
| R48803                      | Convert Document Type for existing orders by running the post install JD Edwards EnterpriseOne UBE R48803. Before running this UBE, see the Programmer's Guide for more information. | Before running the UBE, see the Programmer's guide about more information regarding who should run the UBE, requirements of the UBE, and the purpose of this UBE. | Not applicable.                                                                                                                                                                                          | This is not a Table conversion for converting data from prior release. This is a post install UBE that needs to be run one time to convert Order Types for existing records. This conversion is necessary because of changes made to Document Types, based on EPM requirements. The new document type is defined in the processing options. For the orders selected in the data selection, the document type is converted. |
| R891207B                    | To update PDFG in F1207 when upgrading from 8.9 or below.                                                                                                                            | The TC should be run over the entire F1207 table.                                                                                                                 | This post-install job reads through existing maintenance schedules in the F1207 and updates the schedule type (PDFG) field with a "1" for those schedules that have no service intervals defined.        | As part of the Condition-Based Maintenance enhancement, the schedule type (PDFG) field is now utilized on the Equipment PM Schedule (F1207) record to identify the type of maintenance. A value of blanks is for Interval Based Maintenance. A value of "1" is for Unschedule Maintenance. A value of "2" is for Condition-Based Maintenance.                                                                              |
| R8912071B                   | To update PDFG in F12071 when upgrading from 8.9 or below.                                                                                                                           | The TC should be run over the entire F12071 table.                                                                                                                | This post-install job reads through existing model maintenance schedules in the F12071 and updates the schedule type (PDFG) field with a "1" for those schedules that have no service intervals defined. | As part of the Condition-Based Maintenance enhancement, the schedule type (PDFG) field is now utilized on the Equipment PM Schedule Model (F12071) record to identify the type of maintenance. A value of blank is for Interval Based Maintenance. A value of "1" is for Unscheduled Maintenance. A value of "2" is for Condition-Based Maintenance.                                                                       |



**Upgrading from 8.9 or Below**

| <b>Conversion Program</b> | <b>Run this Job</b>                                    | <b>Requirements</b> | <b>Purpose</b>                                                                                       | <b>Notes</b>                                                                                                                                                                                          |
|---------------------------|--------------------------------------------------------|---------------------|------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R3210CFGID                | To convert Config ID when upgrading from 8.9 or below. | None.               | This UBE determines the highest seed from F3201 and writes it to Bucket 2 of Next Numbers System 32. | The Configuration ID (which is the primary key field of Configurator F3201 Master File) will now be retrieved from Next Number instead of using the "seed" record in F3201 Configurator Master Table. |

**13.4 Upgrading from 8.10 or Below**

This section contains a list of all the Table Conversions required when upgrading from 8.10 or below.

**Upgrading from 8.10 or Below**

| <b>Conversion Program</b> | <b>Run this Job</b>                                                           | <b>Requirements</b>                                                                                                                                                                                                                                                                                            | <b>Purpose</b>                                                                                                                                                               | <b>Notes</b>                                                                                             |
|---------------------------|-------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------|
| R8901151                  | To move Email Address from F0111 to F01151 when upgrading from 8.10 or below. | Four processing Options exist for this conversion:<br>1 - Run in Proof or Final Mode.<br>2 - Do you want to reset the remark field in F0101 to blank or not.<br>3 - Enter the default value of the Email Hierarchy field.<br>4 - Process all records or only records with an associated User ID.               | This conversion moves Email addresses from the Who's Who table (F0111) to the Electronic Address table (F01151). If this is not run, Email addresses will not be accessible. | The UBE prints out a pdf listing the records processed and displays how the F01151 columns were updated. |
| R891755B                  | To convert F1755 for Case when upgrading from 8.10 or below.                  | Three Processing Options exist for this TC:<br>1 - Enter the time zone of the system date and time.<br>2 - Enter the daylight savings rule of the system date and time.<br>3 - Do you want to update the work order table with the case number of the record being converted? "0" - Do Not Update. "1" Update. | To convert the existing dates and times in F1755 to UTC time. To blank out the work order number in F1755 and to populate case number in F4801.                              |                                                                                                          |

**Upgrading from 8.10 or Below**

| <b>Conversion Program</b> | <b>Run this Job</b>                                                        | <b>Requirements</b>                                                                                                                   | <b>Purpose</b>                                                                                                                                                            | <b>Notes</b>                                                                                                                                                                                                                                                                                                                       |
|---------------------------|----------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R3210CFGID                | To convert Config ID when upgrading from 8.10 or below.                    | None.                                                                                                                                 | This UBE determines the highest seed from F3201 and writes it to Bucket 2 of Next Numbers System 32.                                                                      | The Configuration ID (which is the primary key field of Configurator F3201 Master File) will now be retrieved from Next Number instead of using the "seed" record in F3201 Configurator Master Table.                                                                                                                              |
| R01302                    | To convert F0101 Compressed Description when upgrading from 8.10 or below. | Run this UBE when UDC H95 SC has changed. The values shipped with the software are:<br>~!@#^&*()_<br>+`-= {}   [] \ : ; ' < > ? , . \ | This UBE strips off special characters from the DC field in F0101 as a result of changing the UDC H95 SC (Word Search Special Characters).                                | If the UDC H95 SC values are changed and an address book record is added, this will cause inconsistencies in the DC fields. An example of this would be the blank value. If blank is part of the list, the "Digger Corporation" will be stripped to be "DIGGERCORPORATIO N" in the DC field else it would be "DIGGER CORPORATION". |
| R890911CA                 | To populate F0911 Foreign Amount when upgrading from 8.10 or below.        | Run after the table conversions have completed.                                                                                       | A new foreign amount field (GLACR) is added to the Account Ledger table. The TC will populate the new foreign amount field based on the existing CA ledger records.       | A new foreign amount field (GLACR) is added to the Account Ledger table so all of the currency information is available in one F0911 record and the extra CA record is no longer needed. The system continues to write the CA ledger records during this first phase.                                                              |
| R890911PCA                | To populate F0911P Foreign Amount when upgrading from 8.10 or below.       | Run after the table conversions have completed.                                                                                       | A new foreign amount field (GLACR) is added to the Account Ledger Purge table. The TC will populate the new foreign amount field based on the existing CA ledger records. | A new foreign amount field (GLACR) is added to the Account Ledger Purge table so all of the currency information is available in one F0911 record and the extra CA record is no longer needed. The system continues to write the CA ledger records during this first phase.                                                        |

## 13.5 Upgrading from 8.11 or Below

This section contains a list of all the Table Conversions required when upgrading from 8.11 or below.

**Upgrading from 8.11 or Below**

| <b>Conversion Program</b> | <b>Run this Job</b>                                    | <b>Requirements</b>                                                                           | <b>Purpose</b>                                                                                         | <b>Notes</b>                                                                                                                                                                                                                                                                                                                                                                                          |
|---------------------------|--------------------------------------------------------|-----------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R8908771A                 | To populate F08771A when upgrading from 8.11 or below. | The Processing Option of this job sets the value for the new field MSEB in the table F08771A. | This TC populates the F08771A tag table with the MSEB value from the processing option value selected. | The tag table F08771A was added with the MSEB column to allow managers to signoff on the final performance appraisal on behalf of the employee. A value of "1" means Yes, managers can approve or contest the final appraisal on the employee's behalf. A value of "0" means No, employees access the appraisal system through Employee Self Service and approve or contest the appraisal themselves. |
| R8908772A                 | To populate F08772A when upgrading from 8.11 or below. | The Processing Option of this job sets the value for the new field MSEB in the table F08772A. | This TC populates the F08772A tag table with the MSEB value from the processing option value selected. | The tag table F08772A was added with the MSEB column to allow managers to signoff on the final performance appraisal on behalf of the employee. A value of "1" means Yes, managers can approve or contest the final appraisal on the employee's behalf. A value of "0" means No, employees access the appraisal system through Employee Self Service and approve or contest the appraisal themselves. |
| R8908773A                 | To populate F08773A when upgrading from 8.11 or below. | The Processing Option of this job sets the value for the new field MSEB in the table F08773A. | This TC populates the F08773A tag table with the MSEB value from the processing option value selected. | The tag table F08773A was added with the MSEB column to allow managers to signoff on the final performance appraisal on behalf of the employee. A value of "1" means Yes, managers can approve or contest the final appraisal on the employee's behalf. A value of "0" means No, employees access the appraisal system through Employee Self Service and approve or contest the appraisal themselves. |

---

**Upgrading from 8.11 or Below**


---

| <b>Conversion Program</b> | <b>Run this Job</b>                                                | <b>Requirements</b>                                                                            | <b>Purpose</b>                                                                                          | <b>Notes</b>                                                                                                                                                                                                                                                                                                                                                                                            |
|---------------------------|--------------------------------------------------------------------|------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R89087711A   XJDE0001     | To populate F087711A Current when upgrading from 8.11 or below.    | The Processing Option of this job sets the value for the new field MSEB in the table F087711A. | This TC populates the F087711A tag table with the MSEB value from the processing option value selected. | The tag table F087711A was added with the MSEB column to allow managers to sign off on the final performance appraisal on behalf of the employee. A value of "1" means Yes, managers can approve or contest the final appraisal on the employee's behalf. A value of "0" means No, employees access the appraisal system through Employee Self Service and approve or contest the appraisal themselves. |
| R89087711A   XJDE0002     | To populate F087711A Historic when upgrading from 8.11 or below.   | The Processing Option of this job sets the value for the new field MSEB in the table F087711A. | This TC populates the F087711A tag table with the MSEB value from the processing option value selected. | The tag table F087711A was added with the MSEB column to allow managers to sign off on the final performance appraisal on behalf of the employee. A value of "1" means Yes, managers can approve or contest the final appraisal on the employee's behalf. A value of "0" means No, employees access the appraisal system through Employee Self Service and approve or contest the appraisal themselves. |
| R890411B                  | To generate F76C4011 from F0411 when upgrading from 8.11 or below. |                                                                                                |                                                                                                         |                                                                                                                                                                                                                                                                                                                                                                                                         |

---

**Upgrading from 8.11 or Below**

| <b>Conversion Program</b> | <b>Run this Job</b>                                                                                                                                      | <b>Requirements</b>                             | <b>Purpose</b>                                                                                                                                                                | <b>Notes</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|---------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R8913907A                 | To convert F13907 SWO (Separate Work Order) field from 8.11 or below.                                                                                    | Run after the table conversions have completed. | Any data in the SWO field that used to be a Y will be changed to a 1. Any data in the SWO field that used to be an N will be changed to a 2.                                  | <p>Prior to 8.11 SP1, there was no editing for the Separate Work Order (SWO) field in the Associative Service Types (P13907) application. The existing application allowed entries of Y, N, 1, or 2, however the UDC attached to the SWO data dictionary only listed values of 1 and 2.</p> <p>To keep things simple, editing was turned on for the DD item so new entries into that fields would be validated against the UDC. Since clients could have existing data that used a Y or N, this post-install was created to correct that data.</p> |
| R8976V01                  | To generate F76C4015 from F0411 when upgrading from 8.11 and SAR 7668978 has not been previously applied. Do not run if upgrading from 8.10 or below.    | Requires use of Venezuela's localization.       | For each Credit\Debit Note in table F0411 related to a Voucher in table F0411, the TC generates a record into table F76V4015 to relate the Credit\Debit Note and the Voucher. |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
| R8976V02                  | To generate F76V4011 from F76V0401 when upgrading from 8.11 and SAR 7668978 has not been previously applied. Do not run if upgrading from 8.10 or below. | Requires use of Venezuela's localization.       | For each record in table F76V401, the TC generates a record into table F76V4011 to store the localized voucher information.                                                   |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
| R893016                   | To populate F3016T from F3016 when upgrading from 8.11 or below.                                                                                         | None.                                           | This TC creates a corresponding F3016T tag record for every existing F3016 record.                                                                                            |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |

**Upgrading from 8.11 or Below**

| <b>Conversion Program</b> | <b>Run this Job</b>                                                                    | <b>Requirements</b>                             | <b>Purpose</b>                                                                              | <b>Notes</b>                                                                                                                                                                                                                                                                                                                                           |
|---------------------------|----------------------------------------------------------------------------------------|-------------------------------------------------|---------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R893283F                  | To fix CTKID in F3283 when upgrading from 8.11 or below.                               | None.                                           | This TC cleans up the data in F3283 for the entire table.                                   | This report should fix all the records. If there are any problems, the records shall be listed on the report. These problematic records can be re-run using R893283L UBE, which uses data selection. Run the records that had issues. If problems persist, these records may need to be manually removed from the database and re-added.               |
| R893283L                  | To fix CTKID in select F3283 records when upgrading from 8.11 or below.                | R893283F                                        | This TC cleans up the data in F3283 for select records.                                     | Run this TC only if there were problematic records reported in R893283F.                                                                                                                                                                                                                                                                               |
| R893215F                  | To fix CFGSID in F32xx when upgrading from 8.11 or below.                              | None.                                           | This TC cleans up the data in F3215, F3211, F32119, F32159 and F41021 for the entire table. | This report should fix all the records. If there are any problems, the records shall be listed on the report. These problematic records can be re-run using R893215L UBE, which uses data selection. Run the records that had issues. If problems persist, these records may need to be manually removed from the database and re-added.               |
| R893215L                  | To fix CFGSID in select F32xx records when upgrading from 8.11 or below.               | R893215F                                        | This TC cleans up the data in F3215, F3211, F32119, F32159 and F41021 for select records.   | Run this TC only if there were problematic records reported in R893215F.                                                                                                                                                                                                                                                                               |
| R099102                   | To populate the new Debit Amounts AND01-14 in F0902 when upgrading from 8.11 or below. | Run after the table conversions have completed. | The Repost on menu G09316 updates the F0902 table with the Debit Amounts.                   | Debit fields AND01-14 that were formerly located in tag table F0902A were added to the F0902.<br><br>Many applications require data for total debits or total credits. Prior to the change, the data was obtained from the F0911, causing performance issues. With this change the data is retrieved from the F0902 resulting in improved performance. |

**Upgrading from 8.11 or Below**

| <b>Conversion Program</b> | <b>Run this Job</b>                                                       | <b>Requirements</b> | <b>Purpose</b>                                                                                                   | <b>Notes</b>                                                                                                                                                                                                                                                                                                                                                                                               |
|---------------------------|---------------------------------------------------------------------------|---------------------|------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R8900165JC   XJDE0001     | To convert media object data from GT0901 to ACCGT for Job Status Inquiry. | None.               | This conversion copies the data in F00165 for GT0901 to ACCGT so Job Status Inquiry can access the media object. | <p>Prior to 8.11 SP1, Job Status Inquiry was using the media object for GT0901 but all of the other job cost applications were using ACCGT. In order to make the media object data consistent across all of job cost, Job Status Inquiry was changed to use ACCGT instead of GT0901.</p> <p>You only need to run this conversion if you are using Job Status Inquiry with media object data in GT0901.</p> |

**13.6 Upgrading from 8.11 SP1 or Below**

This section contains a list of all the Table Conversions required when upgrading from 8.11 SP1 or below.

**Upgrading from 8.11 SP1 or Below**

| <b>Conversion Program</b> | <b>Run this Job</b>                                                            | <b>Requirements</b>                                                                                     | <b>Purpose</b>                                                                                                                 | <b>Notes</b>                                                                                                                                                                 |
|---------------------------|--------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R8908495                  | To convert GT08495 Media Object from 8.11 SP1 or below.                        | This is to be run after the F00165 table has been successfully upgraded in the automatic Upgrade Plan.  | N\A                                                                                                                            | This media object supported resumes and cover letters in the eRecruit module. Changes were made to allow the resume and cover letter to be searched with Verity text search. |
| R8908490I                 | To save Internal Applicant Address Info when upgrading from 8.11 SP1 or below. | None.                                                                                                   | N\A                                                                                                                            |                                                                                                                                                                              |
| R89069116A                | To convert F069116 from 8.11 SP1 or below.                                     | The processing option on this job prompts the user for a value to update the new field DEFR in F069116. | To update the new column DEFR in F069116. It is updated with a value of "1", "2", or "3" based on the processing option value. | This TC simply calls a BSFN (B8902023) that will do a mass update to DEFR based on the processing option value.                                                              |

**Upgrading from 8.11 SP1 or Below**

| <b>Conversion Program</b> | <b>Run this Job</b>                  | <b>Requirements</b>                                                                                                                                                                                                                                                                                                | <b>Purpose</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                                             | <b>Notes</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|---------------------------|--------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R8901301D                 | To convert Activities from 8.11 SP1. | <p>Prior to running this post upgrade UBE, all users of activity system should already have universal time (time zone) and daylight savings rule set in their user profiles.</p> <p>The processing option on this job prompts the user to enter the maximum number of occurrences for never ending activities.</p> | <p>To populate new and changed fields in F01301.</p> <p>To populate new field in F01331 and create new exclusion records for assignees.</p> <p>To write activity details in F01301D.</p> <p>For recurring activity with no end date: To update F01321 with a calculated end date based on the maximum number of occurrences specified in the Processing Option.</p> <p>To update F01321 with the combination of the originator's time zone and daylight saving rules (separated by  ).</p> | <p>F01301 (Activity Header): The owner parent record is assigned a new GUID for the group activity ID. All assignee's activity records are reassigned the same GUID as the parent owner. "All Day" events and tasks are now stored with time starting 00:00:00 and ending 23:59:59 local time of the originator's time zone from the user profile.</p> <p>F01331 (Exclusion): The existing exclusion record is updated with the Activity id of the Owner Master record. New exclusion records are created for the excluded assignee's series. The activity id updated for the new exclusion records is the activity id of the assignee's master record.</p> <p>F01321 (Recurrence Master): For recurring activities that have no end date, a finite end date is calculated based on the max number of occurrences specified in the UBE processing option. In addition, the combination of the activity's originator's time zone and daylight saving rule (fields separated by  ) is updated in URCH.</p> <p>F01301D (Activity Details): Physical activity records for every instance of a recurring activity rescind in the new activity detail table F01301D. Activity search applications are changed to search over this new table, which allows for faster and easier search capabilities.</p> |



**Upgrading from 8.11 SP1 or Below**

| <b>Conversion Program</b> | <b>Run this Job</b>                                                                                                                                                                                    | <b>Requirements</b> | <b>Purpose</b>                                                                                                                                                                                                                                                             | <b>Notes</b> |
|---------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------|
| R4801T1                   | To populate F4801T1 from F4801T when upgrading from 8.11 SP1 or below. Only customers that have data for ETO in F4801 need to run this TC. Do not run this TC if the ESU was applied prior to upgrade. | None.               | This post-install UBE will populate table F4801T1 with data from F4801T. If there are records in F4801T with PRJM (project number) field populated corresponding records would be created in F4801T1. The only field that gets populated from F4801T into F4801T1 is DOCO. |              |

**13.7 Upgrading from 8.12 or Below**

This section contains a list of all the Table Conversions required when upgrading from 8.12 or below.

**Upgrading from 8.12 or Below**

| <b>Conversion Program</b> | <b>Run this Job</b>                                                                    | <b>Requirements</b> | <b>Purpose</b>                                                                                                                                            | <b>Notes</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
|---------------------------|----------------------------------------------------------------------------------------|---------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R09E115                   | To update Expense Location UDC Codes when upgrading from 8.12 or below.                | None.               | To reformat the values in UDC 09E   EL.                                                                                                                   | The size of the UDC Code 09E   EL has been increased to 10 characters. This caused the values to be left padded with spaces to make up the difference in size. This UBE will remove that left padding.                                                                                                                                                                                                                                                                                                                                                  |
| R05041                    | To add data items to Future Data \ History Tracking when upgrading from 8.12 or below. | None.               | To create a record in F06041 and F08041 for each new data item added to the F060116. For records added, set respective flags in tables (ICDE, XCOD) = "N" | F06041 - Future Data Fields<br>F08041 - History Tracking Fields. These tables are pre-populated with records that the client may toggle to "on" or "off" for tracking history. In 90, 2 new fields were added, that will be shipped with the data set. For customers upgrading, from say 812 to 90, the ube would be run to add the two new records, but maintain the existing data set that the customer may have changed. This UBE should ensure that the client's preferences are not lost, while gaining the ability to modify the two new records. |

**Upgrading from 8.12 or Below**

| <b>Conversion Program</b> | <b>Run this Job</b>                                                    | <b>Requirements</b>                                                                                                                                                     | <b>Purpose</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             | <b>Notes</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
|---------------------------|------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R98305V                   | When upgrading from 8.12.                                              | None                                                                                                                                                                    | To convert all existing Web Only versions to full versions.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                | None                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
| R8915L101A                | To change GT15L101 Key when upgrading from 8.12 or below.              | This post-install UBE, must be run AFTER the R8915L101 TC has completed successfully.                                                                                   | The purpose of this Table Conversion is to enable customers to convert existing media objects in the F00165 that match the GT15L101 media object structure. Since the F15L101 table was changed to include UKID in the primary key, the resulting media objects attached to the unit master were also changed to match this key. As a result, a conversion was written to "re-key" those media objects to utilize the updated key structure. This conversion was required as a result of changes made to support inclusion of multiple leases (i.e. future leases and speculative leases). | <p>This conversion program does not need to be run unless the Media Objects Storage (F00165) table contains very specific data. If the ÖBNM field of any record contains GT15L101, the table conversion is necessary. Although it is not harmful to run the procedure anyway, you can determine if the table conversion is necessary by performing the following SQL statement (with the appropriate syntax, against the appropriate database).</p> <p>Select count (*) from F00165 where GDOBNM = 'GT15L101'</p> <p>If the returned count is greater than zero, the conversion program must be run. This count is the number of records that are candidates to be analyzed by this UBE.</p> |
| R89I100B                  | When upgrading from previous releases and running India Localizations. | Apply ESU for SAR 8868437 to add R89I100B to the menu. If the ESU has not been applied and the conversion needs to be run, you must do it manually from Batch Versions. | To combine the information from F75I100 and F75I101A into one table and add new fields for TDS Certificate functionality.                                                                                                                                                                                                                                                                                                                                                                                                                                                                  | This table was modified to save information that was in the F75I100 table and F75I101A table. Also, some new fields were added to this table. The conversion program copies the old F75I100 records, completes the new fields with blank or zero, and moves information from F75I101A to F75I100 record.                                                                                                                                                                                                                                                                                                                                                                                     |

**Upgrading from 8.12 or Below**

| <b>Conversion Program</b> | <b>Run this Job</b>                                                                                                          | <b>Requirements</b>                                                                                                                                                                                                                                                 | <b>Purpose</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                | <b>Notes</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
|---------------------------|------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R8940G00                  | To convert all Grower Area fields to the correct format based on the new display decimals when upgrading from 8.12 or below. | <p>Four processing Options exist for this conversion:</p> <p>1 - Data Item Class.</p> <p>2 - New Data Display Decimals.</p> <p>3 - Enter 1 to Update the Display Decimals in the Data Dictionary.</p> <p>4 - Enter 1 to convert the data and update the tables.</p> | <p>Display decimal changes in the Data Dictionary are not updated through the upgrade process. A new data class is created for the grower area fields (GROWERAREA). This post install UBE will update the display decimals (specified in the UBE processing options) for the new data class. The UBE will also convert the data to the correct format for the new display decimals for the following tables:</p> <p>F40G03 - Harvest Master</p> <p>F40G0300 - Update Harvest Profile</p> <p>F40G02 - Block Master</p> <p>F40G0200 - Update Block Profile</p> <p>F40G65 - Farming Operation Header</p> <p>F31B70 - Vessel Assignment Table</p> | <p>The following DB items were created with varying lengths and no display decimals. In 9.0, they are modified to have display decimals with a length of 4. The DD items are: PLTAREA, GRSAREA, TRTAREA, PAREA1, PAREA2, PAREA3.</p>                                                                                                                                                                                                                                         |
| R48S84A                   | When upgrading from 8.11 SP1 or 8.12 and you have existing Pool Grouping Code records in the F48S84 table.                   | Run this batch application after the F48S84 table has been converted.                                                                                                                                                                                               | This batch application will update the ending date if applicable on records in the Pool Grouping Code Table (F48S84).                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         | <p>An Ending Effective Date has been added to the F48S84 table. This job should be run to ensure there is no overlapping pool grouping code records. If there is a pool grouping code with different begin dates, the batch application R48S84A will update the ending date of the earlier record with an ending date one day prior to the begin date of the next record.</p> <p><i>Note:</i> This Post Install UBE is only needed when upgrading from 8.11 SP1 and 8.12</p> |

## 13.8 Upgrading from 9.0 or Below

This section contains a list of all the Table Conversions required when upgrading from 9.0 or below.

| Upgrading from 9.0 or Below |                                                                                                                                                                                                                                                      |                                                                                                                                                                 |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|-----------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Conversion Program          | Run this Job                                                                                                                                                                                                                                         | Requirements                                                                                                                                                    | Purpose                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                | Notes                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
| R43S001                     | When upgrading from 9.0 or below and ESU has not already been installed in prior release.                                                                                                                                                            | F43S001, UDC 43S   AL                                                                                                                                           | This TC will populate the F43S001 table with the list of supported alerts from the UDC 43S   AL.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       | If ESU was installed in From Release, then this conversion does not need to be run again.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
| R41B100                     | <p>To update data in tables that contain the VCF data item; it does not modify the table structure.</p> <p>It should be run in Final mode only once.</p> <p>It can be run in Proof mode multiple times. Proof mode does not perform any updates.</p> | Users should verify that this report has not already been run. It was required if the user took the ESU for SARs 8567415 (Xe), 8757032 (8.12) or 8820775 (9.0). | <p>This report converts the data in the Volume Correction Factor (VCF) field of the tables listed below from 4 decimals to 5 decimals.</p> <p>Tables containing VCF:</p> <p>F38111 - Agreements Transaction Ledger</p> <p>F41511 - Bulk Product Transaction File</p> <p>F41515 - Multi-Meter Readings</p> <p>F49211- Sales Order Detail File - Tag</p> <p>F49211Z1- Sales Order Detail Tag Unedited</p> <p>F49219- Sales Order Detail - Tag History</p> <p>F4963 - Load In-transit</p> <p>F49631- Load In-transit Ledger</p> <p>F49632 - Load In-transit Left on Board</p> <p>F49299 - S.O. Detail Tag Ledger File</p> | <p>The report should be run in Proof mode first. If the processing option to display the records is set to 1, the report will display all the records that will be updated and what the volume correction factor will be updated to. If the processing option is not set to display records, the total number of records in each table that will be updated is displayed.</p> <p>Run the report in Final mode only one time, regardless of the value of the processing option to display records. If the report is run in Final mode more than once, the data will be incorrect.</p> |

**Upgrading from 9.0 or Below**

| <b>Conversion Program</b> | <b>Run this Job</b>                                                                                                                                                                           | <b>Requirements</b>                                                                                                                                                                                                                                                                                         | <b>Purpose</b>                                                                                                                                                                                                                                                                                                                                                                                                  | <b>Notes</b>                                                                                                                                                                                                                                                                                                                                                                         |
|---------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R8940G34                  | To populate item and harvest pattern information that was previously stored in the Grower Block table (F40G02) into the Harvest Item Master (F40G034).                                        | This TC is dependent upon the *ALTER record being processed successfully for the Grower Block table (F40G02) and the Grower Harvest table (F40G03). The *ALTER conversions will convert the tables to the new 9.1 format. Then R8940G34 can be run to process the records and populate the F40G034 columns. | F40G034 table was added to support crop rotation functionality in which item is an attribute of the harvest rather than of the block.<br><br>A record is inserted into F40G034 for every Grower Harvest record (F40G03) for each Block record (F40G02). F40G034 will be populated with the Vessel ID from F40G03 and with Short Item Number, 2nd Item Number, 3rd Item Number, and Harvest Pattern from F40G02. | This TC is also being released in an ESU for 9.0. Users upgrading from release 9.0 to 9.1 that have taken the ESU will not be required to run the Post Install table conversion.<br><br>R8940G34 deletes existing records found in F40G034 before creating new records so it may be run more than once without errors.                                                               |
| R41806                    | To automatically mark all item and item branch records as country of origin required.                                                                                                         | None                                                                                                                                                                                                                                                                                                        | The TC should be run as a post install only if the Country of Origin functionality is desired after an upgrade to 9.1.                                                                                                                                                                                                                                                                                          | The user should set up data selection only for those items and branches for which they wish to activate the country of origin required functionality. Users will need to specify proof or final mode, and decide whether to activate the country of origin at the item master level. The user can also specify a default country of origin value to give to the item branch records. |
| R41807                    | After the country of origin required flag has been activated for the first time on an existing item branch you will use this TC to update all existing lots to the correct country of origin. | Should be run after the R41806.                                                                                                                                                                                                                                                                             | This TC is run once the required flag has been activated and if this is being run as part of the post install process it should be run after the R41806 is run.                                                                                                                                                                                                                                                 | User should restrict any lots that already have a country of origin from the data selection. There is a proof and final mode processing option, and there is a default value for the country of origin for the lot.                                                                                                                                                                  |
| R31B8505                  | This TC will update all data currently residing in the weigh tag master file which currently contains lot information to now contain lot and country of origin information.                   | Should be run after the R41806 and R41807.                                                                                                                                                                                                                                                                  | This TC should be run as a post install and only if the client utilizes the grower weigh tag functionality.                                                                                                                                                                                                                                                                                                     | There is a proof and final mode processing option, and there is a default value for the country of origin for the lot.                                                                                                                                                                                                                                                               |

**Upgrading from 9.0 or Below**

| <b>Conversion Program</b> | <b>Run this Job</b>                                                                                                                                               | <b>Requirements</b>                                                                                                                     | <b>Purpose</b>                                                                                                                                                                                           | <b>Notes</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
|---------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| R8976A08                  | This process copies current Country of Origin data at Item/Lot level used by Argentina Localization (field LRP9 of F4108) to the new ORIG field into table F4108. | The process has to be executed only when the customer is using Argentina Localization and selling Imported Items by Sales Order module. | This UBE has to be executed as a Post Install from any 9.1 prior releases to 9.1 or higher releases.                                                                                                     | <p>In case the country codes in UDC 41/L9 are not the same than UDC 00/CN, the user has to define the mapping between values using the special handling code of UDC 41/L9. That means special handling code of UDC 41/L9 should contains the corresponding country code of UDC 00/CN.</p> <p>Execute R8976A08 selecting the correct Lots from F4108 by user data selection.</p> <p>For a given record, the value into ORIG field of F4108 has to contain the same country than the value of LRP9 field.</p> |
| R95SQAQ                   | To convert old saved queries to new enhanced queries.                                                                                                             | This is to be run if you use Saved Query. To verify, please check if you have records in F98950 table with field UOTY = "SQ"            | Enhanced Query uses a different format than Saved Query to store the queries. This conversion program provides users a way to convert your old saved queries to the new format that Enhanced Query uses. | User can use the PO Template D95SQAQPO to specify any combination of 3 attributes (User ID and/or Application Name and/or Form Name) to filter the old queries to be converted to the new format. Records in F98950 and F98950D are converted during the process. The old SQ records are NOT deleted during the conversion.                                                                                                                                                                                 |

## 13.9 Processing Options for R31P40039

This table lists all the processing options required for the R31P40039 program.

**Processing Options for R31P40039**

|                                              |                                                                                                                                                                      |
|----------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Mode                                         | Blank = Final (can be rerun).<br>1 = Proof. Does not change anything in the database.                                                                                |
| <b>Manufacturing</b>                         |                                                                                                                                                                      |
| Order Type value 01 for Manufacturing Orders | The user-defined code that the user wants to replace Order Type value 01 in the manufacturing orders. If no value is entered, the default order type assigned is 01. |
| Order Type value 02 for Manufacturing Orders | The user-defined code that the user wants to replace Order Type value 02 in the manufacturing orders. If no value is entered, the default order type assigned is 01. |
| Order Type value 03 for Manufacturing Orders | The user-defined code that the user wants to replace Order Type value 03 in the manufacturing orders. If no value is entered, the default order type assigned is 01. |
| Order Type value 04 for Manufacturing Orders | The user-defined code that the user wants to replace Order Type value 04 in the manufacturing orders. If no value is entered, the default order type assigned is 01. |

**Processing Options for R31P40039**

|                                              |                                                                                                                                                                      |
|----------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 05 for Manufacturing Orders | The user-defined code that the user wants to replace Order Type value 05 in the manufacturing orders. If no value is entered, the default order type assigned is 01. |
|----------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------|

**Manufacturing Rework**

|                                                           |                                                                                                                                                                                   |
|-----------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 01 for Engineering Change Request Orders | The user-defined code that the user wants to replace Order Type value 01 in the engineering change request orders. If no value is entered, the default order type assigned is 01. |
|-----------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                                           |                                                                                                                                                                                   |
|-----------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 02 for Engineering Change Request Orders | The user-defined code that the user wants to replace Order Type value 02 in the engineering change request orders. If no value is entered, the default order type assigned is 01. |
|-----------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                                           |                                                                                                                                                                                   |
|-----------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 03 for Engineering Change Request Orders | The user-defined code that the user wants to replace Order Type value 03 in the engineering change request orders. If no value is entered, the default order type assigned is 01. |
|-----------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                                           |                                                                                                                                                                                   |
|-----------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 04 for Engineering Change Request Orders | The user-defined code that the user wants to replace Order Type value 04 in the engineering change request orders. If no value is entered, the default order type assigned is 01. |
|-----------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                                           |                                                                                                                                                                                   |
|-----------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 05 for Engineering Change Request Orders | The user-defined code that the user wants to replace Order Type value 05 in the engineering change request orders. If no value is entered, the default order type assigned is 01. |
|-----------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

**Equipment**

|                                          |                                                                                                                                                                  |
|------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 01 for Equipment Orders | The user-defined code that the user wants to replace Order Type value 01 in the equipment orders. If no value is entered, the default order type assigned is 01. |
|------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                          |                                                                                                                                                                  |
|------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 02 for Equipment Orders | The user-defined code that the user wants to replace Order Type value 02 in the equipment orders. If no value is entered, the default order type assigned is 01. |
|------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                          |                                                                                                                                                                  |
|------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 03 for Equipment Orders | The user-defined code that the user wants to replace Order Type value 03 in the equipment orders. If no value is entered, the default order type assigned is 01. |
|------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                          |                                                                                                                                                                  |
|------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 04 for Equipment Orders | The user-defined code that the user wants to replace Order Type value 04 in the equipment orders. If no value is entered, the default order type assigned is 01. |
|------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                          |                                                                                                                                                                  |
|------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 05 for Equipment Orders | The user-defined code that the user wants to replace Order Type value 05 in the equipment orders. If no value is entered, the default order type assigned is 01. |
|------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------|

**S\WM**

|                                        |                                                                                                                                                                |
|----------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 01 for Service Orders | The user-defined code that the user wants to replace Order Type value 01 in the service orders. If no value is entered, the default order type assigned is 01. |
|----------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                        |                                                                                                                                                                |
|----------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 02 for Service Orders | The user-defined code that the user wants to replace Order Type value 02 in the service orders. If no value is entered, the default order type assigned is 01. |
|----------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                        |                                                                                                                                                                |
|----------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 03 for Service Orders | The user-defined code that the user wants to replace Order Type value 03 in the service orders. If no value is entered, the default order type assigned is 01. |
|----------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                        |                                                                                                                                                                |
|----------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 04 for Service Orders | The user-defined code that the user wants to replace Order Type value 04 in the service orders. If no value is entered, the default order type assigned is 01. |
|----------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                        |                                                                                                                                                                |
|----------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 05 for Service Orders | The user-defined code that the user wants to replace Order Type value 05 in the service orders. If no value is entered, the default order type assigned is 01. |
|----------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------|

**Warranty Claim**

|                                                |                                                                                                                                                                       |
|------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 01 for Warranty Claim Orders. | The user-defined code that the user wants to replace Order Type value 01 in the warranty claim orders. If no value is entered, the default order type assigned is 01. |
|------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                                |                                                                                                                                                                       |
|------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 02 for Warranty Claim Orders. | The user-defined code that the user wants to replace Order Type value 02 in the warranty claim orders. If no value is entered, the default order type assigned is 01. |
|------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                                |                                                                                                                                                                       |
|------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 03 for Warranty Claim Orders. | The user-defined code that the user wants to replace Order Type value 03 in the warranty claim orders. If no value is entered, the default order type assigned is 01. |
|------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------|

**Processing Options for R31P40039**

|                                                |                                                                                                                                                                       |
|------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 04 for Warranty Claim Orders. | The user-defined code that the user wants to replace Order Type value 04 in the warranty claim orders. If no value is entered, the default order type assigned is 01. |
|------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                                |                                                                                                                                                                       |
|------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 05 for Warranty Claim Orders. | The user-defined code that the user wants to replace Order Type value 05 in the warranty claim orders. If no value is entered, the default order type assigned is 01. |
|------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------|

**Supplier Recovery**

|                                                  |                                                                                                                                                                          |
|--------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 01 for Supplier Recovery Orders | The user-defined code that the user wants to replace Order Type value 01 in the supplier recovery orders. If no value is entered, the default order type assigned is 01. |
|--------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                                  |                                                                                                                                                                          |
|--------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 02 for Supplier Recovery Orders | The user-defined code that the user wants to replace Order Type value 02 in the supplier recovery orders. If no value is entered, the default order type assigned is 01. |
|--------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                                  |                                                                                                                                                                          |
|--------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 03 for Supplier Recovery Orders | The user-defined code that the user wants to replace Order Type value 03 in the supplier recovery orders. If no value is entered, the default order type assigned is 01. |
|--------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                                  |                                                                                                                                                                          |
|--------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 04 for Supplier Recovery Orders | The user-defined code that the user wants to replace Order Type value 04 in the supplier recovery orders. If no value is entered, the default order type assigned is 01. |
|--------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                                  |                                                                                                                                                                          |
|--------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 05 for Supplier Recovery Orders | The user-defined code that the user wants to replace Order Type value 05 in the supplier recovery orders. If no value is entered, the default order type assigned is 01. |
|--------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

**ECO**

|                                                   |                                                                                                                                                                           |
|---------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 01 for Engineering Change Orders | The user-defined code that the user wants to replace Order Type value 01 in the engineering change orders. If no value is entered, the default order type assigned is 01. |
|---------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                                   |                                                                                                                                                                           |
|---------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 02 for Engineering Change Orders | The user-defined code that the user wants to replace Order Type value 02 in the engineering change orders. If no value is entered, the default order type assigned is 01. |
|---------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                                   |                                                                                                                                                                           |
|---------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 03 for Engineering Change Orders | The user-defined code that the user wants to replace Order Type value 03 in the engineering change orders. If no value is entered, the default order type assigned is 01. |
|---------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                                   |                                                                                                                                                                           |
|---------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 04 for Engineering Change Orders | The user-defined code that the user wants to replace Order Type value 04 in the engineering change orders. If no value is entered, the default order type assigned is 01. |
|---------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                                   |                                                                                                                                                                           |
|---------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 05 for Engineering Change Orders | The user-defined code that the user wants to replace Order Type value 05 in the engineering change orders. If no value is entered, the default order type assigned is 01. |
|---------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

**ECO Request**

|                                                           |                                                                                                                                                                                   |
|-----------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 01 for Engineering Change Request Orders | The user-defined code that the user wants to replace Order Type value 01 in the engineering change request orders. If no value is entered, the default order type assigned is 01. |
|-----------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                                           |                                                                                                                                                                                   |
|-----------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 02 for Engineering Change Request Orders | The user-defined code that the user wants to replace Order Type value 02 in the engineering change request orders. If no value is entered, the default order type assigned is 01. |
|-----------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                                           |                                                                                                                                                                                   |
|-----------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 03 for Engineering Change Request Orders | The user-defined code that the user wants to replace Order Type value 03 in the engineering change request orders. If no value is entered, the default order type assigned is 01. |
|-----------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                                           |                                                                                                                                                                                   |
|-----------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 04 for Engineering Change Request Orders | The user-defined code that the user wants to replace Order Type value 04 in the engineering change request orders. If no value is entered, the default order type assigned is 01. |
|-----------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                                           |                                                                                                                                                                                   |
|-----------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 05 for Engineering Change Request Orders | The user-defined code that the user wants to replace Order Type value 05 in the engineering change request orders. If no value is entered, the default order type assigned is 01. |
|-----------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|



---

**Processing Options for R31P40039**


---

**Real Estate Management**


---

|                                                       |                                                                                                                                                                               |
|-------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 01 for Real Estate Management Orders | The user-defined code that the user wants to replace Order Type value 01 in the real estate management orders. If no value is entered, the default order type assigned is 01. |
| Order Type value 02 for Real Estate Management Orders | The user-defined code that the user wants to replace Order Type value 02 in the real estate management orders. If no value is entered, the default order type assigned is 01. |
| Order Type value 03 for Real Estate Management Orders | The user-defined code that the user wants to replace Order Type value 03 in the real estate management orders. If no value is entered, the default order type assigned is 01. |
| Order Type value 04 for Real Estate Management Orders | The user-defined code that the user wants to replace Order Type value 04 in the real estate management orders. If no value is entered, the default order type assigned is 01. |
| Order Type value 05 for Real Estate Management Orders | The user-defined code that the user wants to replace Order Type value 05 in the real estate management orders. If no value is entered, the default order type assigned is 01. |

---

**Rate Schedules**


---

|                                              |                                                                                                                                                                      |
|----------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 01 for Rate Schedule Orders | The user-defined code that the user wants to replace Order Type value 01 in the rate schedule orders. If no value is entered, the default order type assigned is 01. |
| Order Type value 02 for Rate Schedule Orders | The user-defined code that the user wants to replace Order Type value 02 in the rate schedule orders. If no value is entered, the default order type assigned is 01. |
| Order Type value 03 for Rate Schedule Orders | The user-defined code that the user wants to replace Order Type value 03 in the rate schedule orders. If no value is entered, the default order type assigned is 01. |
| Order Type value 04 for Rate Schedule Orders | The user-defined code that the user wants to replace Order Type value 04 in the rate schedule orders. If no value is entered, the default order type assigned is 01. |
| Order Type value 05 for Rate Schedule Orders | The user-defined code that the user wants to replace Order Type value 05 in the rate schedule orders. If no value is entered, the default order type assigned is 01. |

---

**EPM Order Summary**


---

|                                            |                                                                                                                                                                    |
|--------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Order Type value 01 for EPM Summary Orders | The user-defined code that the user wants to replace Order Type value 01 in the EPM summary orders. If no value is entered, the default order type assigned is 01. |
| Order Type value 02 for EPM Summary Orders | The user-defined code that the user wants to replace Order Type value 02 in the EPM summary orders. If no value is entered, the default order type assigned is 01. |
| Order Type value 03 for EPM Summary Orders | The user-defined code that the user wants to replace Order Type value 03 in the EPM summary orders. If no value is entered, the default order type assigned is 01. |
| Order Type value 04 for EPM Summary Orders | The user-defined code that the user wants to replace Order Type value 04 in the EPM summary orders. If no value is entered, the default order type assigned is 01. |
| Order Type value 05 for EPM Summary Orders | The user-defined code that the user wants to replace Order Type value 05 in the EPM summary orders. If no value is entered, the default order type assigned is 01. |

---

## 13.10 Upgrading E1PAGE from Release 9.0 to Release 9.1

This section describes these tasks to upgrade E1PAGE from Release 9.0 to Release 9.1:

- [Section 13.10.1, "Upgrading E1PAGE Using R98E1UGC"](#)
- [Section 13.10.2, "Upgrading F952400 Objects Using P98E1UGC"](#)
- [Section 13.10.3, "Working With Upgrade UGC Objects Using W98E1UGCA"](#)
- [Section 13.10.4, "Working With Detail Upgrade Using W98E1UGCB"](#)

### 13.10.1 Upgrading E1PAGE Using R98E1UGC

To upgrade your E1PAGE, you should execute the R98E1UGC post upgrade. This function of this UBE is to move data from previous release to the upgraded release for F952400 table. The list of affected tables affected includes:

- F952411  
This is the history table for the record moved.
- F982400  
This table tracks the record as LCM process.
- F982402 and F982405  
These tables track the upgrade process.

This section describes these tasks:

- [Section 13.10.1.1, "Processing Options"](#)
- [Section 13.10.1.2, "Logic Flow"](#)

#### 13.10.1.1 Processing Options

Below is a list of the required processing options and an example of each:

- **From Environment**  
For example, DV900.
- **From Release**  
For example: E900.
- **To Environment**  
For example, DV910.
- **To Release**  
For example, E910.
- **Object Type**  
For example, E1PAGE.

Below is a list of the optional processing options and an example of each:

- **Job Number**  
For example, the default value is.  
UP:USER\_ID,Date and time (UP:USERDATETIME)
- **Report View Mode**

Valid values are:

- 1 - View Only Errors
- 0 - View All Records

- **Update Mode**

Valid values are:

- 1 - Proof Mode (Edit Mode for E1PAGE)
- 0 - Final Mode (APPROVE mode)

### 13.10.1.2 Logic Flow

Below lists the logic flow for each section of the processing for R98E1UGC.

- **Processing Section 1**

The logic flow of Processing Section 1 is based on Path Code Master table (F00942) with these considerations:

- If \*ALL is set for all environment in the processing option, the UBE processes all environments but only executes one path code. The F952400 table is a Central Objects table and should only be mapped by path code.
- If a specific environment is used, the UBE can determine the path code.
- The B98E1UGC business function processes all records in F952400 for the specified path code.

If the target environment F952400 table exists with JDE E1PAGE objects, the BSFN will not overwrite those records from those that exist in the source F952400 table. Therefore, any JDE delivered E1PAGE objects in a previous release are not carried over.

The BSFN creates records in the F952411, F982403, and F982400 tables. In the F982402 table, the header information for the Job Number maps back to the upgrade records in F982403 table.

- **Processing Section 2**

This processing section is based on F982403 table. It reports any records that fail to update.

## 13.10.2 Upgrading F952400 Objects Using P98E1UGC

You can use P98E1UGC to upgrade F952400 objects. Using this program allows users to:

- View records that have been successfully upgraded correctly and also to view any records that have issues.
- View any errors and their suspected reasons.
- Redo the upgrade after the UGC an identified issue has been fixed.

## 13.10.3 Working With Upgrade UGC Objects Using W98E1UGCA

You can use W98E1UGCA to view the header information for the UGC by Job Number.

### **13.10.4 Working With Detail Upgrade Using W98E1UGCB**

You can use W98E1UGCB to work with detail upgrades. Using this program allows users to:

- View all the records that have been upgraded.
- View additional detail on the errors.
- After any errors on the objects are fixed, the user can select Upgrade from this form. This allows the upgrade process to execute without re-running the R98E1UGC.

---

## Building and Testing Packages

This section discusses:

- [Section 14.1, "Understanding Packages"](#)
- [Section 14.2, "Obtaining the JDK\JRE"](#)
- [Section 14.3, "Installing Application Fixes"](#)
- [Section 14.4, "Reviewing Pre-Package Build Issues"](#)
- [Section 14.5, "Reviewing Troubleshooting Tips"](#)
- [Section 14.6, "Building an Alternate Language Package"](#)
- [Section 14.7, "Assembling a Package that Contains Published Business Services"](#)

### 14.1 Understanding Packages

Building and testing packages provides a method to create a package, to define and build a package, to deploy packages to both servers and workstations, and to troubleshoot the packages. These features use a step-by-step director process and include package assembly, package build, and package deployment.

Package build is used to set up a workstation or server with Release 9.1 software. Examples scenarios include:

- Setting up a new workstation.
- Deploying custom solutions to all or to selected users.
- Creating a new pathcode for development.
- Deploying a fix.
- Changing the package from a full to a partial package on some workstations.

There are options to define three different package types, to build and define packages with custom solutions, and to distribute them through two different deployment options. These options are available to a single server, to a workstation or user, or to selected machines, groups, or individual users. These options can be delivered using just-in-time or scheduled installation methods.

You must define, build, and deploy a custom package in order to include any modifications (changed or added business functions or applications) into a package for deployment to workstations (for example, DV910FA or DV910PA).

The system administrator is required to build and test packages at the server level. An installer may complete the process for the workstations. These processes can take several hours, depending on the scope of your business. The procedures take place on

the Deployment Server in the deployment environment as user JDE. Release 9.1 installation must be completed on the Enterprise Server before building and testing packages. The time required to build packages to the workstation varies depending on the database being used.

The package build and assembly process includes many critical tasks that must be successfully completed to install the packages correctly. This section includes a list of known issues associated with the package build, assembly, and deployment process and gives instructions for avoiding them. Before building a package, review these instructions to successfully complete this process.

#### **See Also**

*Package Build* in the *JD Edwards EnterpriseOne Tools Package Management Guide* for information about how to build and deploy packages.

*JD Edwards EnterpriseOne Tools Development Standards for Business Function Programming Guide* for information on how to convert business functions to support Unicode text strings.

## **14.2 Obtaining the JDK\JRE**

You must have a specific JDK\JRE on the Deployment Server in order to build packages. You can obtain the requisite JDK\JRE from Sun.

*See Also*

For the supported version of the JDK\JRE, refer to [Accessing Minimum Technical Requirements \(Certifications\)](#) in *Understanding JD Edwards EnterpriseOne* of this guide.

## **14.3 Installing Application Fixes**

Before you build packages, you should install all application fixes relevant to your business. Application fixes include maintenance packs, ESU bundles, and individual fixes. You should use Change Assistant to find relevant application fixes for system codes associated with the functionality you are using.

Change Assistant is a java-based tool that centralizes and economizes the process of searching, identifying, downloading, and deploying many types of software fixes such as ESUs and Tools Releases. It is available free of charge for maintenance paying customers, and can be downloaded from the Update Center.

Tests conducted in the Oracle labs on EnterpriseOne have shown that the use of this tool results in a significant reduction in elapsed time as well as a considerable reduction in manual steps - when compared to current search, download, and deploy processes.

For instructions on using Change Assistant, refer to *Using the Change Assistant* in the *JD Edwards EnterpriseOne Software Update Guide*.

## **14.4 Reviewing Pre-Package Build Issues**

Check the following items before building packages in order to minimize errors during package builds. Perform each of the relevant tasks on the machine where the package will be built.

This section discusses:

- [Section 14.4.1, "Verifying Available Space in DBMS"](#)

- [Section 14.4.2, "Verifying Specific UBEs are Mapped Locally"](#)
- [Section 14.4.3, "Verifying the Server-Side Settings"](#)
- [Section 14.4.4, "Configuring the Enterprise Server for Simultaneous Builds"](#)
- [Section 14.4.5, "Adding a Security Override for Running Package Build"](#)
- [Section 14.4.6, "Verifying UNICODE Settings When Upgrading From Xe"](#)

### 14.4.1 Verifying Available Space in DBMS

Package Deployment will copy the Central Objects tables in your server database to a new set of Metadata Specifications tables in the same database.

Verify there is enough free disk space for this extra copy.

Note the space used by your Central Objects tables and their indexes. The new set of Metadata Specifications tables will use additional space approximately the same size (for a full package) as your current Central Objects tables plus indexes. Those tables are:

- F98306
- F98710
- F98711
- F98712
- F98713
- F98720
- F98740
- F98741
- F98743
- F98745
- F98750
- F98751
- F98752
- F98753
- F98760
- F98761
- F98762

If you do not have enough free space to accommodate these tables, you must free up some disk space or drop the metadata specifications tables for old packages no longer in use.

### 14.4.2 Verifying Specific UBEs are Mapped Locally

To verify that specific UBEs are mapped locally:

1. Open the Object Configuration Manager (OCM).
2. Find each of the following UBEs and make sure each is mapped locally and is active: R9621, R9622, R98825C, and R98825D.

### 14.4.3 Verifying the Server-Side Settings

To verify the `jde.ini` settings on the Enterprise Server:

1. Open the `jde.ini` on the Enterprise Server.
2. Verify that the `BuildArea` setting in the `[BSFN BUILD]` section points to the `PACKAGES` directory on the Enterprise Server.

Verify that the following `LinkFlags` settings are correct:

- Ensure that the path to the `system\bin32` directory on the Enterprise Server is valid.
- Ensure that `LinkFlags` references the path where Release 9.1 is installed.

### 14.4.4 Configuring the Enterprise Server for Simultaneous Builds

To ensure that simultaneous builds run properly on your Enterprise Server.

1. Open the `jde.ini` on the Enterprise Server.
2. In the `[BSFN BUILD]` section, change the `SimultaneousBuilds` setting to 5 or less (the default is zero, which enables unlimited builds)

### 14.4.5 Adding a Security Override for Running Package Build

If you have secured your EnterpriseOne libraries, the user running package build must sign on as a user who has rights to create tables in the Central Objects library. If you have Security Server turned on, set up a security override for the EnterpriseOne user so that when they connect to the data source, they connect as a system user (IBM i user profile) who has update rights to the library.

Adding a security override must be done by a security administrator. To add a security override, you must first add a system user for the user profile which has update rights to the library (for example, the library owner), and then add an override for the EnterpriseOne user who will run the package build.

Refer to the *Package Management Guide* for further details on setting up security overrides for package build.

### 14.4.6 Verifying UNICODE Settings When Upgrading From Xe

If you are upgrading from Xe and you have modified any applications or UBEs with NERs and which are language-enabled, you must ensure this setting is in your `jde.ini` of the build machine on which you build the NERs, and also on the Deployment Server on which you are running the upgrade processes:

```
[INSTALL]
Unicode Conversion Codepage=code_page_value
```

where `code_page_value` is a valid value for the code page of the language-enabled application with NERs. For example, for Korean language the value would be:

```
[INSTALL]
Unicode Conversion Codepage=ksc-5601
```



---

**Note:** If you are a language customer but have never added NER to your applications, then you are not required to have this setting.

Also note that the `LocalCodeSet=` value is no longer used in releases subsequent to Xe.

---

## 14.5 Reviewing Troubleshooting Tips

The following troubleshooting tips are designed to help avoid known issues with the package build, assembly, and deployment process. Review these tips when working through the process.

- When naming your packages, do *not* use these names:
  - CLIENT
  - SERVER
- Verify the assemble and build processes completed.  
After entering the package information on both the Assembly and Build forms, click the End icon to save the information.
- Verify setting on the package definition screen.  
When selecting servers on the Build Definition form, ensure that a check mark appears next to each server selected. If no check mark appears, highlight the server in the grid and click Select.
- Recompress the parent packages.  
After building an update package that updates the parent package, you must recompress the parent package. This step does not occur automatically.
- Verify the location of server packages.  
When building an update server package, the specified parent package must be stored under the package directory on the server. If the parent package is not under the package directory, the update package does not build.

## 14.6 Building an Alternate Language Package

A package represents a copy of the central objects at a point in time. It contains replicated objects that Release 9.1 reads at run-time. If custom modifications or text overrides have been made at the time that a software upgrade is performed or to deploy development changes, including a specific language, to a local workstation, build a package and specify which language or languages to include in that package. This action involves the following considerations:

- [Section 14.6.1, "Package Build Considerations"](#)
- [Section 14.6.2, "Package Deployment Considerations"](#)

### 14.6.1 Package Build Considerations

Before beginning to build a language package, verify that the language installation is complete. To build the language package, first define the package. Building the package can take several hours, depending on the size of the package and the number of languages used. This task is completed on the Deployment Server, logged on as user JDE in DEP910.

To include language specifications in your package, specify the language in the package definition. The package build process then uses the language preference code. This code is specified as a parameter when building the package. It uses the relational database tables to build the form design aid text and report design aid text specifications. A language package can be a full, update, or partial package.

---

**Caution:** When building the client package with translated processing option text, run the build using Microsoft Windows with the system locale set to the appropriate language. If the system locale on the operating system does not match the installed language, the translated text in processing options (POTEXT) will be corrupted.

---

Building server packages that include languages other than English requires that the LocalCodeSet value of the Release 9.1 client matches the LocalCodeSet value of the `jde.ini` on the Enterprise Server. If the LocalCodeSet value on the local client differs from the one specified on the Enterprise Server, the server package build fails and errors are logged in the `jde.log` on the Enterprise Server.

## 14.6.2 Package Deployment Considerations

A translated package cannot be deployed to a workstation if the appropriate character set is not installed on that workstation. For example, if creating a package containing Japanese text, the workstation must be loaded with Japanese Microsoft Windows to view the Japanese data correctly.

---

**Caution:** To transfer translated objects to a server, complete the server package installation procedures. Define each object you have modified for languages. Therefore, track the objects you changed to include them in a package.

---

---

**Note:** To move all objects, call Global Customer Support for assistance.

---


*See Also*

*JD Edwards EnterpriseOne Tools Package Management Guide* for more information about transferring objects to the server.

## 14.7 Assembling a Package that Contains Published Business Services

To assemble a Business Services package:

1. Navigate to the processing options for Package Assembly from the Package and Deployment Tools menu by right-clicking the Package Assembly application (P9601), and selecting prompt for values.



2. Set the processing option entitled Business Services to a value of 1.

---

**Note:** This processing option is blank by default.

---

3. Click OK.

*See Also*

- To begin the assembly process, refer to the chapter entitled *Assembling Packages* in the JD Edwards EnterpriseOne *Package Management Guide*.
- *Building a Package with Published Business Services* in the JD Edwards EnterpriseOne *Package Management Guide*.
- *Deploying the Package to the Business Services Server* in the JD Edwards EnterpriseOne *Package Management Guide*.



---

## Upgrading the Production Environment

---

This chapter discusses:

- [Section 15.1, "Understanding the Upgrade of the Production Environment"](#)
- [Section 15.2, "General Checklist and Considerations"](#)
- [Section 15.3, "Running the Copy Environment Application \(P989400\)"](#)
- [Section 15.4, "Setting Up an Upgrade Plan for the Production Environment"](#)
- [Section 15.5, "Taking the Production Environment Offline"](#)
- [Section 15.6, "Running the Installation Plan for the Production Environment"](#)
- [Section 15.7, "Testing the Production Package"](#)
- [Section 15.8, "Bringing the Production Environment Online"](#)

### 15.1 Understanding the Upgrade of the Production Environment

Use this procedure after all testing has been successfully completed. This procedure brings your live production environment from the previous release to the newly upgraded release, which in this document is Release 9.1.

In a normal upgrade, there is an upgrade environment, such as development or CRP\PY, and then there is the live environment such as production. During the first phase of an upgrade, all modifications and customizations that are to be kept for the new release are transferred into the upgrade environment. The upgrade then converts the central objects with the table conversions and specification merge, business data table conversions, and control table merges. Once this upgrade is successfully tested, the production environment is ready to be brought up.

The new production environment borrows the already successfully merged central objects containing all your mods and customizations, and can borrow the successfully merged control tables as well. This leaves the business data table conversions as the only merge or conversion that needs to be run in order for Production to be successfully prepared. However, if you decide not to copy the control tables from the PY to the PD, then you will have to rerun the control table merge.

---

**Note:** You cannot use the procedures in this section if you need to bring any additional object specification changes. This is a distinguishing factor between a complete system upgrade and an update to the production environment upgrade.

---

For Release 9.1 on the Deployment Server, Security Server should be turned off during the workbench. There may be security issues if you are using Signon Security during the workbench. There may be password issues when there is not a database sign in as JDE with password JDE.

During both the Upgrade and the Update of the production environment, the workbench begins with the Initial Tasks. The initial tasks runs four reports explained below. However, since these reports have been previously run during the initial upgrade, the Batch Application will run, but do not copy over any data by default. Alternatives to the way these run by default are discussed below the Batch explanations.

Normally after you have upgraded all other environments, you upgrade the live production environment. This chapter explains how to upgrade the production environment with a minimum amount of production downtime.

Before proceeding:

- Apply Planner Update to PS910 and PY910
- Build and deploy full server package to PS910 and PY910
- Test all custom modifications in PY910

During the first phase of an upgrade, all modifications and customizations are transferred into the upgrade environment. The upgrade then converts the central objects with the table conversions and specification merge, business data table conversions, and control table merges. Once the upgrade is successfully tested, the production environment is ready to be brought up. The new production environment will borrow the already successfully merged Central Objects containing all your modifications and customizations, and can borrow the successfully merged Control Tables as well.

The Production Upgrade only converts business data. All shared data, system data, control tables, etc. needs to be converted. Objects and version are copied from the PY910 environment. Then, the Business Data Table conversions is the only merge or conversion that needs to be run in order for Production to be successfully prepared. However, if you opt not to copy the Control Tables from the PY to the PD, then you will have to run the Control Table Merge again.

You cannot use the Updating the Production Environment section if you need to bring any additional object specification changes. This is a distinguishing factor between an upgrade and an update of the production environment.

## 15.2 General Checklist and Considerations

You should review this section prior to beginning an upgrade to the production environment.

- Copying Central Objects, Object Librarian, Packages, ESU history

You will use the Environment Copy application on menu GH9611 to copy the above. Refer to [Section 15.3, "Running the Copy Environment Application \(P989400\)"](#) /

- Signon security

You should turn off the Security Server when you are running the Installation Workbench. Otherwise, security issues may occur while the Installation Workbench is running. If you have changed the password for JDE in your Enterprise Server database on your IBM i you should sign into the Deployment

Server using the correct password for the Enterprise Server. For example, JDE APPLES JDEPLAN. You should add any passwords that have changed since the initial install and which might be used during the upgrade process to the JDE.INI on the Deployment Server in the [DSPWD] section. For example:

```
[DSPWD]
JDE=APPLES
PRODDTA=SNOOPY
```

- Initial Tasks Workbench

Most of the processes in the Initial Tasks Workbench will be marked as Duplicates and will not run again. The Release Master (B9800400) runs every time. If you are upgrading from Xe or ERP8, you will need to run the Media Objects conversion for your business data. You should edit the Upgrade plan to change the status of R8900165 to 30. When the workbench runs, it presents a confirmation window telling you this conversion has already run. You should click Cancel to force the process to run the conversion.

- Control Table Merge

If you copied the Control Tables in the Environment Copy application, in that application you should modify the Advanced options for your environment to uncheck the Control Table Merges. If you already finalized the plan, you will need to re-finalize the plan for this change to take effect. Alternatively you can mark all the Control Table Merges as having run by changing their status to 60.

The Upgrade plan will schedule the Table Conversions for your production data.

- Specifications Merge

By default the Installation Planner will not schedule a Specifications Merge for your PD Upgrade plan. If you are upgrading any other environment, and have copied your Central Objects during Environment Copy, you should set the status of the Specifications Merge to 60 before running the Workbench.

- Log all JD Edwards EnterpriseOne users off

Ensure that all JD Edwards EnterpriseOne users are logged off when running the Installation Workbench for the production upgrade.

## 15.3 Running the Copy Environment Application (P989400)

---

**Caution:** If the target path code directory already exists on the Deployment Server or Enterprise Server (for example, from a previous attempt to copy to that path code), you must remove it before you start the copy process. This is necessary because the copy process breaks if another process has a lock on anything within that directory.

---

You can use this command:

where you should substitute your target path code directory.

For an IBM i Enterprise Server, ensure that you delete the target path code and package libraries that may have been created from a already exist from a previous attempt to copy that path code.

You must run the Copy Environment process on the Deployment Server.


1. From menu GH9611, run the application Environment Copy (P989400).



---

**Note:** For information on Processing Options for this application, refer to Step 3 of this procedure.

---



---

**Note:** If you have environment definitions, data source definitions, or path code definitions that exist in your System - 910 data source, but which are not defined on the Deployment Server which you will be using in this process, you can check the radio button for **Copy Environment Definitions** to copy the missing records from System - 910 to Planner - 910.

---

2. On P989400 - Copy Environment / Packages, click Next.



3. On Environment Copy [Copy to existing environment], complete these fields:

- Source Environment
- Target Environment
- Source Package
- Target Package

---

**Note:** Any environment copy is dependent on the OCM for the target environment. If the OCM does not currently exist, you can enable the checkbox for **Generate OCM in System / Server Map** to create data sources and OCM for your target environment before doing the copies.


---

---

**Note:** The **Copy Metadata Repository** and **Rename Metadata Repository** options are dependent on certain components having been copied before they are run:

- The package definition records for the target package must exist before the **Copy Metadata Repository** or **Rename Metadata Repository** runs. It is recommended that you allow the Copy Environment process to copy the path code and package on the Deployment Server, because that UBE (which runs before the **Copy Metadata Repository** or **Rename Metadata Repository**) also copies the package records and the package.inf.
  - The **Configure Package Manifest** option (which is only selectable by running the following step in this procedure) is dependent on both local and enterprise package repositories having been created, and also depends on the target package definition records.
  - The **Rename Metadata Repository** option assumes that you have used system or database utilities to copy all the tables in Central Objects to the new database / owner / library.
- 

4. You can override the default copy flags by clicking on the Advanced Copy form exit which displays this screen:



5. On Advanced Options Environment / Path Codes, if you want to override the default flags, click the **Override copy options** button.


You are returned to the preceding screen where all the default copy options are unprotected, allowing you to pick and choose which components the process will copy. This non-default method is only recommended if you have provided for the copies in a non-standard way. For example, if you used SAVLIB / RSTLIB in order to make your own copies of Central Objects.

6. After you have set the Environment Copy options as described in Step 3, click Next.

If the data source definitions and OCM for the target environment do not exist, the application generates data source definitions for Business Data, Control Tables, Central Objects and Versions for the target environment. It assumes that the data will be on the same server as the corresponding data sources for the source environment, but you can change this on the Data Source Revisions screens. Below is a sample screen for Business Data:

The screenshot shows the 'Data Source Revisions' dialog box. The title bar reads 'Data Source Revisions'. The interface includes a toolbar with icons for OK, Cancel, Dismiss, and Help, along with a 'Links' dropdown menu showing 'Advan...', 'OLE ...', and 'Internet'. The main area contains several labeled fields: 'Data Source Name' (Business Data - VO), 'Data Source Use' (DB), 'Data Source Type' (O), 'Data Class' (B), 'Platform' (LOCAL), and 'Database Server Name' (LOCAL). To the right of these fields are labels: 'Local Data Source', 'ORACLE', 'JDBNET Data Source?' (with an unchecked checkbox), 'Local Client', and 'Local'. Below these fields is a tabbed interface with tabs for 'SQL/86E/MSDE ODBC', 'SQL/MSDE OLEDB', 'Oracle' (selected), 'DB2 OS/400', 'DB2 UDB', 'Access', 'Logical', and 'Local Or'. At the bottom, there are two more input fields: 'Object Owner ID' and 'Database Name (TNS)'. The bottom right corner of the dialog has a small icon.

7. Following the series of Data Source Revisions screens, the next screen Copy Environments - [ Machines].



This screen shows a list of enterprise servers that allows you to select to which enterprise servers you want to copy the package / path codes.

8. On Copy Environments - [ Machines], highlight the desired machine from the node that lists **Available Enterprise Servers** and click the **Right Arrow** icon to add the machine to the node that lists **Selected Enterprise Servers**.

---

**Caution:** You must select at least one Enterprise Server before clicking **Next**; the P98400 application will not allow you to proceed until a machine is selected. To do so, click on an Enterprise Server located in the left field of the **Filter Available Enterprise Servers** section below the field **Port Number**, and then click the **Right Arrow** icon to move it to the right field under the node **Selected Enterprise Servers**.


---

---

**Note:** The process submits a UBE to each selected server. The source path code and package must exist on the selected servers.

---

9. Click Next.



This screen shows lists all the planned function of the processes of running the business functions and UBEs when you click the End button. All UBEs run locally except for the Enterprise Server Path Code copy, which is submitted to the Enterprise Server.

If you selected **Generate OCM**, a business function runs that generates data sources and OCM in Planner - 910 and copies them up to System - 910. This business function uses the template data source records in F98511, which can be viewed or revised using the Data Source Templates By Environment application on GH9611. The data source template records for the standard environments (DV910, PD910, PS910, PY910) are shipped with the Deployment Server install.

This table lists details of the UBEs that generate the Path Code Data:

| Path Code Data                           | UBE Details                                                                                                                                                                                                                                 |
|------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Control Tables                           | If selected, runs R98403 XJDE0022.                                                                                                                                                                                                          |
| Central Objects and Versions             | Runs R98403 XJDE0019.                                                                                                                                                                                                                       |
| Deployment Server Directory              | Runs R9800942.<br>This UBE also copies the Package Header / Detail records.                                                                                                                                                                 |
| Checkout Records                         | Runs R989861 XJDE0001.                                                                                                                                                                                                                      |
| ESU History                              | Runs R9672 XJDE0001.                                                                                                                                                                                                                        |
| Path Code Directory on Enterprise Server | Submits R9894003 XJDE0001 to the server.                                                                                                                                                                                                    |
| Copy Metadata Repository                 | Runs R9894005 XJDE0001 to copy the metadata repository within Central Objects.<br><br>The local repository is renamed by R9894005 XJDE0002, as the local package directory was copied by R9800942.                                          |
| Configure Manifest                       | Runs in UBE R9894005 XJDE0002 to configure the manifest (F98770PD910FA) in Central Objects and in the target package on the Deployment Server.<br><br>This UBE also configures the spec.ini in the target package on the Deployment Server. |

The application writes history records into F984052. To view the history, run the Table Conversion / Merge Log (P984052) on menu GH9611 by filtering on conversion type 95. This screen shows a sample conversion log:

The screenshot shows the 'Table Conversion/Merge Log' application window. It has a menu bar (File, Edit, Preferences, Row, Window, Help) and a toolbar with icons for Find, Del, Close, Seg, New, Dis, and Ato. Below the toolbar are filters for 'From' and 'To' with fields for Start Date, Start Time, and Start Date B. The main area displays a table of conversion records.

| Plan Name       | Target Environ | Prev Environ | Cnv Type | Object Name | Cnv Sts | Conversion Status       | Start Date | Beg Time | Compl Date | End Time | Program Name |
|-----------------|----------------|--------------|----------|-------------|---------|-------------------------|------------|----------|------------|----------|--------------|
| CPYENV_ES900CLM | ES900CLM       | XX900CLM     | 95       | F0101       | 2       | Conversion Finished Nor | 3/10/2008  | 10:48:14 | 3/10/2008  | 10:52:11 | R98403       |
| CPYENV_ES900CLM | ES900CLM       | XX900CLM     | 95       | F0005       | 2       | Conversion Finished Nor | 3/10/2008  | 10:52:11 | 3/10/2008  | 10:52:44 | R98403       |
| CPYENV_ES900CLM | ES900CLM       | XX900CLM     | 95       | F98741      | 2       | Conversion Finished Nor | 3/10/2008  | 10:52:44 | 3/10/2008  | 10:54:30 | R98403       |
| CPYENV_ES900CLM | ES900CLM       | XX900CLM     | 95       | RNMLCLPKG   | 2       | Conversion Finished Nor | 3/14/2008  | 10:59:59 | 3/14/2008  | 11:02:34 | R9894005     |
| CPYENV_ES900CLM | ES900CLM       | XX900CLM     | 95       | F9861       | 2       | Conversion Finished Nor | 3/14/2008  | 11:02:34 | 3/14/2008  | 11:03:38 | R989861      |
| CPYENV_ES900CLM | ES900CLM       | XX900CLM     | 95       | F9861       | 2       | Conversion Finished Nor | 3/14/2008  | 11:03:38 | 3/14/2008  | 11:41:00 | R989450      |
| CPYENV_ES900CLM | ES900CLM       | XX900CLM     | 95       | F986101     | 2       | Conversion Finished Nor | 3/14/2008  | 11:41:00 | 3/14/2008  | 11:41:06 | R9890953     |
| CPYENV_ES900CLM | ES900CLM       | XX900CLM     | 95       | SRVRDIR     | 2       | Conversion Finished Nor | 3/14/2008  | 11:41:10 | 3/14/2008  | 11:41:06 | R9894003     |
| CPYENV_ES900CLM | ES900CLM       | XX900CLM     | 95       | PATHDIR     | 2       | Conversion Finished Nor | 3/14/2008  | 12:33:31 | 3/14/2008  | 12:41:17 | R9800942     |
| CPYENV_ES900CLM | ES900CLM       | XX900CLM     | 95       | SVRMETADAT  | 2       | Conversion Finished Nor | 3/14/2008  | 12:41:18 | 3/14/2008  | 12:42:23 | R9894005     |
| CPYENV_ES900CLM | ES900CLM       | XX900CLM     | 95       | RNMLCLPKG   | 2       | Conversion Finished Nor | 3/14/2008  | 12:42:23 | 3/14/2008  | 12:45:01 | R9894005     |
| CPYENV_ES900CLM | ES900CLM       | XX900CLM     | 95       | F9861       | 2       | Conversion Finished Nor | 3/14/2008  | 12:45:01 | 3/14/2008  | 12:55:42 | R989450      |
| CPYENV_ES900CLM | ES900CLM       | XX900CLM     | 95       | F986101     | 2       | Conversion Finished Nor | 3/14/2008  | 12:55:42 | 3/14/2008  | 12:55:52 | R9890953     |
| CPYENV_ES900CLM | ES900CLM       | XX900CLM     | 95       | F98611      | 2       | Conversion Finished Nor | 3/14/2008  | 12:55:52 | 3/14/2008  | 12:55:53 | R9894002     |

Row 5

10. After the process completes successfully, you must deploy the target server package to make it available on the Enterprise Server(s).

---

**Caution: OEE Local Database Consideration.** When copying a package using local Oracle database, there are additional .DBF files in the target package spec directory. For example, if copying PY910FULL to PD910FULL, these two DBF files would exist:


PD910\package\PD910FULL\spec\PD910FUL.DBF

PD910\package\PD910FULL\spec\PY910FULL.DBF

Before deploying the package, you must manually delete the source package DBF file (in this example, PY910FULL.DBF). This must be done manually because it is not possible for the R9894005 UBE to delete this file as the database keeps a lock on it until the UBE ends.

---

11. To access the processing options of the Copy Environment Application (P989400), from menu GH9611 right click on the application and select Prompt for Values.



12. In order to activate the Advanced Copy button, enter a value of Y in this field:

Advanced Copy Options Y/N

Click OK to return to the Environment Copy application and note that a new section with advanced options is available:

Directory copies



The screenshot shows the 'Environment Copy - [Copy to existing environment]' dialog box. It has a menu bar with 'File', 'Edit', 'Preferences', and 'Form'. Below the menu bar is a toolbar with icons for 'Can...', 'Prev', 'Next', 'Dis...', 'Abo', 'Links', 'Prev', 'OLE ...', and 'Internet'. The main area is divided into several sections:

- Source Environment:** DV910
- Target Environment:** PD910
- Source Path Code:** DV910
- Target Path Code:** PD910
- Source Package:** DV910FA
- Target Package:** PD910FB
- Generate OCM in System / Server Map:** ☒
- Central Objects:**
  - ☒ Copy Central Objects
    - ☒ Copy Object Librarian
    - ☒ Copy Versions
    - ☒ Copy EBU History
- Business Data / Control Tables:**
  - ☒ Copy Business Data
  - ☒ Copy Control Tables
- Package Copy:**
  - Package / Path Code:**
    - ☒ Copy Metadata Repository
    - ☐ Rename Metadata Repository
    - ☐ Don't copy package
  - ☒ Configure Package Manifest
- Directory copies:**
  - ☒ Copy Path Code, Pkg dir - local
    - ☒ Copy Pkg Hdr / Dtl / pkg inf
  - ☒ Copy Path Code, Pkg dir - server

For example, if you choose to do all the database copies using database / system tools, you would set the copy options like this:



## 15.4 Setting Up an Upgrade Plan for the Production Environment

Your goal should be to set up a plan similar to the plan used to upgrade the other environments. However, note that some exceptions might be given in this task. Remember that production should be the only environment being upgraded at this time because upgrading other environments at the same time increases downtime.

To set up an upgrade plan for the production environment, perform all the normal tasks associated with an initial installation with differences as listed in this table:

| Task                                                      | Difference                                                                                                                              |
|-----------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------|
| <i>Entering a Plan Description</i>                        | Press OK to enter the plan information manually.                                                                                        |
| <i>Entering Location Information</i>                      | Click Select to enter location information for an existing Location.<br>On the next resulting dialog, select the Location and click OK. |
| <i>Entering Deployment Server Information</i>             | Click Select to enter deployment server information for an existing Deployment Server if you are not changing servers.                  |
| <i>Entering Enterprise Server Information</i>             | Click Select to if you are not changing servers.<br>If you are changing servers, click Add your add a new server.                       |
| <i>Entering Enterprise Server Data Source Information</i> | Select the default value, and verify the data sources if you are adding a new Enterprise Server into your plan.                         |

| Task                                               | Difference                                                                                                                                                                                                                                                                                                             |
|----------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>Defining Machine\Server Types</i>               | Keep all of these options turned off. These machines are defined in the initial installation plan.                                                                                                                                                                                                                     |
| <i>Entering Shared Data Source Information</i>     | If you are using recommendations, accept the default values; otherwise, you should modify to fit your specific installation values.                                                                                                                                                                                    |
| <i>Setting Up Environments</i>                     | Turn on the options for Default Environments Data Load and Advanced Options.                                                                                                                                                                                                                                           |
| <i>Selecting an Environment</i>                    | Select the pathcode that you want installed on the Deployment Server from the Deployment Server disk (for missing environments on this form).                                                                                                                                                                          |
| <i>Specifying Environment Data Load Parameters</i> | Enable the Load Production Data option, and click OK.                                                                                                                                                                                                                                                                  |
| <i>Verifying Advanced Parameters</i>               | Select the following: <ul style="list-style-type: none"> <li>■ Upgrade Environment.</li> <li>■ PD7333 or PD7334 as Previous Environment.</li> <li>■ Check Table Conversions.</li> <li>■ Clear Specification Merge.</li> <li>■ Enable Control Table Merge if you need to bring over specific control tables.</li> </ul> |
| <i>Setting Up Environment Data Sources</i>         | Click OK for manual set up if you want to set up data sources except for these: Control Tables - Prod, Versions - PD910, Central Objects - PD910, Business Data - PROD.                                                                                                                                                |
| <i>Adding a Remote Location</i>                    | Skip this section.                                                                                                                                                                                                                                                                                                     |

After you run the Installation Planner with these settings, click OK at the congratulations screen to obtain a report. Review each section of the Planner Validation report and check for any of these potential error conditions:

- Duplicate Entry is the result of conversions that have run previously on Data Dictionary and System Tables. You can safely disregard these duplicate entries.
- Source and Target data source entries must be identical, and all must read as Business Data - PROD. You should remove conversions for the Central Objects or System data sources if they are present.
- Control Table Merge displays the control tables you have chosen to run. The remaining Control Table merges are for Solution Explorer, UDCs, and other Control Tables.

## 15.5 Taking the Production Environment Offline

Take the production environment offline before continuing.

## 15.6 Running the Installation Plan for the Production Environment

---

**Caution:** The production environment must be unavailable during this task. All users must be logged off the production environment, and no production processes can run during this time.

---

After you have created a plan for the production environment, as well as having copied all the necessary components from the prototype environment, you are ready to run the plan using Installation Workbench. During Installation Workbench, run Table Conversion Workbench and Control Table Workbench. These processes preserve and merge the business data and control tables from your production environment.

To run the Installation Plan for the production environment:

1. Take the production environment offline.
2. Log on to the planner environment.
3. On **Installation Workbench**, double-click the installation plan you created for the production environment.
4. Perform the tasks in the Installation Workbench section.

## 15.7 Testing the Production Package

The next step in upgrading production is testing your modifications on the workstation where you should surface test the Release 9.1 production environment. After you finish testing the environment, you can deploy it to other workstations.

## 15.8 Bringing the Production Environment Online

The final step in upgrading the production environment is to bring the production environment online.



---

## Retrofitting Custom Modifications

This section discusses these topics:

- [Section 16.1, "Overview"](#)
- [Section 16.2, "Retrofitting Custom Modifications"](#)
- [Section 16.3, "Using JD Edwards Compare and Merge Tools"](#)

### 16.1 Overview

When upgrading to a new release, you might need to retrofit some of your modifications to the new release. Because it is a laborious process to recreate custom modifications each time you upgrade the software, the upgrade process preserves most of your custom modifications. This chapter explains how to integrate any custom modifications that the upgrade process did not preserve into your new Release 9.1 software. This integration, called retrofitting, enables refitting of your customizations that could not be merged into the new version of the software.

Retrofitting modifications only needs a workstation with the upgraded software and the development tools provided with Release 9.1. These tools compare the customizations that Release 9.1 merged into the new software with any pathcode in the system. Thus, you can easily compare your upgraded modifications with a version of your modifications before the upgrade or with the pristine environment of the new release.

---

**Note:** The ability to carry forward the deletion of standard JD Edwards EnterpriseOne text overrides is not a supported custom modification. That is, if a text override is deleted by a customer it is re-deployed with the next ESU or upgrade. The original static text control should be hidden. A new control with the desired text should be added in its place.

---

### 16.2 Retrofitting Custom Modifications

To retrofit custom modifications:

1. From the workstation on which you will retrofit the object modifications, check out the modified objects.

To check out objects, see *JD Edwards EnterpriseOne Tools Object Management Workbench for the Web Guide*.

[http://docs.oracle.com/cd/E24705\\_01/doc.91/e24255/toc.htm](http://docs.oracle.com/cd/E24705_01/doc.91/e24255/toc.htm)

2. Use the ER Compare utility to compare the upgraded version of the object on the client machine to a version of the object as it was before the upgrade.

This tool enables the direct copy of event rules from the original specifications to the upgraded specifications. See the section of the *JD Edwards EnterpriseOne Tools Software Updates Guide* entitled: *JD Edwards EnterpriseOne ER Compare* for more information about this procedure.

[http://docs.oracle.com/cd/E24705\\_01/doc.91/e24260/compare\\_tools.htm#BABDEDHF](http://docs.oracle.com/cd/E24705_01/doc.91/e24260/compare_tools.htm#BABDEDHF)

3. Use the other design tools described in the JD Edwards EnterpriseOne Development Tools Guides to retrofit other modified components of objects.
4. Use ER Compare to show the difference in named event rule (NER) business function source codes.
5. Redo any custom event rules for Do Initialize events because they have been removed from the UBE event list.
6. When you have tested and retrofitted the modifications, check them back in and rebuild the package.
7. Test and fix the modifications, and then rebuild and re-deploy the corrected package.

Repeat this step until all the modifications are functioning properly.

## 16.3 Using JD Edwards Compare and Merge Tools

The chapter entitled: *Using JD Edwards Compare and Merge Tools* in the *JD Edwards EnterpriseOne Software Updates Guide* fully describes all of the tools that have been created to help you compare between releases as well as with environments on the same release.

See Also

- *JD Edwards EnterpriseOne Software Updates Guide*

[http://docs.oracle.com/cd/E24705\\_01/doc.91/e24260/toc.htm](http://docs.oracle.com/cd/E24705_01/doc.91/e24260/toc.htm)

The following sections in this guide provide a high-level description of the compare and merge tools, including those that have been added since the base release of JD Edwards EnterpriseOne Tools Release 9.1:

- [Section 16.3.1, "Using the Application Configuration Analyzer \(Release 9.1 Update 2\)"](#)
- [Section 16.3.2, "Using the Customization Object Analyzer \(Release 9.1 Update 2\)"](#)
- [Section 16.3.3, "JD Edwards Visual Compare for UDC Descriptions and Glossary Tool"](#)
- [Section 16.3.4, "JD Edwards EnterpriseOne FDA Compare"](#)
- [Section 16.3.5, "JD Edwards EnterpriseOne ER Compare"](#)

### 16.3.1 Using the Application Configuration Analyzer (Release 9.1 Update 2)

The Application Configuration Analyzer is a set of reports which identify differences for processing options, data dictionary (DD) items, and user defined codes (UDCs) between releases or environments. These reports are:

- Versions Compare Report

- User Defined Codes Compare Report
- Data Dictionary Compare Report

If you have made custom modifications to business data, these reports can help you verify that your modifications were carried forward to the new release. You can use these tools anytime you want to compare items between two environments.

#### See Also

- The section entitled: *Application Configuration Analyzer* in the *JD Edwards EnterpriseOne Software Updates Guide*.

[http://docs.oracle.com/cd/E24705\\_01/doc.91/e24260/compare\\_tools.htm#BABEHIBI](http://docs.oracle.com/cd/E24705_01/doc.91/e24260/compare_tools.htm#BABEHIBI)

### 16.3.2 Using the Customization Object Analyzer (Release 9.1 Update 2)

If you are on an older release of JD Edwards EnterpriseOne, you need to identify customizations in order to determine the impact and level of effort to retrofit the customizations into the newer release of JD Edwards EnterpriseOne. This utility helps to identify the customizations in order to determine the impact and level of effort to retrofit the customizations into the newer release of JD Edwards EnterpriseOne. A review of this information, prior to performing modifications within the software, will allow for a smoother and more predictable upgrade of the EnterpriseOne software.

The Customization Object Analyzer is comprised of a UBE that loads a table and UBEs that read from that table to create either a summary or detailed report. The UBEs are:

- **R9840DL (Object Dataload)**  
This UBE loads the F98881CU table in a parent-child hierarchy of object changes with a list of all JD Edwards EnterpriseOne customized objects.
- **RD9840RS (Object Customization Summary Report - BI Publisher)**  
This UBE creates a summary report from the data in the F98881CU table.
- **RD9840RD (Object Customization Detail Report - BI Publisher)**  
This UBE creates a detail report from data in the F98881CU table that shows the details of the customizations grouped by various criteria.
- **R9840R (Object Customization Summary and Detail Report - Standard Version)**  
This UBE creates a summary and detail report from the data in the F98881CU table.

#### See Also

- The section entitled *Customization Object Analyzer* in the *JD Edwards EnterpriseOne Tools Software Updates Guide*.

[http://docs.oracle.com/cd/E24705\\_01/doc.91/e24260/compare\\_tools.htm#CHDFHBHB](http://docs.oracle.com/cd/E24705_01/doc.91/e24260/compare_tools.htm#CHDFHBHB)

### 16.3.3 JD Edwards Visual Compare for UDC Descriptions and Glossary Tool

JD Edwards EnterpriseOne Visual Compare for UDC Descriptions and Glossary tool (P96472) enables you to review and apply text updates for Data Dictionary glossaries and UDCs. You can see a side-by-side comparison of the new and old text values, which enables you to choose whether to accept the changes.

The Visual Compare for UDC Descriptions and Glossary Tool, application P96472, is run from an administrative client workstation within JD Edwards EnterpriseOne and applies the changes to the current environment.

**See Also**

- The section entitled *JD Edwards Visual Compare for UDC Descriptions and Glossary Tool* in the *JD Edwards EnterpriseOne Tools Software Updates Guide*.

[http://docs.oracle.com/cd/E24705\\_01/doc.91/e24260/compare\\_tools.htm#BABJCAED](http://docs.oracle.com/cd/E24705_01/doc.91/e24260/compare_tools.htm#BABJCAED)

### 16.3.4 JD Edwards EnterpriseOne FDA Compare

The FDA Compare tool in Oracle's JD Edwards EnterpriseOne Form Design Aid (FDA) enables you to compare one version of an application to another. You can compare them on the application level to determine whether forms have been added, deleted, or rearranged and whether the properties have changed. You also can compare the forms in the applications to each other to see whether controls have been added, deleted, or rearranged and whether the properties have changed.

Additionally, you can compare two different applications as well. This feature is useful when you have made a new application by copying an existing one and then modifying it. Then, when you upgrade, you can not only compare the base application to its new counterpart, but also you can compare a custom application.

While working with the target object, you can use all FDA functions except creating new forms. While comparing, you can change the target object to match the source object. If an object exists in the source but not in the target, you can copy it to the target. If an object exists in both but is different in some way, you can merge the specifications from the source to the target to make them identical.

As a software developer, you might use FDA Compare as the final step before checking in the changes to ensure that you made all of the changes you intended to make. In this way, you can also make sure that you did not move a control or make a property change unintentionally.

As an administrator, you might use FDA Compare to see the changes between a software update and the pristine or current implementation. If you have performed a number of customized modifications, you can more carefully implement the software changes without fear of ruining the customization.

**See Also**

- The section entitled *JD Edwards FDA Compare* in the *JD Edwards EnterpriseOne Tools Software Updates Guide*.

[http://docs.oracle.com/cd/E24705\\_01/doc.91/e24260/compare\\_tools.htm#BABBFJFF](http://docs.oracle.com/cd/E24705_01/doc.91/e24260/compare_tools.htm#BABBFJFF)

### 16.3.5 JD Edwards EnterpriseOne ER Compare

JD Edwards ER Compare provides a detailed, on-screen comparison of event rules. You can change the target object (your local version) within the utility by moving lines directly from the source. You can also remove or disable lines. In addition to providing an on-screen comparison, you can select to print a report detailing the changes as well.

**See Also**

- The section entitled *JD Edwards ER Compare* in the *JD Edwards EnterpriseOne Tools Software Updates Guide*.



[http://docs.oracle.com/cd/E24705\\_01/doc.91/e24260/compare\\_tools.htm#BABJCAED](http://docs.oracle.com/cd/E24705_01/doc.91/e24260/compare_tools.htm#BABJCAED)



This chapter discusses:

- [Section 17.1, "Using the PORTTEST Checklist"](#)
- [Section 17.2, "Resolving Data Errors"](#)
- [Section 17.3, "Planner Update Special Instructions"](#)
- [Section 17.4, "Resolving Errors Due to Lack of \\*ALLOBJ and \\*JOBCTL Authority"](#)

## 17.1 Using the PORTTEST Checklist

If the PORTTEST program fails to run, use this checklist to diagnose the problem before calling Global Customer Support. Please have the answers to these questions as well as copies of error messages, your Enterprise Server , and any error logs, such as JDE.log or JDE\_xx.log.

PORTTEST may fail if replication, security server, or transaction processing have been installed incorrectly. If problems occur after the installation of one or more of these services, check the setup of those services for incorrect parameters.

Additionally, if PORTTEST reports warnings that indicate data dictionary or company constants are invalid, it may be because the F0010 table is empty. As is true with the full JD Edwards EnterpriseOne installation, this is a normal condition in Pristine and Production environments.

| General Issues                                                           | Yes\No |
|--------------------------------------------------------------------------|--------|
| Is the user logged on with administrator privileges?                     |        |
| Is the JDENET Service starting with a network domain user?               |        |
| Is the JDENET Service account included in the local administrator group? |        |
| Are all the environment variables set?                                   |        |
| Is the C compiler installed with Unicode module?                         |        |
| Can you query the database on the Enterprise Server?                     |        |
| Is a PostScript or PCL printer connected to this machine?                |        |
| Are the printer drivers for this printer installed?                      |        |
| Is this printer configured as the default printer?                       |        |

| <b>jde.ini Issues</b>                                | <b>Yes\No</b> |
|------------------------------------------------------|---------------|
| Is your jde.ini located in the correct directory?    |               |
| Does your jde.ini have the correct permissions?      |               |
| Are the following jde.ini parameters set properly?   |               |
| [Network Queue Settings]                             |               |
| Default Printer OUTQ=your printer                    |               |
| [UBE]                                                |               |
| If you use PostScript, is the correct filter set up? |               |
| [DB System Settings]                                 |               |
| Verify all parameters, especially the following:     |               |
| Default Env= your default environment                |               |
| Default Pathcode = your default path code            |               |
| Server = database server name                        |               |
| [JDENET]                                             |               |
| serviceNameListen = port number                      |               |
| serviceNameConnect = port number                     |               |
| [INSTALL]                                            |               |
| E910=your path                                       |               |

| <b>Communications Issues</b>                                          | <b>Yes\No</b> |
|-----------------------------------------------------------------------|---------------|
| Do the workstations and server agree on the IP address of the server? |               |

| <b>Other Issues</b>                                                                                                    | <b>Yes\No</b> |
|------------------------------------------------------------------------------------------------------------------------|---------------|
| Were your server map tables (F98611 and F986101) edited properly?                                                      |               |
| Run the Verify OCM application and verify:                                                                             |               |
| Do only host databases exist?                                                                                          |               |
| No entries for batch applications exist.                                                                               |               |
| Are OneWorld tables accessible to the host?                                                                            |               |
| Can you query the F0902 table?                                                                                         |               |
| Does PORTTEST run without error for each valid path code?                                                              |               |
| Does the user name match that of a valid Release 9.1 account? Remember that the user name is case sensitive.           |               |
| Is the password valid for the given Release 9.1 account?                                                               |               |
| Does the environment name match a valid Release 9.1 environment? Remember that the environment name is case sensitive. |               |
| Does JDENET start and stop properly?                                                                                   |               |

If you answered no to any of these questions, your batch application might not run. If you answered yes to all the questions, submit a batch application now.

If your batch application does not run correctly, turn on error logging and resubmit the batch. This log helps Global Customer Support diagnose the exact problem.

## 17.2 Resolving Data Errors

If you are receiving data warnings against the F0010 table in the Pristine or Production environments, the table might be empty. This is how it is delivered. You can ignore these warnings, load demo data, or load your own data.

## 17.3 Planner Update Special Instructions

The Electronic Software Update (ESU) for the Planner Update Special Instructions was created with special features that updates the Planner pathcode on the Deployment Server. It includes all fixes for Release 9.1 installation and upgrade process.

You must run the `specialInstrs.bat` file to copy certain table records from the ESU database to the Planner databases on the Deployment server.

1. On the Deployment server, browse to this directory:

```
\JDEdwards\910\Planner\Package\JMxxxxxxx\Scripts
```

2. Run the batch file `specialInstrs.bat`. Note any success or failure messages that appear in the command window.

Review the `SpecialInstrs.log` file that is created in the same directory for details.

## 17.4 Resolving Errors Due to Lack of \*ALLOBJ and \*JOBCTL Authority

By default the Installation program grants \*JOBCTL authority to the ONEWORLD user profile. You may have a temporary requirement to grant \*ALLOBJ authority to ONEWORLD. This could be required if ONEWORLD needs to start journaling on a table but does not have OBJMGT rights to that table. For example, when submitting a UBE to the server for the first time, ONEWORLD needs to start journaling on F986111. Symptoms of this problem are errors indicating a transaction was cancelled because a commit cycle could not be start.

Of the multiple ways to grant the \*ALLOBJ authority to ONEWORLD, the simplest is to give ONEWORLD rights to all tables using the SETOWAUT tool. Alternatively, you could run the GRTOBJAUT command to give ONEWORLD OBJMGT authority of to all tables in your business data, system, and server map libraries. Note that either method causes locks to be put on tables, which could interfere with other users on your system. In order to avoid that potential interference caused by locks, it may be preferable to temporarily grant \*ALLOBJ authority to ONEWORLD, which you can revoke after a short while.

To grant \*ALLOBJ authority, from a green screen enter the following command:

```
CHGUSRPRF USRPRF (ONEWORLD) SPCAUT (*ALLOBJ *JOBCTL) JOBD (*LIBL\ONEWORLD)
```



---

## Performing a Data-Only Upgrade

This chapter describes an abbreviated upgrade method that can be used if the customer has made no software modifications that need to be brought forward to the new release of the software. In this method, only customer business data is preserved, and all other changes that might have been made to the software are overwritten. Basically, the process is a new installation of the software for everything except the business data. The business data is then converted to the new release by running table conversions on this data source only.

In this abbreviated method, you can skip many of the tasks required for a normal upgrade. In some cases, you might need to slightly modify normal upgrade tasks as well.

For the data-only upgrade, the term business data refers to application tables only. Changes to control tables, such as user-defined codes (UDCs), menus, and data dictionary are merged, and additions to the Object Librarian are populated when you run the Environment Workbench. However, changes to the specification tables (including Versions List) are not merged into the new release. Custom or modified tables, business functions, and applications are also not preserved in this process.

This section includes these tasks:

- [Section 18.1, "Testing Long File Names"](#)
- [Section 18.2, "Pre-Upgrade Procedures"](#)
- [Section 18.3, "Installing the Deployment Server"](#)
- [Section 18.4, "Planning the Upgrade"](#)
- [Section 18.5, "Running Installation Workbench"](#)
- [Section 18.6, "Custom Modifications and Packages"](#)
- [Section 18.7, "Upgrading the Production Environment"](#)

### 18.1 Testing Long File Names

Before you run a data only upgrade, you must test the cross-reference table to ensure that you can create tables with names longer than 10 characters. To test the cross-reference table, follow the procedure described in Section 4.3.9, "Testing Long File Names on the IBM i" in the Chapter 4 of this guide.

### 18.2 Pre-Upgrade Procedures

These procedures do not apply to a data-only upgrade because control table changes and customizations are not carried forward to the new release.

Skip the following steps which are in the [Chapter 2, "Before You Begin the Upgrade"](#) section of this guide:

- [Section 2.3, "Preparing the Development Environment"](#)
- [Section 2.5, "Checking Modification and Merge Flags"](#)
- [Section 2.7.3, "Refreshing the Control Tables"](#)

Instead of refreshing the existing user defined code and menu tables, delete them to ensure that they will be reloaded at the new release level when you run the Installation Workbench. Do not delete the F0002 and F00021 tables; these control tables must match the business data tables in order for the Next Numbers to be correct. Alternatively, you can save the control tables (menu, UDC, and data dictionary tables) and run the Control Table merge to update the tables with the new software release information.

#### See Also

[Section 2.7.4, "Verifying Custom Changes in Master Control Tables"](#) in the [Chapter 2, "Before You Begin the Upgrade"](#) section of this guide.

## 18.3 Installing the Deployment Server

Install the Deployment Server as instructed in the upgrade guide for your platform. You must then load central objects for the environment that you are installing (for example, if you are upgrading the production environment, run the loaded or reloaded executable program).

## 18.4 Planning the Upgrade

When defining the plan, do the following:

- Verify that the Upgrade Environment and Table Conversions options are turned on.
- Set up the plan to upgrade the chosen environment.
- Do not turn on Specification Merges.
- If you choose not to delete the control tables, set the Control Tables Merges to merge.

Once you have defined your plan, go back to **Work with Installation Plans**. Highlight your plan and click **Expand**, and then choose the table conversion section and click **Select**.

Because you need to run only the vertical application table conversions, delete any of the following table conversion records that are in your plan. The records listed in your plan will depend on the version of the software from which you are upgrading. Some records might be listed multiple times.

- F89210
- F98710
- F9210 (R8989210)
- F98741 (R89IDVAR)
- F9862
- F98740



- F98741 (R8998741)
- F98752
- F98753
- F98720
- F9210 (R899210)
- F98711
- F98743
- F98762
- F98745
- F98760
- F98750
- F98751
- F98761 (R8998761)
- F98761 (R8998763)
- F98762
- F98950
- F9860
- F89210
- F983051
- F98306

## 18.5 Running Installation Workbench

Run Installation Planner as you normally would for an upgrade, and complete all of these Installation Workbench tasks:

- [Section 6.10, "Working With Initial Tasks Workbench"](#)
- [Section 6.11, "Configuring Your Locations"](#)
- [Section 6.12, "Configuring Your Data Sources"](#)
- [Section 6.13, "Configuring Your Environments"](#)
- [Section 6.14, "Using Machine Workbench"](#)
- [Section 6.16.4, "Verifying the Table Conversion Process"](#) (for business data only)
- [Section 6.20, "Using Remote Location Workbench"](#)

## 18.6 Custom Modifications and Packages

Do not perform the following chapter if you do not need to distribute customizations:

- [Chapter 14, "Building and Testing Packages"](#)

When testing the new release, use one of the delivered standard packages, because no modifications are carried forward.

## 18.7 Upgrading the Production Environment

If you are upgrading the production environment, follow the instruction for creating a production plan. Keep in mind the notes for Installation Planner, and repeat the steps above for removing the listed tables from the Table Conversion Planner.

---

## Creating a Remote Installation Plan

This section discusses:

- [Section 19.1, "Understanding Remote Installation Plans"](#)
- [Section 19.2, "Starting Installation Planner"](#)
- [Section 19.3, "Entering Information in Installation Planner"](#)
- [Section 19.4, "Entering Plan Location Information"](#)
- [Section 19.5, "Entering Deployment Server Information"](#)
- [Section 19.6, "Entering Enterprise Server Information"](#)
- [Section 19.7, "Enter Data Source Information for Server Map"](#)
- [Section 19.8, "Entering HTML Web Server Information"](#)
- [Section 19.9, "Entering Data Server Information"](#)
- [Section 19.10, "Replicating Information to Remote Locations"](#)
- [Section 19.11, "Entering Shared Data Source Information"](#)
- [Section 19.12, "Setting Up Environments"](#)
- [Section 19.13, "Verifying Advanced Parameters"](#)
- [Section 19.14, "Setting Up Data Sources for Environment"](#)
- [Section 19.15, "Remote Location Packages"](#)
- [Section 19.16, "Finalizing the Installation Plan"](#)
- [Section 19.17, "Concluding the Planner Validation Report"](#)

### 19.1 Understanding Remote Installation Plans

Installation Planner is a Release 9.1 application that runs on the Deployment Server. It is a system administration tool that guides through the process of configuring the machines on which your company will run Release 9.1.

To set up Release 9.1 for a remote location, create a plan that includes remote locations. Complete the tasks in this section after you create and complete a basic installation plan, and are ready to add the remote locations to the configuration. This section includes information for installing an alternate language.

Before you begin, decide what your replication strategy is for Release 9.1. You can use Installation Workbench to copy the system, data dictionary, control, constant and master tables to your remote location. Ongoing replication of the data in these sources must be implemented using third-party software; as of release 8.9, JD Edwards

EnterpriseOne no longer has a built-in replication engine. To use replication for Release 9.1, review the processing options for the Installation Planner to make sure that they are set correctly for replication.

The information that you provide on the Installation Planner forms, such as database type and Enterprise Server type, determines the information that the system displays on the remaining forms.

*See Also*

*Reviewing Installation Planner Processing Options* for more information about how the processing options for Installation Planner also affect the choices that you are given while setting up your plan

---

---

**Note:** *Installation Planner Considerations.* Depending on which tables you want to replicate, you are prompted for different data source information. For example, if you choose to replicate the control tables, you are asked to define the control tables data source.

---

---

---

---

**Note:** *Data Source Considerations.* JD Edwards EnterpriseOne provides configured data sources. However, when you run Installation Planner, you might need to modify some data source information to reflect your system-specific configuration. Only data sources that are referenced in the replication forms appear when you create a remote plan.


---

---

## 19.2 Starting Installation Planner

To start Installation Planner:

1. Log on to Release 9.1 as user JDE with the database password for user JDE.
2. Access the planner environment (JDEPLAN).
3. From the System Installation Tools menu (GH961), click Custom Installation Plan.



4. On Work with Installation Plans, click Add.  
The Installation Planner form appears.

## 19.3 Entering Information in Installation Planner

To enter information in Installation Planner:

**Custom Installation Plan - [Installation Planner]**

File Edit Preferences Form Window Help

OK Cancel Dis... Add Links Deplo... OLE... Internet

Tools  
Form  
Deploy...

**Plan Information:**

Name: REMOTE

Description: Remote Plan

Status: 10 In Planning

**Install Type:**

☒ Install ☐ Upgrade ☐ Software Update (ASU/ESU)

**Release:**

To Release: E910

1. On Installation Planner, complete these fields:

| Field        | Description                                  |
|--------------|----------------------------------------------|
| Name         | Enter the name of your remote plan.          |
| Description  | Enter the description of your remote plan.   |
| Status       | Select 10 as the status of your remote plan. |
| Install Type | Select Install.                              |
| To Release   | Verify that the release number is E910.      |

2. On Installation Planner, click OK.

**Location**

A plan must be associated with a location. If you would like to define a new location press OK. To select an existing location press select.

OK Select Cancel

3. On the Location dialog, click OK.

## 19.4 Entering Plan Location Information

To enter plan location information:

1. When you are prompted to enter new location information, click OK to enter a new location.
2. On Location Revisions, complete these fields:

| Field           | Description                                                                                                                                                                                                                                                                                                                                                                                                                            |
|-----------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Location        | Enter the location to which this plan applies. The location could be a city, company headquarters, or a division of a company.                                                                                                                                                                                                                                                                                                         |
| Description     | Enter a description of the location name.                                                                                                                                                                                                                                                                                                                                                                                              |
| Location Code   | For a remote location, enter a 3-character alphanumeric identification code. This 3-character code is used as a prefix for the environments of the remote location, and a suffix is attached for replicated data sources. For example, you might use DAL if the location were Dallas, Texas. In that case, the prototype environment would be named DALPY910, and the business data data source would be named Business Data - CRPDAL. |
| Parent Location | Enter the parent location to which this remote location is attached.                                                                                                                                                                                                                                                                                                                                                                   |


3. Click OK.




## 19.5 Entering Deployment Server Information

Once a plan location is specified, complete the information for the Deployment Server. You are given the option to enter a new Deployment Server or choose an existing one. For most situations, you will have a tiered Deployment Server for the remote location.

To enter Deployment Server information:



1. At the Installation Planner prompt asking if you want to enter new Deployment Server information, click OK to add a Deployment Server.



2. On Deployment Server Revisions, complete these fields:



| Field         | Description                                                                                                                                                            |
|---------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Machine Usage | Displays the default value of 15 to indicate that this is a Deployment Server.                                                                                         |
| Machine Name  | Enter the name of your Deployment Server. The name is case sensitive, should not exceed 15 characters, and should not contain any special characters.                  |
| Description   | Enter a description of the machine name. This name includes the location with which this Deployment Server is associated, and whether or not it is the primary server. |
| Release       | Enter the Release 9.1 release number that you are installing, or use the visual assist button to choose one from the list. For example, E910 is the current release.   |
| Host Type     | Displays the default value of 50 to indicate that the server type is an Intel NT.                                                                                      |
| Location      | Displays the default location chosen for this plan.                                                                                                                    |
| Primary User  | Enter the user to whom email is sent when a package is deployed. The default for Primary User is JDE.                                                                  |

**3.** On the Deployment tab, complete these fields:


| Field                     | Description                                                                                                                                                                                                         |
|---------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Primary Deployment Server | Enter the hierarchy of the servers. Type 0 (zero) if a primary Deployment Server for the location exists and this is a secondary server. Type 1 if this is the primary Deployment Server for the location.          |
| Server Share Path         | Enter the server share path where you installed Release 9.1 on your Deployment Server. Make sure that this path is specific to your version of the release. For example, for Release 9.1, the path ends with \E910. |

**4.** Click OK.

**Tip:** If you enter invalid information into a tab field, a stop sign symbol appears next to the tab name, such as Deployment Server. For more information about the error, click the stop sign icon in the bottom right-hand corner of the form.

**5.** Click OK.

**Tip:** If you enter invalid information into a tab field, a stop sign symbol appears next to the tab name, such as Deployment Server. For more information about the error, click the stop sign icon in the bottom right-hand corner of the form.




6. To continue with Remote Installation Planner setup, click No.

## 19.6 Entering Enterprise Server Information

---

**Note:** During the definition of the Enterprise Server, a port number must be defined. While Enterprise Servers running the same release can use the same port number, an Enterprise Server running two different versions of software must use two different port numbers.

---



On Enterprise Server, click the OK button to define a new Enterprise Server, or click the Select button to choose an existing Enterprise Server.

**Custom Installation Plan - [Enterprise Server Revisions]**

File Edit Preferences Form Window Help

OK Can... Dis... Abo Links Window OLE ... Internet

Machine Usage: 20 Enterprise Server Location: Denver

Machine Name: Ent6 Primary User: JDE

Description: Enterprise Server iSeries

Release: E910

Host Type: 10 AS/400

Workstation Deployment **Enterprise** Data HTML Crystal CMS

Port Number: 6016

Logical Machine Name: ENT6

Database Type: DB2 UDB on OS/400

Server Map Data Source: Ent6 - 910 Server Map

Installation Path: E900SYS

Deployment Server Name: TITANIC

1. On Enterprise Server Revisions, verify or complete these fields:

| Field               | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
|---------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>Machine Name</i> | <p>The name of the primary Enterprise Server. The name is case sensitive and should not contain any special characters.</p> <p>Because the machine name is used to create the Server Map datasource name, and because the Platform Pack Installer does not restrict you from entering a machine name that results in a datasource name greater than 30 characters; if the machine name for the Enterprise Server is longer than 13 characters, the resulting datasource name will be longer than the allowed 30 characters. For example, if your machine name is 15 characters (A23456789012345), the base datasource name input into the Planner would be: A23456789012345 - 910 Server Map.</p> <p><b>Note:</b> The field in table F98611 is a hard restriction; the field only allows 30 characters. The actual field size cannot be modified or changed.</p> <p>When the Planner runs it truncates the value to 30 characters because that is the restriction in the F98611 table. The Platform Pack does not truncate the value when it builds the <code>jde.ini</code> for the Enterprise Server. Therefore, any value greater than 30 characters will result in a mismatch between the <code>jde.ini</code> and the F98611 table. That is, using the previous example, the <code>jde.ini</code> would have the full length value A23456789012345 - 910 Server Map (which is 32 characters) while the F98611 populated by the Planner would have a value of A23456789012345 - 910 Server M.</p> <p>To remedy, you could do any one of the following:</p> <ul style="list-style-type: none"> <li>Manually modify values in table F98611 to match the truncated value in the <code>jde.ini</code> file.</li> <li>Ensure that the value is not truncated by limiting the datasource name to 30 characters (this would mean limiting the machine name for the Enterprise Server to 13 characters).</li> <li>Manually truncate the value in the F98611 table (for example, A23456789012345 - 910 Svr Map.</li> </ul> <p>In any case, you <b>must</b> ensure that the values for Server Map datasource names in the F98611 table exactly match those in the <code>jde.ini</code> file on the Enterprise Server.</p> |
| <i>Description</i>  | Enter a description for the machine.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
| <i>Release</i>      | Enter the release number to which this plan applies, or use the visual assist button to choose one from the list. The default value is E910.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
| <i>Host Type</i>    | Click the visual assist button and choose the type of Enterprise Server you are adding to the plan. In this case, IBM i.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
| <i>Location</i>     | The location chosen for this plan appears by default.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| <i>Primary User</i> | The user to whom an email is sent when a package is deployed. The default value for Primary User is JDE.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |

---

**Note:** The case of machine name must also match the network ID for that machine.

---

- Continuing on Enterprise Server Revisions, select the Enterprise tab, and complete or verify these fields:

| Field              | Description                                                                                                |
|--------------------|------------------------------------------------------------------------------------------------------------|
| <i>Port Number</i> | The port number value (6016) for this Enterprise Server appears by default from the <code>jde.ini</code> . |

| Field                         | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
|-------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>Logical Machine Name</i>   | The Installation Planner detects and provides a default value based on the current machine name on which the program is running. The name is case sensitive, should not exceed 15 characters, and should not contain any special characters.                                                                                                                                                                                                                             |
| <i>Database Type</i>          | Enter the value for your database:<br><b>I - DB2 400</b>                                                                                                                                                                                                                                                                                                                                                                                                                 |
| <i>Server Map Data Source</i> | Whenever you enter a host type, the Installation Planner populates this field with a default value:<br><i>machinename</i> - 910 Server Map<br>where <i>machinename</i> is the name of your machine.                                                                                                                                                                                                                                                                      |
| <i>Installation Path</i>      | Verify that the default value is the installation directory path to which you want to install Release 9.1 on the Enterprise Server. Make sure the value is specific to your version of the release. For example, for Release 9.1 the default path is:<br><br>\\JDEdwards\\PPack\\E910SYS<br><br>This is the system library.<br><br><b>Caution:</b> You must change the value that defaults into the <i>Installation Path</i> field as shown in the screen capture above. |
| <i>Deployment Server Name</i> | Using the visual assist button, choose the name of the Deployment Server to which this Enterprise Server is attached. A Deployment Server name appears in this field by default, but it can be changed if necessary.                                                                                                                                                                                                                                                     |

---


**Note:** If you change the port number to a value other than 6016, you must also change this setting in both the Enterprise Server and workstation JDE.INIjde.ini.

---


3. Click OK.

## 19.7 Enter Data Source Information for Server Map


To enter information for the Server Map data source:



1. On Data Source, click OK to continue entering unique data source information.



2. On Data Source Revisions, verify the accuracy of the Server Map data source.
3. Click OK.



4. On the **Would you like to add another Enterprise Server?** dialog, click the **Yes** or **No** button.

## 19.8 Entering HTML Web Server Information

---

**Note:** For Release 9.1, the current terminology and that used in this guide is to refer to the machine running the JD Edwards EnterpriseOne Java Application Server (JAS) as the HTML Web Server. Functionally, these terms are all synonymous. However, this guide only uses the terms JAS or Java Server when explicitly labeled as such by the software.

---



---

**Caution:** The HTML Web Server is mandatory for the majority of JD Edwards EnterpriseOne applications because the end-user applications are only accessible through a web interface.

---

To enter HTML Web Server information:



1. Click OK to define a new HTML Server, or click Select to choose from a list of existing HTML Servers.

If you choose Select, you are presented with the Machine Search table, from which you can make your selection.

2. On HTML Server Revisions, complete these fields:

| Field                | Description                                                       |
|----------------------|-------------------------------------------------------------------|
| <i>Machine Usage</i> | The default value of 30 indicates that this is a HTML Web Server. |

| Field               | Description                                                                                                                                         |
|---------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>Machine Name</i> | Enter the name of your HTML Web Server. The name is case sensitive, should not exceed 15 characters, and should not contain any special characters. |
| <i>Description</i>  | Enter a description of the HTML Web Server machine.                                                                                                 |
| <i>Release</i>      | Enter E910 to indicate the release number that you are installing.                                                                                  |
| <i>Host Type</i>    | The default value of 50 specifies the server type as Intel NT. Select the correct server type.                                                      |
| <i>Location</i>     | The location chosen for this plan appears in this field by default.                                                                                 |
| <i>Primary User</i> | The user to whom an email is sent when a package is deployed. The default for Primary User is listed in the <code>jde.ini</code> .                  |


**3.** On the HTML tab, complete these fields:

| Field                      | Description                                                                                                                                                                                                                                                                 |
|----------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>Primary HTML Server</i> | When the system code generates an email message with a web shortcut pointing to a form, the web shortcut generated points to the "Primary" HTML Web Server. Only one of all the HTML Web Servers defined in installation planner can be defined as primary ("1").           |
| <i>Protocol</i>            | This is the protocol used by the HTML Web Server. Valid values are <i>http</i> or <i>https</i> .                                                                                                                                                                            |
| <i>Server URL</i>          | This is the Domain Name System (DNS) host name of the HTML Web Server.<br><br>The syntax is:<br><code>server_name:port\jde\owhtml</code><br>For example:<br><code>DEVNTA:81\jde\owhtml</code>                                                                               |
| <i>Http Port</i>           | This is the port number the HTML Web Server is listening to.<br><br>For HTTP, the typical port number is <i>80</i> .<br><br>For HTTPS, the typical port number is <i>443</i> .<br><br>However, you can choose to implement a HTML Web Server using a different port number. |




| Field                         | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
|-------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>Default Login</i>          | <p>Defines how shortcuts to a web form are generated by the system code. Values are either a reserved value or an explicit servlet name. Reserved values are:</p> <ul style="list-style-type: none"> <li> <b>Standard</b><br/> The URL generated will point to a servlet on the Primary HTML Web Server. </li> <li> <b>Redirector</b><br/> The URL generated will point to redirector in the Primary HTML Web Server, and redirector will point to a servlet on another HTML Web Server for load balancing. The servlet name to use is generated by the system. </li> <li> <b>Explicit Servlet Name</b><br/> The user can specify an explicit servlet name in this field. In this case, the redirector functionality cannot be used. The URL generated will point to the specified servlet in the Primary HTML Web Server.<br/><br/> Usage of Explicit servlet name is for backward compatibility only. You should not use it unless you have a direct need. </li> </ul> |
| <i>Installation Path</i>      | <p>Enter the installation directory path to which you are installing Release 9.1 on your HTML Web Server. Make sure this is specific to your version of the release, and also the platform and application server on which your HTML Web Server is running.</p> <p>For default paths, refer to the applicable platform- and application server-dependent version of the <i>JD Edwards EnterpriseOne HTML Web Server Reference Guide</i> (WebLogic for Windows, WebLogic for UNIX, WebSphere for Windows, WebSphere for UNIX, WebSphere for IBM i). Otherwise, you must obtain this value from the HTML Web Server machine itself, or its administrator.</p>                                                                                                                                                                                                                                                                                                              |
| <i>Deployment Server Name</i> | <p>Using the visual assist button, choose the name of the Deployment Server to which this HTML Web Server is attached. A Deployment Server name appears in this field by default, but you can change it if necessary.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |

4. Click OK.



5. To add another HTML Web Server, click Yes and repeat steps 1 through 4 to define another HTML Web Server.

## 19.9 Entering Data Server Information



1. On Data Server, choose one of these options:

- OK

If your database resides on a separate server, choose click OK to continue entering unique Data Server information.

- Select

Click this option to select an existing Data Server.

- Skip

Click this option if you do not want to define a Data Server.

- On Data Source, click OK to continue entering unique data source information, or click Take Defaults to select the default data.


For purposes of this procedure to setup a Remote Installation Plan, the Skip option is assumed.

2. Click OK.

## 19.10 Replicating Information to Remote Locations

The options on this form determine whether the software will configure data sources and mappings for the remote location. Ongoing replication must be implemented using third-party software.

To replicate information to remote locations:



1. On Control/System Replication, select the **Replication Setup** tab and select the following options to replicate information to remote locations:


| Field                            | Description                                                                                                                                                                                                                                                   |
|----------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Replicate System Tables          | Select this checkbox to replicate all tables within the System data source. A new data source will be created for the remote location and the mappings for the remote environment will be activated to point to the new System data source.                   |
| Replicate Data Dictionary Tables | Select this checkbox to replicate all tables within the Data Dictionary data source. A new data source will be created for the remote location and the mappings for the remote environment will be activated to point to the new Data Dictionary data source. |

---

**Caution:** Replication must be implemented using a third-party tool.

---

2. Select the Data Load tab.



3. On the **Data Load** tab, choose from the following options to copy selected tables to the remote locations:

| Field                       | Description                                                                                                                                                                                                                          |
|-----------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Load System Tables          | Select this checkbox to initially load the replicated System Tables. The following version of R98403 will be launched to accomplish the task of copying system tables from the base location to remote locations.                    |
| Load Data Dictionary Tables | Select this checkbox to initially load the replicated Data Dictionary Tables. The following version of R98403 will be launched to accomplish the task of copying data dictionary tables from the base location to remote locations.. |

---

**Note:** To edit or change the versions of the R98403 program that copy the control tables, constant tables, and master tables, click the Edit or Search buttons next to their respective versions.

---



---

**Note:** If you have defined multiple locations, the system will prompt you to complete sets of the Replication Setup and Data Load screens for each location.


---

4. Click OK.




## 19.11 Entering Shared Data Source Information

This section describes entering the shared data source information for the Data Dictionary and System data sources.



1. When you are prompted to enter the data source information for the shared data sources, to use the Release 9.1 data sources, click OK to specify or verify the data source information.



2. On Data Source Revisions, enter the data source name for the Data Dictionary data source that will be used by the remote location. For example, **Data Dictionary - 910ATL**.
3. Complete the other fields as applicable for your database and platform.

4. Click the OK button.

The screenshot shows the 'Custom Installation Plan - [Data Source Revisions]' window. The 'Tools' sidebar on the left includes 'Form', 'Advanced', 'Port', 'Database Sizing', and 'Default Sizing'. The main area contains the following fields:

- Data Source Name:** System - 910ATL
- Data Source Use:** DB (Local Data Source)
- Data Source Type:** O (ORACLE) with a checkbox for 'JDBNET Data Source?'.
- Data Class:** S (System)
- Platform:** NTSVR (NT Server)
- Database Server Name:** DENLCM17


At the bottom, there are tabs for different database types: SQL/MSDE ODBC, SQL/MSDE OLEDB, **Oracle**, DB2 OS/400, DB2 UDB, Access, and Logical. The 'Oracle' tab is active, showing:

- Object Owner ID:** SY910
- Database Name (TNS):** orcl


5. On Data Source Revisions, enter the data source name for the System data source that will be used by the remote location. For example, **Data Dictionary - 910ATL**.
6. Complete the other fields as applicable for your database and platform.
7. Click the OK button.

## 19.12 Setting Up Environments

To set up environments:




1. On Environment Selection, with the Default Environments checkbox selected, click the OK button.



2. On Select Environments, double click on an Environment to select it.
3. Click the Close button.





4. On Control/System Replication, select the **Replication Setup** tab and select the following options to replicate information to remote locations:


| Field                                                               | Description                                                                                                                                                                                                                                                 |
|---------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Replicate Control Tables                                            | Select this checkbox to replicate all tables within the Control Tables data source. A new data source will be created for the remote location and the mappings for the remote environment will be activated to point to the new Control Tables data source. |
| Replicate Constant Tables - Object Librarian Object Use = 280       | Select this checkbox to replicate Constant Tables. A new data source will be created for the remote location and the mappings for the remote environment will be activated to point to the new Constant Tables data source.                                 |
| Replicate Master Tables - Object Librarian Object Use = 210 and 211 | Select this checkbox to replicate Master Tables. A new data source will be created for the remote location and the mappings for the remote environment will be activated to point to the new Master Tables data source.                                     |

---

**Caution:** Replication must be implemented using a third-party tool.

---

5. Select the Data Load tab.



6. On the **Data Load** tab, choose from the following options to copy selected tables to the remote locations:

| Field                | Description                                                                                                                                                                                                           |
|----------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Load Control Tables  | Select this checkbox to initially load the replicated Control Tables. The following version of R98403 will be launched to accomplish the task of copying Control tables from the base location to remote locations.   |
| Load Constant Tables | Select this checkbox to initially load the replicated Constant Tables. The following version of R98403 will be launched to accomplish the task of copying Constant tables from the base location to remote locations. |
| Load Master Tables   | Select this checkbox to initially load the replicated Master Tables. The following version of R98403 will be launched to accomplish the task of copying Master tables from the base location to remote locations.     |

**Note:** To edit or change the versions of the R98403 program that copy the control tables, constant tables, and master tables, click the Edit or Search buttons next to their respective versions.



---

**Note:** If you have defined multiple locations, the system will prompt you to complete sets of the Replication Setup and Data Load screens for each location.

---

7. Click OK.

## 19.13 Verifying Advanced Parameters

If you turned off Default Advanced Parameters on the Environment selection form, the Advanced Parameters form appears.

To verify advanced parameters:

1. On Advanced Parameters, complete these fields and turn on the following options:

| Field             | Description                                                          |
|-------------------|----------------------------------------------------------------------|
| Logic Data Source | Displays the server data source where the table conversions will run |

| Field                     | Description                                                                   |
|---------------------------|-------------------------------------------------------------------------------|
| Table Conversion Throttle | Displays the number of table conversions to be run concurrently on the server |

---

**Note:** The Table Conversion Workbench checks the maximum jobs for the default job queue for the logic server. It will only submit up to the number of maximum jobs on the queue to run at once. If the throttle is set higher than the queue, it uses the queue maximum number of jobs. If the queue is set higher than the throttle, it uses the throttle.

---


2. Click OK.

If you are not installing languages, you are prompted to enter data source information.

If you turned off Default Languages on the Select Environments selection form, continue with the next task.

## 19.14 Setting Up Data Sources for Environment

After specifying which tables to replicate, you can set up environment data sources.



1. On Data Source, click OK.

**Custom Installation Plan - [Data Source Revisions]**

File Edit Preferences Form Window Help

OK Cancel Dismiss Abort Links Advanced OLE Internet

Tools  
Form  
Advanced  
Port  
Database Sizing  
Default Sizing

Data Source Name: Business Data - PS910ATL

Data Source Use: DB Local Data Source

Data Source Type: O ORACLE ☐ JDBNET Data Source?

Data Class: B Business Data

Platform: NTSVR NT Server

Database Server Name: DENLCM17

SQL/88/M8DE ODBC SQL/M8DE OLEDB **Oracle** DB2 OS/400 DB2 UDB Access Logical

Object Owner ID: PS910DTA

Database Name (TNS): orcl

2. On Data Source Revisions, enter the data source name for the Business Data data source that will be used by the remote location. For example, **Business Data - PS910ATL**.
3. Complete the other fields as applicable for your database and platform.
4. Click the OK button.



**Custom Installation Plan - [Data Source Revisions]**

File Edit Preferences Form Window Help

OK Cancel Dismiss Apply Links Advanced OLE DB Internet

**Tools**  
Form  
Advanced  
Port  
Database Sizing  
Default Sizing

Data Source Name: Control Tables - PS910ATL

Data Source Use: DB Local Data Source

Data Source Type: O ORACLE ☐ JDBNET Data Source?

Data Class: T Control Tables

Platform: NTSVR NT Server


Database Server Name: DENLCM17

SQL/88E/M8DE ODBC SQL/M8DE OLEDB **Oracle** DB2 OS/400 DB2 UDB Access Logical

Object Owner ID: PS910CTL

Database Name (TNS): orcl


5. On Data Source Revisions, enter the data source name for the Control Tables data source that will be used by the remote location. For example, **Control Tables - PS910ATL**.
6. Complete the other fields as applicable for your database and platform.
7. Click the OK button.




- On Select Environments, click the Close button to exit the form.

## 19.15 Remote Location Packages

After you complete the data source setup for the environments, you can choose whether to push packages to a remote location.




- On Remote Location Packages, click the OK button.




2. On Remote Location Packages, click the Select button to choose the highlighted package.






3. On Remote Location Packages, verify that "Selected" is displayed in the "Selected" column.
4. Click the Close button.



5. On Location, click the No button to finalize the plan.



6. On the Information Prompt that indicates Installation Planner has concluded, click OK to exit the message box and initiate the Planner Validation Report.
  - If the processing option default was selected, Planner Validation Report automatically prompts you to run this report.
  - If the processing option default was not selected, click Validate on the tree view of your plan to initiate the Planner Validation Report.

## 19.16 Finalizing the Installation Plan


Installation Planner finalizes your installation plan automatically. The Information Prompt message appears to let you know that the installation plan is finalized.

When the plan is finalized:

- The status is set to 20. This value means that several adjustments to OCM mappings and tables were made according to your plan.
- The following tables are now updated:
  - Release Master table (F00945).
  - Path Code Master table (F00942).
  - Create OCM (F986101).
  - Package Plan table (F98404).
  - Machine Detail table (F9651).
  - Table Conversion Scheduler (F98405).
  - Language table (F984031) - if you are installing an alternate language.

## 19.17 Concluding the Planner Validation Report

To conclude the planner validation report:



1. On Report Output Destination, select On Screen or To Printer.
2. Click OK.

3. Review the report to confirm that all records were validated.

For more information about [Section 25.1, "Installation Planner Validation Report \(R9840B\)"](#), refer to [Chapter 25, "Working with Reports"](#).

4. On Work With Installation Plans, click Expand to review the plan you created.

*See Also*

- A separate chapter in this guide entitled: [Chapter 19, "Creating a Remote Installation Plan"](#)
- A separate chapter in this guide entitled: [Chapter 20, "Adding a Server to an Existing Configuration"](#)
- A separate chapter in this guide entitled: [Chapter 21, "Creating a Language-Only Installation Plan"](#)



---

## Adding a Server to an Existing Configuration

---

This section contains the procedures for adding additional servers to your configuration. Use these procedures only if you have already defined and run your initial installation plan and set up your environments.

This section discusses:

- [Section 20.1, "Assumptions about Adding a Server to an Existing Installation Plan"](#)
- [Section 20.2, "Starting Installation Planner"](#)
- [Section 20.3, "Entering a Plan Description"](#)
- [Section 20.4, "Entering a Plan Location"](#)
- [Section 20.5, "Selecting Additional Server Types"](#)
- [Section 20.6, "Entering Deployment Server Information"](#)
- [Section 20.7, "Specifying an Enterprise Server"](#)
- [Section 20.8, "Entering HTML Web Server Information"](#)
- [Section 20.9, "Entering Data Server Information"](#)
- [Section 20.10, "Entering Shared Data Source Information"](#)
- [Section 20.11, "Setting Up Environments"](#)
- [Section 20.12, "Setting Up Environment Data Sources"](#)
- [Section 20.13, "Finalizing the Installation Plan"](#)
- [Section 20.14, "Concluding the Validation Planner Report"](#)
- [Section 20.15, "Configuring Additional Servers"](#)

### 20.1 Assumptions about Adding a Server to an Existing Installation Plan

This table outlines assumptions for adding a server to an existing Installation Plan phase as a whole.

| Personnel    | Installer                                                                                                            |
|--------------|----------------------------------------------------------------------------------------------------------------------|
| Logon Status | On the Deployment Server, logged on as user JDE with the database password for user JDE, in the planner environment. |

| Personnel        | Installer                                                                                                                                                                                                                                                                                                                               |
|------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Prerequisites    | <p>Verify that the Deployment Server is installed and the Release 9.1 directory is shared.</p> <p>In order to run EnterpriseOne on an additional server, you must deploy JD Edwards EnterpriseOne to the server using either:</p> <ul style="list-style-type: none"> <li>■ Server Manager</li> <li>■ Platform Pack installer</li> </ul> |
| Concurrent Tasks | None.                                                                                                                                                                                                                                                                                                                                   |

## 20.2 Starting Installation Planner

**Caution:** In order to run EnterpriseOne on an additional server, you must deploy JD Edwards EnterpriseOne to the server using either:


- Server Manager
- Platform Pack installer

Begin your installation plan by logging on to Release 9.1 and starting Installation Planner.

To start the Installation Planner:

1. Log on to Release 9.1 as user JDE with the database password for user JDE.
2. Access the planner environment (JDEPLAN).
3. From the System Installation Tools menu (GH961), double-click Add-on Servers Plan.
4. On Work with Installation Plans, click Add.

Release 9.1 displays the following warning:



5. Click OK.

The Installation Planner form appears.

## 20.3 Entering a Plan Description

After starting Installation Planner, enter basic plan information, such as plan name and description.

To enter a plan description:

The screenshot shows the 'Typical Installation Plan - [Installation Planner]' window. The 'Plan Information' section is filled out as follows:

- Name:** INSTALL
- Description:** Install Plan
- Status:** 10 (In Planning)
- Install Type:** Install (selected), Upgrade, Software Update (ASU/ESU)
- Release:** To Release, E910

1. On Installation Planner, complete the following fields:

- *Name*  
Enter the name of your installation plan.
- *Description*  
Enter the description of your installation plan.
- *Status*  
Select 10 as the status of your installation plan.
- *To*  
Verify that the release number is E910.


2. Click OK.

The Location Search form appears.


## 20.4 Entering a Plan Location

Once basic plan installation information is entered, you must choose an existing plan location. For most instances, choose the location defined during your base installation.

To enter a plan location:



1. On Location Search, choose a location and click Select.




2. On Location Revisions, click OK.



## 20.5 Selecting Additional Server Types

Once a plan location is specified, specify the types of servers you want to add to your installation plan.

To select additional server types:



1. On Server Add, check the types of servers that you want to add to your configuration.

2. Click OK.

A Server Revisions form appears in the order listed on the Server Add form for each type of server that you chose.

3. Continue with the relevant sections that follow.

## 20.6 Entering Deployment Server Information

When choosing to add an additional Deployment Server to your plan, the Deployment Server Revisions form appears.

To enter Deployment Server information:

1. On Deployment Server Revisions, complete the following fields:

| Field        | Description                                                                                                                                                      |
|--------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Machine Name | Enter the name of your additional Deployment Server. The name is case sensitive, should not exceed 15 characters, and should not contain any special characters. |
| Description  | Enter a description of the machine.                                                                                                                              |
| Release      | Enter E910.                                                                                                                                                      |
| Location     | Displays the system-provided default value chosen for this plan.                                                                                                 |
| Primary User | This identifies the user to whom email is sent when a package is deployed. The default for Primary User is The default value for Primary User.                   |

2. On the Deployment tab, verify or complete the following fields:

| Field                     | Description                                                                                                                                                                                                      |
|---------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Primary Deployment Server | This field indicates the hierarchy of the servers. The default value for a secondary Deployment Server is 0.                                                                                                     |
| Server Share Path         | Enter the server share path where you installed Release 9.1 on your Deployment Server. Verify that this path matches your version of the release; for example, for Release 9.1, the server share path is \\E910. |

3. Click OK.

**Tip:** If you enter invalid information into a tab field, a stop sign icon appears next to the tab name, such as Deployment Server. For more information about the error, click on the stop sign icon in the bottom right-hand corner of the form.

4. You are prompted to add another Deployment Server.
  - To add another Deployment Server, click Yes.  
Repeat [Section 20.6, "Entering Deployment Server Information"](#).
  - To continue with the additional server plan, click No.  
Continue with the relevant sections that follow.

## 20.7 Specifying an Enterprise Server

This section discusses:

- [Section 20.7.1, "Entering Enterprise Server Information"](#)
- [Section 20.7.2, "Entering Enterprise Server Data Source Information"](#)

### 20.7.1 Entering Enterprise Server Information

To enter the base information for the Enterprise Server that you use in this plan:

The screenshot shows the 'Custom Installation Plan - [Enterprise Server Revisions]' window. It has a menu bar (File, Edit, Preferences, Form, Window, Help) and a toolbar with buttons like OK, Cancel, Dismiss, and Abort. A left sidebar contains a 'Tools' section and a 'Form' section with icons for 'Environ...', 'Generate Scripts', 'Generate Svr Map', 'OCM', 'Path Code', 'Data', and 'Foundat...'. The main area is divided into tabs: 'Workstation', 'Deployment', 'Enterprise' (selected), 'Data', 'HTML', 'Crystal', and 'CMS'. The 'Enterprise' tab contains the following fields:

- Machine Usage: 20
- Machine Name: Ent6
- Description: Enterprise Server iSeries
- Release: E910
- Host Type: 10 AS/400
- Location: Denver
- Primary User: JDE
- Port Number: 8016
- Logical Machine Name: ENT6
- Database Type: I DB2 UDB on OS/400
- Server Map Data Source: Ent6 - 910 Server Map
- Installation Path: E900SYS
- Deployment Server Name: TITANIC

1. On Enterprise Server Revisions, complete or verify the following fields:

| Field         | Description                                                                     |
|---------------|---------------------------------------------------------------------------------|
| Machine Usage | Displays the default value of 20 to indicate that this is an Enterprise Server. |

| Field        | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
|--------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Machine Name | <p>The name of the primary Enterprise Server. The name is case sensitive and should not contain any special characters.</p> <p>Because the machine name is used to create the Server Map datasource name, and because the Platform Pack Installer does not restrict you from entering a machine name that results in a datasource name greater than 30 characters; if the machine name for the Enterprise Server is longer than 13 characters, the resulting datasource name will be longer than the allowed 30 characters. For example, if your machine name is 15 characters (A23456789012345), the base datasource name input into the Planner would be: A23456789012345 - 910 Server Map.</p> <p><b>Note:</b> The field in table F98611 is a hard restriction; the field only allows 30 characters. The actual field size cannot be modified or changed.</p> <p>When the Planner runs it truncates the value to 30 characters because that is the restriction in the F98611 table. The Platform Pack does not truncate the value when it builds the <code>jde.ini</code> for the Enterprise Server. Therefore, any value greater than 30 characters will result in a mismatch between the <code>jde.ini</code> and the F98611 table. That is, using the previous example, the <code>jde.ini</code> would have the full length value A23456789012345 - 910 Server Map (which is 32 characters) while the F98611 populated by the Planner would have a value of A23456789012345 - 910 Server M.</p> <p>To remedy, you could do any one of the following:</p> <ul style="list-style-type: none"> <li>Manually modify values in table F98611 to match the truncated value in the <code>jde.ini</code> file.</li> <li>Ensure that the value is not truncated by limiting the datasource name to 30 characters (this would mean limiting the machine name for the Enterprise Server to 13 characters).</li> <li>Manually truncate the value in the F98611 table (for example, A23456789012345 - 910 Svr Map).</li> </ul> <p>In any case, you <b>must</b> ensure that the values for Server Map datasource names in the F98611 table exactly match those in the <code>jde.ini</code> file on the Enterprise Server.</p> |
| Description  | Enter a description of the machine.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| Release      | Enter the release number to which this plan applies, or use the visual assist button to choose one from the list, such as E910.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| Host Type    | Click the visual assist button and choose the type of Enterprise Server that you are adding to the plan, such as IBM i.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| Location     | Enter the default location chosen for this plan.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| Primary User | Enter the user to whom email is sent when a package is deployed. The default for Primary User is JDE.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |

2. On the Enterprise tab, complete these fields:

| Field                | Description                                                                                                                                                                          |
|----------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Port Number          | Displays the default value for this field, which is supplied the <code>jde.ini</code> . Change the port number for this Enterprise Server to a unique value, for example, 6016.      |
| Logical Machine Name | Displays the system-supplied default value when you enter the host type. The name is case sensitive, should not exceed 15 characters, and should not contain any special characters. |

| Field                  | Description                                                                                                                                                                                                                                                                                                              |
|------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Database Type          | Enter the type of database that you want to use for data sources on the Enterprise Server. Value is:<br><br>I is for IBM i Access                                                                                                                                                                                        |
| Server Map Data Source | Displays the system-supplied default value when you enter the host type.                                                                                                                                                                                                                                                 |
| Installation Path      | Verify that the default value is the installation directory path to which you want to install Release 9.1 on the Enterprise Server. Make sure the value is specific to your version of the release. For example, for Release 9.1 the default path is:<br><br>\JDEdwards\PPack\E910SYS<br><br>This is the system library. |
| Deployment Server Name | Using the visual assist button, choose the name of the Deployment Server to which this Enterprise Server is attached. The system provides a default value for this field, but you can change it.                                                                                                                         |

3. Click OK.

A message box appears prompting you to enter custom data sources or take the default data sources. Proceed to [Section 20.10, "Entering Shared Data Source Information"](#).

## 20.7.2 Entering Enterprise Server Data Source Information

After specifying Enterprise Server information, enter the data source information for the Enterprise Server you will use in this plan. The server data source holds the system configuration files that enable the server to run UBEs.

This section discusses:

- [Section 20.7.2.1, "Specifying Custom or Default Data Source Information"](#)
- [Section 20.7.2.2, "Verifying Custom Server Map Data Source Information"](#)
- [Section 20.7.2.3, "Adding another Enterprise Server"](#)


### 20.7.2.1 Specifying Custom or Default Data Source Information

You are prompted to enter custom data sources or take the default data sources for the Enterprise Server you just added. Choose one of the following options:

- To enter custom data sources, click OK.  
Skip to [Section 20.7.2.2, "Verifying Custom Server Map Data Source Information"](#).
- To accept default data sources, click Take Defaults.  
This option limits your customization choices.

### 20.7.2.2 Verifying Custom Server Map Data Source Information

To verify custom Server Map data source information:



1. On Data Source Revisions, verify your Server Map data source information.

**Tip:** Default data sources are configured as completely as possible. However, when you run Installation Planner, you might need to modify some data source information to reflect your system-specific configuration.

2. While defining your plan, some fields were changed to reflect the previous release values.

Change the following fields:

|                   |                                                                                                               |
|-------------------|---------------------------------------------------------------------------------------------------------------|
| Data Source Type  | Enter <i>I</i> for IBM i Access.                                                                              |
| Data Library Name | Enter <i>SVMrelease</i> , where <i>release</i> is the release to which you are installing, for example, E910. |

3. Click OK.

### 20.7.2.3 Adding another Enterprise Server


On the prompt to add another Enterprise Server, choose one of the following options:

- To add another Enterprise Server, click Yes.  
Repeat processes, starting with [Section 20.7.1, "Entering Enterprise Server Information"](#).
- To continue with Installation Planner setup, click No.  
The Machine\Server Types form appears.




## 20.8 Entering HTML Web Server Information

To enter HTML Web Server information:



1. On the HTML Application Server dialog, click OK to continue entering HTML Web Server information, or click Select to select an existing HTML Web Server.



2. On HTML Server Revisions, complete these fields:

| Field                | Description                                                                                                                                         |
|----------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>Machine Usage</i> | The default value of 30 indicates that this is a HTML Web Server.                                                                                   |
| <i>Machine Name</i>  | Enter the name of your HTML Web Server. The name is case sensitive, should not exceed 15 characters, and should not contain any special characters. |
| <i>Description</i>   | Enter a description of the HTML Web Server machine.                                                                                                 |
| <i>Release</i>       | Enter E910 to indicate the release number that you are installing.                                                                                  |

| Field               | Description                                                                                                                        |
|---------------------|------------------------------------------------------------------------------------------------------------------------------------|
| <i>Host Type</i>    | The default value of 50 specifies the server type as Intel NT. Select the correct server type.                                     |
| <i>Location</i>     | The location chosen for this plan appears in this field by default.                                                                |
| <i>Primary User</i> | The user to whom an email is sent when a package is deployed. The default for Primary User is listed in the <code>jde.ini</code> . |

3. On the HTML tab, complete these fields:


| Field                      | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
|----------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>Primary HTML Server</i> | When the system code generates an email message with a web shortcut pointing to a form, the web shortcut generated points to the "Primary" HTML Web Server. Only one of all the HTML Web Servers defined in installation planner can be defined as primary ("1").                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| <i>Protocol</i>            | This is the protocol used by the HTML Web Server. Valid values are <b>http</b> or <b>https</b> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| <i>Server URL</i>          | This is the Domain Name System (DNS) host name of the HTML Web Server.<br><br>For example: <code>www.oracle.com</code>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
| <i>HTTP Port</i>           | This is the port number the HTML Web Server is listening to.<br><br>For HTTP, the typical port number is 80.<br><br>For HTTPS, the typical port number is 443.<br><br><b>Note:</b> You can choose to implement a HTML Web Server using a different port number.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| <i>JDENET Listen Port</i>  | This is the port on which the JDENET communications protocol communicates with the JD Edwards EnterpriseOne Enterprise Server. The value is dependent on the release of JD Edwards EnterpriseOne.<br><br>For JD Edwards EnterpriseOne Release 9.1, the value is 6016.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
| <i>Default Login</i>       | Defines how shortcuts to a web form are generated by the system code. Values are either a reserved value or an explicit servlet name. Reserved values are: <ul style="list-style-type: none"> <li>■ <b>Standard</b><br/>The URL generated will point to a servlet on the Primary HTML Web Server.</li> <li>■ <b>Redirector</b><br/>The URL generated will point to redirector in the Primary HTML Web Server, and redirector will point to a servlet on another HTML Web Server for load balancing. The servlet name to use is generated by the system.</li> <li>■ <b>Explicit Servlet Name</b><br/>The user can specify an explicit servlet name in this field. In this case, the redirector functionality cannot be used. The URL generated will point to the specified servlet in the Primary HTML Web Server.<br/><br/>Usage of Explicit servlet name is for backward compatibility only. You should not use it unless you have a direct need.</li> </ul> |



| Field                    | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
|--------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>Installation Path</i> | <p>Enter the installation directory path to which you are installing Release 9.1 on your HTML Web Server. Make sure this is specific to your version of the release, and also the platform and application server on which your HTML Web Server is running.</p> <p>For default paths, refer to the applicable platform- and application server-dependent version of the <i>JD Edwards EnterpriseOne HTML Web Server Reference Guide</i> (WebLogic for Windows, WebLogic for UNIX, WebSphere for Windows, WebSphere for UNIX, WebSphere for IBM i). Otherwise, you must obtain this value from the HTML Web Server machine itself, or its administrator.</p> |

4. Click OK.
5. To add another HTML Web Server, click Yes and repeat steps 1 through 4 to define another HTML Web Server.

## 20.9 Entering Data Server Information



1. On Data Server, choose one of these options:
  - OK  
If your database resides on a separate server, choose click OK to continue entering unique Data Server information.
  - Select  
Click this option to select an existing Data Server.
  - Skip  
Click this option if you do not want to define a Data Server. Continue with the Planner using the environment selection in Step 6 of this task.

2. On Data Server Revisions, complete these fields:

| Field                | Description                                                                                                                                                                                                                                                                                                                                                     |
|----------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>Machine Usage</i> | The default value of 25 indicates that this is a Database Server.                                                                                                                                                                                                                                                                                               |
| <i>Machine Name</i>  | Enter the name of the Database Server where your central objects reside. If you are using the IBM i to store your central objects, enter the name of this server. The name is case sensitive, should not exceed 15 characters, and should not contain any special characters.                                                                                   |
| <i>Description</i>   | Enter a description of the Database Server machine.                                                                                                                                                                                                                                                                                                             |
| <i>Release</i>       | Enter the release number you are installing, for example, E910.                                                                                                                                                                                                                                                                                                 |
| <i>Host Type</i>     | <p>Select the type of Database Server that you are adding to the plan. Values are:</p> <ul style="list-style-type: none"> <li>■ 10 — IBM i</li> <li>■ 25 — Sun Solaris</li> <li>■ 30 — RS\6000</li> <li>■ 35 — Linux</li> <li>■ 50 — Microsoft Windows (Intel)</li> <li>■ 80 — Client - Microsoft Windows</li> <li>■ 90 — Client - Microsoft Windows</li> </ul> |
| <i>Location</i>      | The Installation Planner populates this field by default, based on previous selections.                                                                                                                                                                                                                                                                         |
| <i>Primary User</i>  | The user to whom an email is sent once a package is deployed. The default for Primary User is JDE.                                                                                                                                                                                                                                                              |

3. On the **Data** tab, complete the following field:

| Field                   | Description                                                                                                |
|-------------------------|------------------------------------------------------------------------------------------------------------|
| <i>Data Source Type</i> | Choose the type of data source. For example: <ul style="list-style-type: none"> <li>■ I - IBM i</li> </ul> |

4. Click OK.
5. To add another Data Server, click Yes and repeat steps 1 through 4 to define another Data Server.
6. On Data Source, click OK to continue entering unique shared data source information, or click Take Defaults to select the default data for the shared data sources.
7. On Location, select Yes to add another location, or click No to continue with Installation Planner.

## 20.10 Entering Shared Data Source Information

This section discusses:

- [Section 20.10.1, "Specifying \(Custom or Default\) Shared Data Source Setup Information"](#)
- [Section 20.10.2, "Verifying the Data Source for Data Dictionary"](#)
- [Section 20.10.3, "Verifying the Object Librarian Data Source"](#)
- [Section 20.10.4, "Verifying the OWJRNL Data Source"](#)
- [Section 20.10.5, "Verifying the System Data Source"](#)

### 20.10.1 Specifying (Custom or Default) Shared Data Source Setup Information

When you are prompted to enter the data source information for the shared data sources, to use the Release 9.1 data sources, click Take Defaults, or click OK to specifically enter the data source information.

#### See Also

For more information about System data source fields or fields for other data sources mentioned in this process, refer to Chapter 19, "Understanding Data Source Charts".

### 20.10.2 Verifying the Data Source for Data Dictionary

To verify the data source for Data Dictionary:

**Custom Installation Plan - [Data Source Revisions]**

File Edit Preferences Form Window Help

OK Cancel Dis... Help Links Advan... OLE ... Internet

**Data Source Name** Data Dictionary - 910

**Data Source Use** DB Local Data Source

**Data Source Type** I DB2 UDB on OS/400 ☐ JDBNET Data Source?

**Data Class** D Data Dictionary

**Platform** AS400 IBM AS/400 (CISC)

**Database Server Name** DS2

SQL/MSDE ODBC SQL/MSDE OLEDB Oracle **DB2 OS/400** DB2 UDB Access Logical

**Library Name** DD910

**ODBC Data Source Name** Data Dictionary - 910

1. On Data Source Revisions, verify the accuracy of the settings for the Data Dictionary data source.  
The library name in the Library Name field is the Release 9.1 data dictionary library (DD910).
2. Click OK.

### 20.10.3 Verifying the Object Librarian Data Source

To verify the Object Librarian data source:

**Custom Installation Plan - [Data Source Revisions]**

File Edit Preferences Form Window Help

OK Cancel Dis... Abort Links ▾ Advan... OLE ... Internet

Tools  
Form  
Advanced  
Port  
Database Sizing  
Default Sizing

Data Source Name: Object Librarian - 910

Data Source Use: DB Local Data Source

Data Source Type: DB2 UDB on OS/400 ☐ JDBNET Data Source?

Data Class: Object Librarian

Platform: AS400 IBM AS/400 (CISC)

Database Server Name: DS2

BQM/MSDE ODBC BQM/MSDE OLEDB Oracle **DB2 OS/400** DB2 UDB Access Logical


Library Name: OL910

ODBC Data Source Name: Object Librarian - 910

1. On Data Source Revisions, verify the accuracy of the settings for the Object Librarian data source.
2. Click OK.

## 20.10.4 Verifying the OWJRNL Data Source

To verify the OWJRNL data source:



1. On Data Source Revisions, verify the accuracy of the settings for the OWJRNL data source.
2. Click OK.

## 20.10.5 Verifying the System Data Source

To verify the System data source:

**Custom Installation Plan - [Data Source Revisions]**

File Edit Preferences Form Window Help

OK Cancel Dismiss Abort Links ▾ Advan... OLE ... Internet

**Data Source Name** System - 910

**Data Source Use** DB Local Data Source

**Data Source Type** I DB2 UDB on OS/400 ☐ JDBNET Data Source?

**Data Class** S System

**Platform** AS400 IBM AS/400 (CISC)

**Database Server Name** DS2

SQL/MSE ODBC SQL/MSE OLEDB Oracle **DB2 OS/400** DB2 UDB Access Logical

**Library Name** SY910

**ODBC Data Source Name** System - 910

1. On Data Source Revisions, verify the accuracy of the settings for the System data source.
2. Click OK.

The Environment Selection screen appears.

#### See Also


For more information about System data source fields or fields for other data sources mentioned in this process, refer to Chapter 19, "Understanding Data Source Charts".

## 20.11 Setting Up Environments

By default, Release 9.1 configures your system using values for typical environments. Depending on the options chosen when you set up your plan, Release 9.1 displays one or more of the following parameters, which you can customize in these tasks:

- Environments
- Data load options
- Advanced parameters
- Languages

You can customize any of these parameters by turning off the default option on the Environment Selection form. As you move through the plan, Release 9.1 displays a customization form for each parameter that you turn off.



1. On Environment Selection, clear the options for those parameters that you want to customize.

---

**Note:** The parameters that are available vary depending on the options that you selected at the beginning of the planning process.

---

2. Click OK.

---

**Note:** If you selected the default option for all parameters, skip to [Section 20.12, "Setting Up Environment Data Sources"](#).

---

Use the following tasks to customize each of the parameters listed above. Release 9.1 displays customization forms only for those parameters for which were cleared of the default options. Skip the tasks for those parameters that were selected.


3. Continue with the following relevant tasks:
  - [Section 20.11.1, "Selecting an Environment"](#)
  - [Section 20.11.2, "Specifying Environment Data Load Parameters"](#)
  - [Section 20.11.3, "Verifying Advanced Parameters"](#)
  - [Section 20.11.4, "Selecting Languages"](#)



## 20.11.1 Selecting an Environment

The Select Environment form appears. Environments prefixed with J are required for the HTML Web Server.

To select an environment:



On Select Environments, double-click the environment that you want to define.

To set up multiple environments, choose and define them one at a time. This screen appears after the following tasks are completed.

## 20.11.2 Specifying Environment Data Load Parameters

If you cleared Default Data Load on the Environment Selection form, the Data Load Parameters form appears.

To specify environment data load parameters:

The data load options are used when creating new tables (R98407) during an Upgrade. The option must be set to Load Production or Load Development in order to populate F9861 and F983051.

☐ Load Production Data ☒ Load DemoData

**Data Load Setup**

|                                                     |                                                  |                               |
|-----------------------------------------------------|--------------------------------------------------|-------------------------------|
| Environment                                         | <input type="text" value="PS910"/>               | E910 Pristine Environment     |
| Previous Environment                                | <input type="text"/>                             |                               |
| Plan Detail Status                                  | <input type="text" value="10"/>                  | In Planning                   |
| Program Name                                        | <input type="text" value="R98403"/>              | Environment Database Creation |
| Version                                             | <input type="text" value="XJDE0033"/>            | Express Install               |
| <input checked="" type="radio"/> Source Environment | <input type="text" value="JDEPLAN"/>             | Planner                       |
| <input type="radio"/> Source Data Source            | <input type="text" value="Business Data Local"/> |                               |

---

**Note:** The data load radio buttons on this form are no longer applicable as of JD Edwards EnterpriseOne Release 9.1 because data is automatically loaded by the Platform Pack Installer.

For additional details, refer to [Section 6.1.2, "Loading Data \(Demo Data and Production Data\)"](#).

---

### 20.11.3 Verifying Advanced Parameters

If you turned off Default Advanced Parameters on the Environment selection form, the Advanced Parameters form appears.

To verify advanced parameters:



**Custom Installation Plan - [Advanced Parameters]**

File Edit Preferences Form Window Help

OK Cancel Dismiss Abort Links Options OLE ... Internet

☒ Upgrade Environment

Plan Name: PRODUCTION

Library List Name: PD910 E910 Production Environment

Previous Environment: PD900 E900 Production Environment

Object Configuration Manager

☒ Recreate Object Mappings

Table / Specification

☒ Table Conversions

☒ Specification Merges

Control Table Merges

☐ None

☒ Upgrade Merges

TC Properties

Logic Data Source: DENUDBSN1

Table Conversion Throttle: 4

1. On **Advanced Parameters**, complete the following fields and turn on the following options:

| Field                     | Description                                                                   |
|---------------------------|-------------------------------------------------------------------------------|
| Logic Data Source         | Displays the server data source where the table conversions will run          |
| Table Conversion Throttle | Displays the number of table conversions to be run concurrently on the server |

**Note:** The Table Conversion Workbench checks the maximum jobs for the default job queue for the logic server. It will only submit up to the number of maximum jobs on the queue to run at once. If the throttle is set higher than the queue, it uses the queue maximum number of jobs. If the queue is set higher than the throttle, it uses the throttle.


2. Click OK.

If you are not installing languages, Release 9.1 prompts you for data source information. Skip to [Section 20.12, "Setting Up Environment Data Sources"](#).

If you turned off Default Languages on the **Select Environments** selection form, continue with [Selecting Languages](#).

## 20.11.4 Selecting Languages

To select languages:



1. On Language Selection, to set up a language for the selected environment, choose the appropriate language.
2. From the Row menu, click Select.
3. Repeat the above steps until all your languages have been selected.
4. Click OK.

**Tip:** *Customization Considerations.* If you have customizations that you do not want to merge, you can prevent individual conversions and merges from running by changing their status or deleting the appropriate records from the plan before you run the Installation Workbench.

## 20.12 Setting Up Environment Data Sources

Once the Environments have been set up, it is necessary to set up the data sources for those environments. If you created a custom environment, data source information is generated from the data source template provided with JD Edwards EnterpriseOne.

*See Also*

To modify this template, see the *JD Edwards EnterpriseOne Configurable Network Computing Implementation Guide*.

### 20.12.1 Selecting an Environment Data Source Setup Option

When you are prompted to set up data sources for the environment you just configured, click OK to manually enter the data sources, continue with the following task, or click Take Defaults to accept the Release 9.1 default data sources.

### 20.12.2 Setting Up the Data Source for Business Data

To set up the data source for business data:

The screenshot shows the 'Custom Installation Plan - [Data Source Revisions]' window. On the left is a 'Tools' sidebar with 'Form' selected. The main area contains the following fields:

- Data Source Name: Business Data - TEST
- Data Source Use: DB (Local Data Source)
- Data Source Type: I (DB2 UDB on OS/400)
- Data Class: B (Business Data)
- Platform: AS400 (IBM AS/400 (CISC))
- Database Server Name: DS2

Below these fields are tabs for different data source types: SQLMSDE ODBC, SQLMSDE OLEDB, Oracle, **DB2 OS/400**, DB2 UDB, Access, and Logical. The 'DB2 OS/400' tab is active, showing:

- Library Name: TESTDTA
- ODBC Data Source Name: Business Data - TEST

1. From the Form menu, click Advanced.

Verify the UNICODE flag is off. If your Business Data was not set to Unicode in a previous release and the data source had not yet been converted to Unicode, the Unicode flag must match the contents of the data source.



**Custom Installation Plan - [Advanced Parameters]**

File Edit Preferences Form Window Help

OK Cancel Dismiss Abort Links Options OLE Internet

☒ Upgrade Environment

Plan Name: PRODUCTION

Library List Name: PD910 E910 Production Environment

Previous Environment: PD900 E900 Production Environment

Object Configuration Manager

☒ Recreate Object Mappings

Table / Specification

☒ Table Conversions

☒ Specification Merges

Control Table Merges

☐ None

☒ Upgrade Merges

TC Properties

Logic Data Source: DENUDBSN1

Table Conversion Throttle: 4

2. Click OK.
3. On Data Source Revisions, verify the data source for your Business Data.  
Be sure this data source points either to the existing production data source you want to upgrade or to a copy of it.

---

**Note:** Business Data data sources are specific to the environment and pathcode.

---

4. When you ran Copy Plan, some fields were changed to reflect the previous release values. Change the following fields:


| Field               | Description                                                                                 |
|---------------------|---------------------------------------------------------------------------------------------|
| Data Source Type    | Enter <i>I</i> for IBM i Access.                                                            |
| IBM i Database Name | Type the name of the data source, such as Business Data - TEST) in the Database Name field. |

5. Click OK.


### 20.12.3 Setting Up the Data Source for Central Objects

You should change the data source if Central Objects are not on an IBM i machine.

To set up the data source for central objects:



1. On Data Source Revisions, verify the information for your Central Objects data source.  
Verify that your Central Objects data source is Central Objects - <Path Code>.
2. Click OK.




- On Advanced Set-Up, because the central objects data source must be Unicode, verify the **Unicode** setting is checked.

For IBM i, ensure the **AS/400 BLOB Support** setting is checked.

## 20.12.4 Setting Up the Data Source for Control Tables

To set up the data source for control tables:



- On Data Source Revisions, verify the accuracy of the Control Tables data source.

| Field                        | Description                                                                                                                                                                                                                                                                 |
|------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>Data Source Name</i>      | Verify the name of the data source.                                                                                                                                                                                                                                         |
| <i>Server Name</i>           | Verify the name of the Enterprise Server.<br><br><b>Caution:</b> When you defined your plan, some fields were changed to reflect the previous release values. Verify the value in Data Source Type field is appropriate for your database. Enter <b>I</b> for IBM i Access. |
| <i>Library Name</i>          | Enter the name of the library housing your Control Tables for the selected environment.                                                                                                                                                                                     |
| <i>ODBC Data Source Name</i> | Enter the name of the data source. For example, Control Tables - Test.                                                                                                                                                                                                      |

---

**Note:** Control Tables data sources are specific to the environment and pathcode.

---

- Click Advanced and verify that UNICODE is off only if the Control Tables are not set to Unicode in a previous release.



---


**Note:** If you upgrade from Release 8.9 the Unicode flag is on.

---

3. Click OK.

## 20.12.5 Verifying the Data Source for Versions

To verify the data source for versions:



1. On Data Source Revisions, verify the accuracy of the Versions data source.
2. Click OK.

---

**Note:** Versions data sources are specific to the pathcode, and the Unicode flag on the Advanced Form must be checked.

---

## 20.13 Finalizing the Installation Plan

Installation Planner finalizes your installation plan automatically. A message appears to let you know that the installation plan is finalized.

When the plan is finalized:

- The \JD Edwards\E910\hosts\hosttype\hostname directory is created on the Deployment Server. This contains the jde.ini and the configuration files used by the JD Edwards EnterpriseOne Platform Pack Installer.

---

**Note:** The JD Edwards EnterpriseOne Platform Pack Installer cannot be run until the Installation Plan is finalized.

---

- The status is set to 20, which signals that several adjustments to tables were made according to your plan.
- Create the OCM.
- Modify the jde.ini.
- The following tables are upgraded:
  - Release Master table (F00945)
  - Path Code Master table (F00942)
  - Package Plan table (F98404)
  - Machine Detail table (F9651)
  - Language table (F984031), if you are installing an alternate language

To finalize the installation plan:

1. Click OK to exit the concluding message box and initiate the Planner Validation Report.
  - If you chose the default processing option, Planner Validation Report automatically prompts you to run this report.
  - If you did not choose the default processing option, on the tree view of your plan, click Validate to initiate the Planner Validation Report.

## 20.14 Concluding the Validation Planner Report

To conclude the validation planner report:

1. On Report Output Destination, choose On Screen or To Printer, and then click OK.
2. Review the report to confirm that all records were validated.
3. After reviewing the report, on the Batch Versions form, click Close.

For more information about [Section 25.1, "Installation Planner Validation Report \(R9840B\)"](#), refer to [Section 25, "Working with Reports"](#).

4. On Work With Installation Plans, click Expand to review the plan that you created.
5. Run Installation Workbench for this installation plan.

For more information about Installation Workbench, refer to [Chapter 6, "Working With Installation Workbench"](#).

## 20.15 Configuring Additional Servers

To configure any additional servers that you have added:

1. Create server map Library (SVM910) on additional Enterprise Servers.
2. After configuring your database and server, use Installation Workbench to allocate and configure software and resources.

When using the Installation Workbench for adding servers, the Table Conversion and the Specification Merge workbenches do not appear because they are not needed.

3. When adding a server plan for a HTML Web Server, using the P9654A program, you must add all environments prefixed with J to the Enterprise Server and generate a Server Map data source.

---

## Creating a Language-Only Installation Plan

This section discusses:

- [Section 21.1, "Understanding Language-Only Installation Plans"](#)
- [Section 21.2, "Reviewing Requirements for a Language Installation"](#)
- [Section 21.3, "Installing Languages on the Deployment Server"](#)
- [Section 21.4, "Running Installation Planner"](#)
- [Section 21.6, "Running Installation Workbench"](#)
- [Section 21.7, "Verifying Enterprise Server Requirements"](#)
- [Section 21.8, "Verifying Workstation Requirements"](#)
- [Section 21.9, "Completing the Language Installation"](#)
- [Section 21.10, "Building and Deploying Alternate Language Packages"](#)

### 21.1 Understanding Language-Only Installation Plans

To make the language-only installation as easy and quick as possible, you should use the procedures in this chapter when installing an alternate language or multiple languages for the first time. These tasks will help you organize the pre-installation preparation required for a language-only installation:

- Install alternate languages at the same time that you install Release 9.1, or after completing a working upgrade .
- Implement a language-only plan only for installations in which a language has not been previously installed.

It is important that you complete all tasks in this chapter to achieve a successful language installation.

### 21.2 Reviewing Requirements for a Language Installation

To review the basic requirements for performing a language installation:

1. Review the language installation process.

The detailed information regarding the language installation process is found in [Section 1.6, "Language Process Overview"](#).

2. Review the disk space requirements.

Verify that the disk space requirements are available for each language and each environment that you are installing on the deployment and Enterprise Servers.


3. Review the directory structure.

The detailed information about directory structures is found in the [Chapter 23, "Understanding JD Edwards EnterpriseOne Directory Structures"](#) chapter of this guide.

## 21.3 Installing Languages on the Deployment Server


To install languages on the Deployment Server:

1. Obtain the JD Edwards EnterpriseOne language and run the `setup.exe`.




2. On JD Edwards Installation Manager, click the link for the language that you want to install.

In this example, the language installation image is for French.




3. On the Welcome screen, click Next.




4. On Client Workstation Installation Setup Type, complete these fields:

| Field             | Description                                                                                                                                                                                                                                                        |
|-------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Select Setup Type | Ensure the radio button for your language is selected.                                                                                                                                                                                                             |
| Install Path      | <p>The Installer provides a default path to the existing client installation on this machine:</p> <p>c:\JDEdwards\910</p> <p>You must verify that this drive and path is valid for your installation. You can use the browse function to locate the directory.</p> |

5. Click Finish.



The Client Workstation Install Progress displays the progress of the language installation.



When the installation finishes, the Oracle Deployment Server Setup form indicates whether the installation was successful.

6. On Installation Complete, click OK.

---

**Note:** To access more than one language within the same package, you need to build a custom package that includes all available languages.

---

## 21.4 Running Installation Planner

Once you have installed languages on the Deployment Server, run Installation Planner. These tasks highlight the critical language-related stages of this operation.

- [Section 21.4.1, "Accessing Installation Planner"](#)
- [Section 21.4.2, "Entering Information into Installation Planner"](#)
- [Section 21.4.3, "Selecting Custom or Default Parameters"](#)
- [Section 21.4.4, "Selecting an Environment"](#)

### 21.4.1 Accessing Installation Planner

For details on accessing the Installation Planner, refer to the chapter of this guide entitled: *Working with the Installation Planner*.

---

**Note:** If you choose a custom installation plan, you can choose which language to install for each environment. This section assumes you are defining a custom plan.

---

## 21.4.2 Entering Information into Installation Planner

To enter information into the Installation Planner:

The screenshot shows the 'Custom Installation Plan - [Installation Planner]' window. The 'Form' tab is active. The 'Plan Information' section contains the following fields:

- Name:** LANGUAGE ONLY
- Description:** Language only plan
- Status:** 10 (In Planning)

The 'Install Type' section has three radio buttons: ☒ Install, ☐ Upgrade, and ☐ Software Update (ASU/ESU).

The 'Release' section has a 'To Release' field with the value E910.


The 'Include Languages' section has three radio buttons: ☐ No, ☐ Yes, and ☒ Language Only.

1. On Installation Planner, enter the basic plan information.
2. In the Include Language area, select the Language Only option.

## 21.4.3 Selecting Custom or Default Parameters

To select custom or default parameters:






1. From Environment Selection, all environments and languages are the default values. Clear the options for Default Environment and Default Languages if you want to specify which language or languages to install for each environment.

## 21.4.4 Selecting an Environment

To select an environment:




Choose the environment for which you wish to install a language.

The Language Selection form appears.

## 21.5 Selecting a Language

To select a language:



1. On Language Selection, to set up a language for the selected environment, choose the appropriate language.
2. From the Row menu, click Select.
3. Repeat the above steps until all your languages have been selected.
4. Click OK.

## 21.6 Running Installation Workbench

After you create the language-only plan, you must run it through a series of workbenches in order to load the language tables to the appropriate data sources. The language installation process is the same for every database.

To run the Installation Workbench:

1. Go to [Chapter 6, "Working With Installation Workbench"](#).
2. Complete the procedures for Control Table Workbench and Specification Table Merge Workbenches.

The control tables, data dictionary, and central objects will be loaded by the Control Table Workbench and the Specification Table Merge Workbench.

## 21.7 Verifying Enterprise Server Requirements

To verify Enterprise Server requirements:

1. Verify that the Enterprise Server hardware and software meet all requirements.

2. Verify that the Enterprise Server disk space meets all requirements.
3. Verify that the `jde.ini` settings for local code set and code page values are set for your preferred language. These values are found in the National Language Support tables in [Section 1.6, "Language Process Overview"](#).

## 21.8 Verifying Workstation Requirements

To verify workstation requirements:

1. Verify that the workstation hardware and software meet all requirements.
2. Install the appropriate language character set to a workstation.
3. Complete the step to verify the JDE.INI settings on the Deployment Server for Interactive Runtime, Install, and Network Queues.
4. Complete the tasks in [Chapter 8, "Installing the Development Clients for Developers and System Administrators"](#).
5. Verify that the group and user profiles are set up properly.

## 21.9 Completing the Language Installation

Once you have verified that the Enterprise Server and workstation hardware and software meet your language install requirements, you can complete the installation.

See the *JD Edwards EnterpriseOne Tools Package Management Guide* for more information about how to transfer language specifications to the Enterprise Server.

## 21.10 Building and Deploying Alternate Language Packages

Once you have concluded the installation, it is time to build and deploy the alternate language packages. See *Package Build* in the *JD Edwards EnterpriseOne Tools Package Management Guide* for the details of including a language or creating language-only packages.


## FTP on the IBM i

This chapter provides instructions on setting up FTP on your IBM i Enterprise Server for JD Edwards EnterpriseOne. Using FTP is an alternate method to transfer the unwrapped .jar file from a Microsoft Windows-machine to the IBM i machine.

This chapter includes the following tasks:

- [Section 22.1, "Setting up FTP on the IBM i"](#)
- [Section 22.2, "Starting the FTP Server"](#)
- [Section 22.3, "Copying assembly.dat to the IBM i IFS Directory \(optional\)"](#)

### 22.1 Setting up FTP on the IBM i



1. Use the AS\400 Operations Navigator to open your IBM i machine node and navigate to Network > Servers > TCP\IP.
2. If the DDM server is not already started, you can manually start it using the Operations Navigator. In the right-hand pane of the Operations Navigator, in the Server Name column, highlight *DDM*, right-click, and choose Start.
3. Configure the FTP server. In the right-hand pane of the Operations Navigator, in the Server Name column, highlight the FTP server, right click, and choose Properties.
4. On FTP Properties, select the Initial Formats tab.
5. With the Initial Formats tab selected, ensure the following checkboxes are enabled:

| Checkbox            | Description               |
|---------------------|---------------------------|
| File naming format  | Path                      |
| Working directory   | Use user's home directory |
| File listing format | UNIX listing format       |

6. Click OK to save the changes and exit the FTP Properties.

## 22.2 Starting the FTP Server

1. Use the AS\400 Operations Navigator to open your IBM i machine node and navigate to Network > Servers > TCP\IP.
2. In the right-hand pane of the Operations Navigator, highlight *FTP*, right click, and choose Start.

## 22.3 Copying assembly.dat to the IBM i IFS Directory (optional)

If you are not able to copy the install image from your Windows client to your IBM i because the *assembly.dat* file is too large, alternatively you can use FTP to transfer that file into the IFS directory.

On the Microsoft Windows client where you ran the IBM i Wrapper install:

1. Start a command window (Run | cmd), then enter this command:

```
ftp machine_name
```

where *machine\_name* is the name of your IBM i machine.

Enter a valid IBM i user and password when prompted to do so.

2. To indicate you want to use the IFS instead of the standard file system on the IBM i, enter this command:

```
cd \
```

---

**Note:** This command specifies you want to put files into the IFS without changing any system settings on your IBM i, as would be the case if you entered a quote `site namefmt 1` command.

---

3. In Microsoft Windows Explorer, drill down to the *assembly.dat* file in your install image on the Microsoft Windows client.

For example, the assembly.dat file might be in a location similar to this:

```
d:\disk1\install\data\E910-3ffd45216a0d2fb17cd87deda05\9.1.000
```

4. In the command window type this command (but do not press Enter):

```
lcd
```

---

---

**Note:** Do not press Enter at this point. Continue with the steps below to finish populating the lcd command.

---

---

5. Drag the location of the assembly.dat from Microsoft Windows Explorer results from Step 3 into the command window to append the lcd command begun in Step 4, and then press Enter to execute the lcd command.

Your completed command will look similar to this:

```
lcd d:\disk1\install\data\E910-3ffd45216a0d2fb17cd87deda05\9.1.000
```

6. In the command window type this command (but do not press Enter):

```
cd
```

---

---

**Note:** Do not press Enter at this point. Continue with the steps below to finish populating the cd command.

---

---

7. In Microsoft Windows Explorer, copy the location of the assembly.dat on the Microsoft Windows box from the Address bar and paste the results to append the cd command.

Your completed command will look similar to this:

```
cd address_copied_from_Windows_Explorer
```

8. In the command window, enter this command:

```
bin
```

9. In the command window, enter this command:

```
put assembly.dat
```

10. Using Microsoft Windows Explorer, verify that the size and number of files match in the Microsoft Windows install image and the IBM i install image.





---

## Understanding JD Edwards EnterpriseOne Directory Structures

The charts in this section illustrate the directory structures for JD Edwards EnterpriseOne on the Deployment Server, the Enterprise Server, and Workstations. You must understand these directory structures to verify that you installed or upgraded Release 9.1 correctly.

Assuming you use the recommended shared path names, the process does not delete or overlay your previous release. You will have the Release 9.1 directories in addition to your existing directories.

The recommended configuration is for all business functions to be mapped to the server. The only exception to this rule is a client development environment in which case all business functions should be mapped locally.

This chapter discusses:

- [Section 23.1, "Deployment Server Directory Structure"](#)
- [Section 23.2, "Language Directory Structure"](#)
- [Section 23.3, "IBM i Libraries"](#)
- [Section 23.4, "Workstation General Directory Structure"](#)

### 23.1 Deployment Server Directory Structure

After you install Release 9.1 on the Deployment Server, you should have the following directory structure:

```
JDEdwardsE910\CD Templates
JDEdwardsE910\CD Templates\Esu & Asu
JDEdwardsE910\CD Templates\Esu & Asu\planner
JDEdwardsE910\CD Templates\Esu & Asu\planner\Package
JDEdwardsE910\CD Templates\Esu & Asu\planner\Package\PKGNAME
JDEdwardsE910\cfgtoollogs
JDEdwardsE910\cfgtoollogs\cfgfw
JDEdwardsE910\cfgtoollogs\oui
JDEdwardsE910\Change Assistant
JDEdwardsE910\Change Assistant\Downloads
JDEdwardsE910\Change Assistant\Downloads\CopiedESUs
JDEdwardsE910\Change Assistant\Downloads\ESUs
JDEdwardsE910\Change Assistant\Downloads\logs
JDEdwardsE910\Change Assistant\SupportAssistant
JDEdwardsE910\client
JDEdwardsE910\database
JDEdwardsE910\database\Oracle
```

```
JDEdwardsE910\database\SQL
JDEdwardsE910\database\UDB
JDEdwardsE910\diagnostics
JDEdwardsE910\diagnostics\config
JDEdwardsE910\diagnostics\config\registration
JDEdwardsE910\path_code
JDEdwardsE910\path_code\bin32
JDEdwardsE910\path_code\include
JDEdwardsE910\path_code\ini
JDEdwardsE910\path_code\ini\sbf
JDEdwardsE910\path_code\java
JDEdwardsE910\path_code\java\sbfjars
JDEdwardsE910\path_code\lib32
JDEdwardsE910\path_code\make
JDEdwardsE910\path_code\obj
JDEdwardsE910\path_code\PACKAGE
JDEdwardsE910\path_code\PACKAGE\DATA
JDEdwardsE910\path_code\PACKAGE\DATACOMP
JDEdwardsE910\path_code\PACKAGE\path_codeFA
JDEdwardsE910\path_code\PACKAGE\path_codeFA\bin32
JDEdwardsE910\path_code\PACKAGE\path_codeFA\include
JDEdwardsE910\path_code\PACKAGE\path_codeFA\java
JDEdwardsE910\path_code\PACKAGE\path_codeFA\java\sbfjars
JDEdwardsE910\path_code\PACKAGE\path_codeFA\lib32
JDEdwardsE910\path_code\PACKAGE\path_codeFA\make
JDEdwardsE910\path_code\PACKAGE\path_codeFA\obj
JDEdwardsE910\path_code\PACKAGE\path_codeFA\res
JDEdwardsE910\path_code\PACKAGE\path_codeFA\res\actionbmps
JDEdwardsE910\path_code\PACKAGE\path_codeFA\res\AVI Files
JDEdwardsE910\path_code\PACKAGE\path_codeFA\res\FormLines
JDEdwardsE910\path_code\PACKAGE\path_codeFA\res\Icons
JDEdwardsE910\path_code\PACKAGE\path_codeFA\res\images
JDEdwardsE910\path_code\PACKAGE\path_codeFA\res\treebmps
JDEdwardsE910\path_code\PACKAGE\path_codeFA\source
JDEdwardsE910\path_code\PACKAGE\path_codeFA\spec
JDEdwardsE910\path_code\PACKAGE\path_codeFA\spec\runtimeCache
JDEdwardsE910\path_code\PACKAGE\path_codeFA\work
JDEdwardsE910\path_code\PACKAGE\path_codeFA\work\sbf
JDEdwardsE910\path_code\PACKAGE\path_codeFA\work\sbf\oas
JDEdwardsE910\path_code\PACKAGE\path_codeFA\work\sbf\oas\META-INF
JDEdwardsE910\path_code\res
JDEdwardsE910\path_code\res\actionbmps
JDEdwardsE910\path_code\res\AVI Files
JDEdwardsE910\path_code\res\FormLines
JDEdwardsE910\path_code\res\Icons
JDEdwardsE910\path_code\res\images
JDEdwardsE910\path_code\res\treebmps
JDEdwardsE910\path_code\source
JDEdwardsE910\path_code\spec
JDEdwardsE910\path_code\spec\runtimeCache
JDEdwardsE910\path_code\work
JDEdwardsE910\path_code\work\sbf
JDEdwardsE910\path_code\work\sbf\oas
JDEdwardsE910\path_code\work\sbf\oas\META-INF
```

---

**Note:** In the preceding paths, the path\_code portion is DV910, PD910, PS910, or PY910.

---

---

**Note:** The PACKAGE\path\_code directory contains the same sub-structure as this parent directory:

JDEdwardsE910\path\_code

---

```
JDEdwardsE910\E1InstallerLibs
JDEdwardsE910\install
JDEdwardsE910\inventory
JDEdwardsE910\inventory\Actions21
JDEdwardsE910\inventory\Actions21\e1FileActions
JDEdwardsE910\inventory\Actions21\e1FileActions\10.2.0.3.0
JDEdwardsE910\inventory\Actions21\e1GeneralActions
JDEdwardsE910\inventory\Actions21\e1FileActions\10.2.0.3.0
JDEdwardsE910\inventory\Actions21\e1PackageActions
JDEdwardsE910\inventory\Actions21\e1PackageActions\10.2.0.3.0
JDEdwardsE910\inventory\Actions21\fileActions
JDEdwardsE910\inventory\Actions21\fileActions\11.2.0.2.0
JDEdwardsE910\inventory\Actions21\generalActions
JDEdwardsE910\inventory\Actions21\generalActions\10.2.0.9.0
JDEdwardsE910\inventory\Actions21\ntServicesActions
JDEdwardsE910\inventory\Actions21\ntServicesActions\10.2.0.6.0
JDEdwardsE910\inventory\Actions21\ntw32FoldersActions
JDEdwardsE910\inventory\Actions21\ntw32FoldersActions\10.2.0.3.0
JDEdwardsE910\inventory\Actions21\SpawnActions
JDEdwardsE910\inventory\Actions21\SpawnActions\10.1.0.3.4
JDEdwardsE910\inventory\Actions21\w32RegActions
JDEdwardsE910\inventory\Actions21\w32RegActions\10.2.0.1.0
JDEdwardsE910\inventory\backup
JDEdwardsE910\inventory\checkpoints
JDEdwardsE910\inventory\Clone
JDEdwardsE910\inventory\Components21
JDEdwardsE910\inventory\Components21\com.e1.bpm
JDEdwardsE910\inventory\Components21\com.e1.bpm\1.0.0.0.0
JDEdwardsE910\inventory\Components21\com.e1.bpm\1.0.0.0.0\resources
JDEdwardsE910\inventory\Components21\com.e1.deployment.data
JDEdwardsE910\inventory\Components21\com.e1.deployment.data\1.0.0.0.0
JDEdwardsE910\inventory\Components21\com.e1.deployment.data\1.0.0.0.0\resources
JDEdwardsE910\inventory\Components21\com.e1.deployment.development
JDEdwardsE910\inventory\Components21\com.e1.deployment.development\9.1.0.0.0
JDEdwardsE910\inventory\Components21\com.e1.deployment.development\9.1.0.0.0\resources
JDEdwardsE910\inventory\Components21\com.e1.deployment.e1files
JDEdwardsE910\inventory\Components21\com.e1.deployment.e1files\9.1.0.0.0
JDEdwardsE910\inventory\Components21\com.e1.deployment.e1files\9.1.0.0.0\resources
JDEdwardsE910\inventory\Components21\com.e1.deployment.oh4a
JDEdwardsE910\inventory\Components21\com.e1.deployment.oh4a\1.0.0.0.0
JDEdwardsE910\inventory\Components21\com.e1.deployment.oh4a\1.0.0.0.0\resources
JDEdwardsE910\inventory\Components21\com.e1.deployment.planner
JDEdwardsE910\inventory\Components21\com.e1.deployment.planner\9.1.0.0.0
JDEdwardsE910\inventory\Components21\com.e1.deployment.planner\9.1.0.0.0\resources
JDEdwardsE910\inventory\Components21\com.e1.deployment.top
JDEdwardsE910\inventory\Components21\com.e1.deployment.top\9.1.0.0.0
JDEdwardsE910\inventory\Components21\com.e1.deployment.top\9.1.0.0.0\resources
JDEdwardsE910\inventory\Components21\com.e1.features
JDEdwardsE910\inventory\Components21\com.e1.features\1.0.0.0.0
JDEdwardsE910\inventory\Components21\com.e1.features\1.0.0.0.0\resources
JDEdwardsE910\inventory\Components21\com.e1.foundation
JDEdwardsE910\inventory\Components21\com.e1.foundation\1.0.0.0.0
JDEdwardsE910\inventory\Components21\com.e1.foundation\1.0.0.0.0\resources
```

```
JDEdwardsE910\inventory\Components21\oracle.jdk
JDEdwardsE910\inventory\Components21\oracle.jdk\1.6.0.21.51
JDEdwardsE910\inventory\Components21\oracle.jdk\1.6.0.21.51\resources
JDEdwardsE910\inventory\Components21\oracle.swd.opatch
JDEdwardsE910\inventory\Components21\oracle.swd.opatch\11.2.0.0.2
JDEdwardsE910\inventory\Components21\oracle.swd.opatch\11.2.0.0.2\resources
JDEdwardsE910\inventory\Components21\oracle.swd.oui
JDEdwardsE910\inventory\Components21\oracle.swd.oui\11.2.0.2.0
JDEdwardsE910\inventory\Components21\oracle.swd.oui\11.2.0.2.0\resources
JDEdwardsE910\inventory\Components21\oracle.swd.oui.core
JDEdwardsE910\inventory\Components21\oracle.swd.oui.core\11.2.0.2.0
JDEdwardsE910\inventory\Components21\oracle.swd.oui.core\11.2.0.2.0\resources
JDEdwardsE910\inventory\ContentsXML
JDEdwardsE910\inventory\ContentsXML\ConfigXML
JDEdwardsE910\inventory\Dialogs21
JDEdwardsE910\inventory\Dialogs21\standardDialogs
JDEdwardsE910\inventory\Dialogs21\standardDialogs\10.2.0.1.0
JDEdwardsE910\inventory\Queries21
JDEdwardsE910\inventory\Queries21\areasQueries
JDEdwardsE910\inventory\Queries21\areasQueries\10.2.0.1.0
JDEdwardsE910\inventory\Queries21\e1DBQueries
JDEdwardsE910\inventory\Queries21\e1DBQueries\10.2.0.3.0
JDEdwardsE910\inventory\Queries21\e1FileQueries
JDEdwardsE910\inventory\Queries21\e1FileQueries\10.2.0.3.0
JDEdwardsE910\inventory\Queries21\e1GeneralQueries
JDEdwardsE910\inventory\Queries21\e1GeneralQueries\10.2.0.3.0
JDEdwardsE910\inventory\Queries21\e1PackageQueries
JDEdwardsE910\inventory\Queries21\e1PackageQueries\10.2.0.3.0
JDEdwardsE910\inventory\Queries21\fileQueries
JDEdwardsE910\inventory\Queries21\fileQueries\10.1.0.3.0
JDEdwardsE910\inventory\Queries21\generalQueries
JDEdwardsE910\inventory\Queries21\generalQueries\10.2.0.2.0
JDEdwardsE910\inventory\Queries21\w32RegQueries
JDEdwardsE910\inventory\Queries21\w32RegQueries\10.2.0.1.0
JDEdwardsE910\inventory\Queries21\WindowsGeneralQueries
JDEdwardsE910\inventory\Queries21\WindowsGeneralQueries\10.2.0.1.0
JDEdwardsE910\inventory\Scripts
JDEdwardsE910\inventory\Scripts\ext
JDEdwardsE910\inventory\Scripts\ext\jlib
JDEdwardsE910\inventory\Scripts\ext\lib
JDEdwardsE910\inventory\Templates
JDEdwardsE910\inventory\Templates\OPatch
JDEdwardsE910\inventory\Templates\oui
JDEdwardsE910\inventory\Templates\oui\bin
JDEdwardsE910\inventory\Templates\system
JDEdwardsE910\inventory\Templates\system\OC4J
JDEdwardsE910\inventory\Templates\system\OC4J\j2ee
JDEdwardsE910\inventory\Templates\system\OC4J\j2ee\home
JDEdwardsE910\inventory\Templates\system\OC4J\j2ee\home\applications
JDEdwardsE910\inventory\Templates\system\OC4J\j2ee\home\applications\webclient.ear
JDEdwardsE910\inventory\Templates\system\OC4J\j2ee\home\applications\webclient.ear
\webclient
JDEdwardsE910\inventory\Templates\system\OC4J\j2ee\home\applications\webclient.ear
\webclient\WEB-INF
JDEdwardsE910\inventory\Templates\system\OC4J\j2ee\home\applications\webclient.ear
\webclient\WEB-INF\classes
JDEdwardsE910\jdk
JDEdwardsE910\jdk\bin
JDEdwardsE910\jdk\include
JDEdwardsE910\jdk\include\win32
```

```
JDEdwardsE910\jdk\jre
JDEdwardsE910\jdk\jre\bin
JDEdwardsE910\jdk\jre\bin\client
JDEdwardsE910\jdk\jre\bin\new_plugin
JDEdwardsE910\jdk\jre\bin\server
JDEdwardsE910\jdk\jre\lib
JDEdwardsE910\jdk\jre\lib\applet
JDEdwardsE910\jdk\jre\lib\audio
JDEdwardsE910\jdk\jre\lib\cmm
JDEdwardsE910\jdk\jre\lib\deploy
JDEdwardsE910\jdk\jre\lib\deploy\jqs
JDEdwardsE910\jdk\jre\lib\deploy\jqs\ff
JDEdwardsE910\jdk\jre\lib\deploy\jqs\ff\chrome
JDEdwardsE910\jdk\jre\lib\deploy\jqs\ff\chrome\content
JDEdwardsE910\jdk\jre\lib\deploy\jqs\ie
JDEdwardsE910\jdk\jre\lib\ext
JDEdwardsE910\jdk\jre\lib\fonts
JDEdwardsE910\jdk\jre\lib\i386
JDEdwardsE910\jdk\jre\lib\im
JDEdwardsE910\jdk\jre\lib\images
JDEdwardsE910\jdk\jre\lib\images\cursors
JDEdwardsE910\jdk\jre\lib\management
JDEdwardsE910\jdk\jre\lib\security
JDEdwardsE910\jdk\jre\lib\servicetag
JDEdwardsE910\jdk\jre\lib\zi
JDEdwardsE910\jdk\jre\lib\zi\Africa
JDEdwardsE910\jdk\jre\lib\zi\America
JDEdwardsE910\jdk\jre\lib\zi\America\Argentina
JDEdwardsE910\jdk\jre\lib\zi\America\Indiana
JDEdwardsE910\jdk\jre\lib\zi\America\Kentucky
JDEdwardsE910\jdk\jre\lib\zi\America\North_Dakota
JDEdwardsE910\jdk\jre\lib\zi\Antarctica
JDEdwardsE910\jdk\jre\lib\zi\Asia
JDEdwardsE910\jdk\jre\lib\zi\Atlantic
JDEdwardsE910\jdk\jre\lib\zi\Australia
JDEdwardsE910\jdk\jre\lib\zi\Etc
JDEdwardsE910\jdk\jre\lib\zi\Europe
JDEdwardsE910\jdk\jre\lib\zi\Indian
JDEdwardsE910\jdk\jre\lib\zi\Pacific
JDEdwardsE910\jdk\jre\lib\zi\SystemV
JDEdwardsE910\jdk\lib
JDEdwardsE910\jdk\lib\visualvm
JDEdwardsE910\jdk\lib\visualvm\etc
JDEdwardsE910\jdk\lib\visualvm\platform11
JDEdwardsE910\jdk\lib\visualvm\platform11\config
JDEdwardsE910\jdk\lib\visualvm\platform11\config\ModuleAutoDeps
JDEdwardsE910\jdk\lib\visualvm\platform11\config\Modules
JDEdwardsE910\jdk\lib\visualvm\platform11\core
JDEdwardsE910\jdk\lib\visualvm\platform11\core\locale
JDEdwardsE910\jdk\lib\visualvm\platform11\docs
JDEdwardsE910\jdk\lib\visualvm\platform11\lib
JDEdwardsE910\jdk\lib\visualvm\platform11\lib\locale
JDEdwardsE910\jdk\lib\visualvm\platform11\modules
JDEdwardsE910\jdk\lib\visualvm\platform11\modules\ext
JDEdwardsE910\jdk\lib\visualvm\platform11\modules\ext\locale
JDEdwardsE910\jdk\lib\visualvm\platform11\modules\locale
JDEdwardsE910\jdk\lib\visualvm\platform11\update_tracking
JDEdwardsE910\jdk\lib\visualvm\profiler3
JDEdwardsE910\jdk\lib\visualvm\profiler3\config
JDEdwardsE910\jdk\lib\visualvm\profiler3\config\Modules
```

```

JDEdwardsE910\jdk\lib\visualvm\profiler3\lib
JDEdwardsE910\jdk\lib\visualvm\profiler3\lib\deployed
JDEdwardsE910\jdk\lib\visualvm\profiler3\lib\deployed\jdk15
JDEdwardsE910\jdk\lib\visualvm\profiler3\lib\deployed\jdk15\windows
JDEdwardsE910\jdk\lib\visualvm\profiler3\lib\deployed\jdk16
JDEdwardsE910\jdk\lib\visualvm\profiler3\lib\deployed\jdk16\windows
JDEdwardsE910\jdk\lib\visualvm\profiler3\lib\locale
JDEdwardsE910\jdk\lib\visualvm\profiler3\modules
JDEdwardsE910\jdk\lib\visualvm\profiler3\modules\locale
JDEdwardsE910\jdk\lib\visualvm\profiler3\update_tracking
JDEdwardsE910\jdk\lib\visualvm\visualvm
JDEdwardsE910\jdk\lib\visualvm\visualvm\config
JDEdwardsE910\jdk\lib\visualvm\visualvm\config\Modules
JDEdwardsE910\jdk\lib\visualvm\visualvm\core
JDEdwardsE910\jdk\lib\visualvm\visualvm\core\locale
JDEdwardsE910\jdk\lib\visualvm\visualvm\modules
JDEdwardsE910\jdk\lib\visualvm\visualvm\modules\locale
JDEdwardsE910\jdk\lib\visualvm\visualvm\update_tracking
JDEdwardsE910\mediaobj
JDEdwardsE910\mediaobj\Composer
JDEdwardsE910\mediaobj\Composer\html
JDEdwardsE910\mediaobj\Composer\html\Images
JDEdwardsE910\mediaobj\Composer\Visio
JDEdwardsE910\mediaobj\ComposerCBT
JDEdwardsE910\mediaobj\ComposerCBT\Order_to_Cash
JDEdwardsE910\mediaobj\ComposerCBT\Procure_to_Pay
JDEdwardsE910\mediaobj\ComposerCBT>ShowMe_Eapxxxxx
JDEdwardsE910\mediaobj\ComposerCBT>ShowMe_Eapxxxxx\graphics
JDEdwardsE910\mediaobj\ComposerCBT>ShowMe_Earxxxxx
JDEdwardsE910\mediaobj\ComposerCBT>ShowMe_Earxxxxx\graphics
JDEdwardsE910\mediaobj\ComposerCBT>ShowMe_Ecoxxxxx
JDEdwardsE910\mediaobj\ComposerCBT>ShowMe_Ecoxxxxx\graphics
JDEdwardsE910\mediaobj\ComposerCBT\Standard_Graphics
JDEdwardsE910\mediaobj\Distribution
JDEdwardsE910\mediaobj\Financials
JDEdwardsE910\mediaobj\htmlupload
JDEdwardsE910\mediaobj\Human Resources
JDEdwardsE910\mediaobj\Manufacturing
JDEdwardsE910\mediaobj\MISC
JDEdwardsE910\mediaobj\Misc Animations
JDEdwardsE910\mediaobj\Misc Images
JDEdwardsE910\mediaobj\Oleque
JDEdwardsE910\mediaobj\OMW
JDEdwardsE910\mediaobj\SelfService
JDEdwardsE910\mediaobj\Text
JDEdwardsE910\MISC
JDEdwardsE910\OneWorld Client Install
JDEdwardsE910\OneWorld Client Install\install
JDEdwardsE910\OneWorld Client Install\install\access
JDEdwardsE910\OneWorld Client Install\install\access\jdk
JDEdwardsE910\OneWorld Client Install\install\access\jdk\jre
JDEdwardsE910\OneWorld Client Install\install\access\jdk\jre\bin
JDEdwardsE910\OneWorld Client Install\install\access\jdk\jre\lib
JDEdwardsE910\OneWorld Client Install\install\access\jdk\jre\lib\ext
JDEdwardsE910\OneWorld Client Install\install\resource
JDEdwardsE910\OneWorld Client Install\Misc
JDEdwardsE910\OneWorld Client Install\Misc\SBFServer
JDEdwardsE910\OneWorld Client Install\Stage
JDEdwardsE910\OneWorld Client Install\Stage\Actions
JDEdwardsE910\OneWorld Client Install\Stage\Actions\dbActions

```

```

JDEdwardsE910\OneWorld Client Install\Stage\Actions\dbActions\10.1.0.2.0
JDEdwardsE910\OneWorld Client Install\Stage\Actions\dbActions\10.1.0.2.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Actions\e1FileActions
JDEdwardsE910\OneWorld Client Install\Stage\Actions\e1FileActions\10.2.0.3.0
JDEdwardsE910\OneWorld Client Install\Stage\Actions\e1FileActions\10.2.0.3.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Actions\e1GeneralActions
JDEdwardsE910\OneWorld Client Install\Stage\Actions\e1GeneralActions\10.2.0.3.0
JDEdwardsE910\OneWorld Client Install\Stage\Actions\e1GeneralActions\10.2.0.3.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Actions\e1ISeriesActions
JDEdwardsE910\OneWorld Client Install\Stage\Actions\e1ISeriesActions\10.2.0.3.0
JDEdwardsE910\OneWorld Client Install\Stage\Actions\e1ISeriesActions\10.2.0.3.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Actions\e1PackageActions
JDEdwardsE910\OneWorld Client Install\Stage\Actions\e1PackageActions\10.2.0.3.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Actions\fileActions
JDEdwardsE910\OneWorld Client Install\Stage\Actions\fileActions\11.2.0.2.0
JDEdwardsE910\OneWorld Client Install\Stage\Actions\fileActions\11.2.0.2.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Actions\generalActions
JDEdwardsE910\OneWorld Client Install\Stage\Actions\generalActions\10.2.0.9.0
JDEdwardsE910\OneWorld Client Install\Stage\Actions\generalActions\10.2.0.9.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Actions\jarActions
JDEdwardsE910\OneWorld Client Install\Stage\Actions\jarActions\10.2.0.0.0
JDEdwardsE910\OneWorld Client Install\Stage\Actions\jarActions\10.2.0.0.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Actions\launchPadActions
JDEdwardsE910\OneWorld Client Install\Stage\Actions\launchPadActions\10.1.0.2.0
JDEdwardsE910\OneWorld Client Install\Stage\Actions\launchPadActions\10.1.0.2.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Actions\ntServicesActions
JDEdwardsE910\OneWorld Client Install\Stage\Actions\ntServicesActions\10.2.0.6.0
JDEdwardsE910\OneWorld Client Install\Stage\Actions\ntServicesActions\10.2.0.6.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Actions\ntw32FoldersActions
JDEdwardsE910\OneWorld Client Install\Stage\Actions\ntw32FoldersActions\10.2.0.3.0
JDEdwardsE910\OneWorld Client
Install\Stage\Actions\ntw32FoldersActions\10.2.0.3.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Actions\rgsActions
JDEdwardsE910\OneWorld Client Install\Stage\Actions\rgsActions\10.1.0.3.0
JDEdwardsE910\OneWorld Client Install\Stage\Actions\rgsActions\10.1.0.3.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Actions\SpawnActions
JDEdwardsE910\OneWorld Client Install\Stage\Actions\SpawnActions\10.1.0.3.4
JDEdwardsE910\OneWorld Client Install\Stage\Actions\SpawnActions\10.1.0.3.4\1
JDEdwardsE910\OneWorld Client Install\Stage\Actions\unixActions
JDEdwardsE910\OneWorld Client Install\Stage\Actions\unixActions\10.2.0.3.0
JDEdwardsE910\OneWorld Client Install\Stage\Actions\unixActions\10.2.0.3.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Actions\w32OcxRegActions
JDEdwardsE910\OneWorld Client Install\Stage\Actions\w32OcxRegActions\10.2.0.1.0
JDEdwardsE910\OneWorld Client Install\Stage\Actions\w32OcxRegActions\10.2.0.1.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Actions\w32RegActions
JDEdwardsE910\OneWorld Client Install\Stage\Actions\w32RegActions\10.2.0.1.0
JDEdwardsE910\OneWorld Client Install\Stage\Actions\w32RegActions\10.2.0.1.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Actions\wingeneralActions
JDEdwardsE910\OneWorld Client Install\Stage\Actions\wingeneralActions\10.2.0.1.0
JDEdwardsE910\OneWorld Client Install\Stage\Actions\wingeneralActions\10.2.0.1.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Components
JDEdwardsE910\OneWorld Client Install\Stage\Components\com.e1.devclient.top
JDEdwardsE910\OneWorld Client
Install\Stage\Components\com.e1.devclient.top\1.0.0.0.0
JDEdwardsE910\OneWorld Client
Install\Stage\Components\com.e1.devclient.top\1.0.0.0.0\1
JDEdwardsE910\OneWorld Client
Install\Stage\Components\com.e1.devclient.top\1.0.0.0.0\1\DataFiles
JDEdwardsE910\OneWorld Client Install\Stage\Components\oracle.jdk
JDEdwardsE910\OneWorld Client Install\Stage\Components\oracle.jdk\1.6.0.21.51

```

```
JDEdwardsE910\OneWorld Client Install\Stage\Components\oracle.jdk\1.6.0.21.51\1
JDEdwardsE910\OneWorld Client
Install\Stage\Components\oracle.jdk\1.6.0.21.51\1\DataFiles
JDEdwardsE910\OneWorld Client Install\Stage\Components\oracle.swd.jre
JDEdwardsE910\OneWorld Client Install\Stage\Components\oracle.swd.jre\1.5.0.11.0
JDEdwardsE910\OneWorld Client Install\Stage\Components\oracle.swd.jre\1.5.0.11.0\1
JDEdwardsE910\OneWorld Client
Install\Stage\Components\oracle.swd.jre\1.5.0.11.0\1\DataFiles
JDEdwardsE910\OneWorld Client Install\Stage\Components\oracle.swd.opatch
JDEdwardsE910\OneWorld Client
Install\Stage\Components\oracle.swd.opatch\11.2.0.0.2
JDEdwardsE910\OneWorld Client
Install\Stage\Components\oracle.swd.opatch\11.2.0.0.2\1
JDEdwardsE910\OneWorld Client
Install\Stage\Components\oracle.swd.opatch\11.2.0.0.2\1\DataFiles
JDEdwardsE910\OneWorld Client Install\Stage\Components\oracle.swd.oui
JDEdwardsE910\OneWorld Client Install\Stage\Components\oracle.swd.oui\11.2.0.2.0
JDEdwardsE910\OneWorld Client Install\Stage\Components\oracle.swd.oui\11.2.0.2.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Components\oracle.swd.oui.core
JDEdwardsE910\OneWorld Client
Install\Stage\Components\oracle.swd.oui.core\11.2.0.2.0
JDEdwardsE910\OneWorld Client
Install\Stage\Components\oracle.swd.oui.core\11.2.0.2.0\1
JDEdwardsE910\OneWorld Client
Install\Stage\Components\oracle.swd.oui.core\11.2.0.2.0\1\DataFiles
JDEdwardsE910\OneWorld Client Install\Stage\Dialogs
JDEdwardsE910\OneWorld Client Install\Stage\Dialogs\e1Dialogs
JDEdwardsE910\OneWorld Client Install\Stage\Dialogs\e1Dialogs\10.2.0.1.0
JDEdwardsE910\OneWorld Client Install\Stage\Dialogs\e1Dialogs\10.2.0.1.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Dialogs\standardDialogs
JDEdwardsE910\OneWorld Client Install\Stage\Dialogs\standardDialogs\10.2.0.1.0
JDEdwardsE910\OneWorld Client Install\Stage\Dialogs\standardDialogs\10.2.0.1.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Disk1
JDEdwardsE910\OneWorld Client Install\Stage\Disk1\stage
JDEdwardsE910\OneWorld Client Install\Stage\ext
JDEdwardsE910\OneWorld Client Install\Stage\ext\jlib
JDEdwardsE910\OneWorld Client Install\Stage\ext\lib
JDEdwardsE910\OneWorld Client Install\Stage\globalvariables
JDEdwardsE910\OneWorld Client Install\Stage\Queries
JDEdwardsE910\OneWorld Client Install\Stage\Queries\areasQueries
JDEdwardsE910\OneWorld Client Install\Stage\Queries\areasQueries\10.2.0.1.0
JDEdwardsE910\OneWorld Client Install\Stage\Queries\areasQueries\10.2.0.1.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Queries\dbQueries
JDEdwardsE910\OneWorld Client Install\Stage\Queries\dbQueries\10.1.0.2.0
JDEdwardsE910\OneWorld Client Install\Stage\Queries\dbQueries\10.1.0.2.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Queries\e1DBQueries
JDEdwardsE910\OneWorld Client Install\Stage\Queries\e1FileQueries
JDEdwardsE910\OneWorld Client Install\Stage\Queries\e1FileQueries\10.2.0.3.0
JDEdwardsE910\OneWorld Client Install\Stage\Queries\e1FileQueries\10.2.0.3.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Queries\e1GeneralQueries
JDEdwardsE910\OneWorld Client Install\Stage\Queries\e1GeneralQueries\10.2.0.3.0
JDEdwardsE910\OneWorld Client Install\Stage\Queries\e1GeneralQueries\10.2.0.3.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Queries\e1ISeriesQueries
JDEdwardsE910\OneWorld Client Install\Stage\Queries\e1ISeriesQueries\10.2.0.3.0
JDEdwardsE910\OneWorld Client Install\Stage\Queries\e1ISeriesQueries\10.2.0.3.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Queries\e1PackageQueries
JDEdwardsE910\OneWorld Client Install\Stage\Queries\e1PackageQueries\10.2.0.3.0
JDEdwardsE910\OneWorld Client Install\Stage\Queries\e1PackageQueries\10.2.0.3.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Queries\fileQueries
JDEdwardsE910\OneWorld Client Install\Stage\Queries\fileQueries\10.1.0.3.0
```



```

JDEdwardsE910\OneWorld Client Install\Stage\Queries\fileQueries\10.1.0.3.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Queries\generalQueries
JDEdwardsE910\OneWorld Client Install\Stage\Queries\generalQueries\10.2.0.2.0
JDEdwardsE910\OneWorld Client Install\Stage\Queries\generalQueries\10.2.0.2.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Queries\netQueries
JDEdwardsE910\OneWorld Client Install\Stage\Queries\netQueries\10.2.0.2.0
JDEdwardsE910\OneWorld Client Install\Stage\Queries\netQueries\10.2.0.2.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Queries\NtServicesQueries
JDEdwardsE910\OneWorld Client Install\Stage\Queries\NtServicesQueries\10.2.0.3.0
JDEdwardsE910\OneWorld Client Install\Stage\Queries\NtServicesQueries\10.2.0.3.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Queries\rgsQueries
JDEdwardsE910\OneWorld Client Install\Stage\Queries\rgsQueries\10.1.0.3.0
JDEdwardsE910\OneWorld Client Install\Stage\Queries\rgsQueries\10.1.0.3.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Queries\unixQueries
JDEdwardsE910\OneWorld Client Install\Stage\Queries\unixQueries\10.1.0.2.0
JDEdwardsE910\OneWorld Client Install\Stage\Queries\unixQueries\10.1.0.2.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Queries\w32RegQueries
JDEdwardsE910\OneWorld Client Install\Stage\Queries\w32RegQueries\10.2.0.1.0
JDEdwardsE910\OneWorld Client Install\Stage\Queries\w32RegQueries\10.2.0.1.0\1
JDEdwardsE910\OneWorld Client Install\Stage\Queries\WindowsGeneralQueries
JDEdwardsE910\OneWorld Client
Install\Stage\Queries\WindowsGeneralQueries\10.2.0.1.0
JDEdwardsE910\OneWorld Client
Install\Stage\Queries\WindowsGeneralQueries\10.2.0.1.0\1
JDEdwardsE910\OneWorld Client Install\Stage\shiphomeinfo
JDEdwardsE910\OneWorld Client Install\Stage\shiphomeinfo\summary
JDEdwardsE910\OneWorld Client Install\ThirdParty
JDEdwardsE910\OneWorld Client Install\ThirdParty\BPMBroker
JDEdwardsE910\OneWorld Client Install\ThirdParty\ORACLE
JDEdwardsE910\OneWorld Client Install\ThirdParty\VSRunTime
JDEdwardsE910\OneWorld Client Install\ThirdParty\WebDevFeature
JDEdwardsE910\OneWorld Client Install\ThirdParty\WebDevFeature\H4A7
JDEdwardsE910\OneWorld Client Install\ThirdParty\WebDevFeature\OH4A
JDEdwardsE910\OPatch
JDEdwardsE910\OPatch\crs
JDEdwardsE910\OPatch\docs
JDEdwardsE910\OPatch\fmw
JDEdwardsE910\OPatch\jlib
JDEdwardsE910\OPatch\ocm
JDEdwardsE910\OPatch\ocm\generic.zip
JDEdwardsE910\OPatch\opatchprereqs
JDEdwardsE910\OPatch\opatchprereqs\opatch
JDEdwardsE910\OPatch\opatchprereqs\oui
JDEdwardsE910\oui
JDEdwardsE910\oui\bin
JDEdwardsE910\oui\bin\resource
JDEdwardsE910\oui\instImages
JDEdwardsE910\oui\jlib
JDEdwardsE910\oui\jlib\lib
JDEdwardsE910\oui\lib
JDEdwardsE910\oui\lib\win32
JDEdwardsE910\oui\schema
JDEdwardsE910\package_inf
JDEdwardsE910\package_inf\Feature_inf
JDEdwardsE910\Planner
JDEdwardsE910\Planner\bin32
JDEdwardsE910\Planner\bin32
JDEdwardsE910\Planner\data
JDEdwardsE910\Planner\include
JDEdwardsE910\Planner\ini

```

```

JDEdwardsE910\Planner\ini\sbf
JDEdwardsE910\Planner\java
JDEdwardsE910\Planner\java\sbfjars
JDEdwardsE910\Planner\lib32
JDEdwardsE910\Planner\make
JDEdwardsE910\Planner\obj
JDEdwardsE910\Planner\res
JDEdwardsE910\Planner\res\actionbmps
JDEdwardsE910\Planner\res\AVI Files
JDEdwardsE910\Planner\res\FormLines
JDEdwardsE910\Planner\res\Icons
JDEdwardsE910\Planner\res\images
JDEdwardsE910\Planner\res\treebmps
JDEdwardsE910\Planner\source
JDEdwardsE910\Planner\spec
JDEdwardsE910\Planner\spec\runtimeCache
JDEdwardsE910\Planner\work
JDEdwardsE910\Planner\work\sbf
JDEdwardsE910\SolutionExplorer
JDEdwardsE910\SolutionExplorer\+ Concept To Opportunity
JDEdwardsE910\SolutionExplorer\+ Concept To Opportunity\CustomWorks
JDEdwardsE910\SolutionExplorer\+ Concept To Opportunity\CustomWorks\Object Model
Documentation
JDEdwardsE910\SolutionExplorer\+ Consumption To Reorder
JDEdwardsE910\SolutionExplorer\+ Demand To Available
JDEdwardsE910\SolutionExplorer\+ Demand To Available\MakeProduct
JDEdwardsE910\SolutionExplorer\+ Demand To Available\MakeProduct\Make Product
Interview Questions_files
JDEdwardsE910\SolutionExplorer\+ Demand To Available\PlanSupplyChain
JDEdwardsE910\SolutionExplorer\+ Implementation Approach
JDEdwardsE910\SolutionExplorer\+ Manage The Business
JDEdwardsE910\SolutionExplorer\+ Manage The Business\Activity Scripts
JDEdwardsE910\SolutionExplorer\+ Manage The Business\Activity Scripts\Account and
Report Script_files
JDEdwardsE910\SolutionExplorer\+ Manage The Business\Activity Scripts\Process
Payments Script_files
JDEdwardsE910\SolutionExplorer\+ Manage The Business\Activity Scripts\Process
Receivables Script_files
JDEdwardsE910\SolutionExplorer\+ Manage The Business\Interview Questions
JDEdwardsE910\SolutionExplorer\+ Manage The Business\Interview Questions\Account
and Report Questions_files
JDEdwardsE910\SolutionExplorer\+ Manage The Business\Interview Questions\Process
Payments Questions_files
JDEdwardsE910\SolutionExplorer\+ Manage The Business\Interview Questions\Process
Receivables Questions_files
JDEdwardsE910\SolutionExplorer\+ Order To Cash
JDEdwardsE910\SolutionExplorer\+ Order To Cash_vti_cnf
JDEdwardsE910\SolutionExplorer\+ Procure To Pay
JDEdwardsE910\SolutionExplorer\+ Procure To Pay_vti_cnf
JDEdwardsE910\SolutionExplorer\+ Procure To Pay\CRP Scripts procure to pay_files
JDEdwardsE910\SolutionExplorer\+ Procure To Pay\CRP Scripts procure to pay_files_
vti_cnf
JDEdwardsE910\SolutionExplorer\BM944072060102
JDEdwardsE910\SolutionExplorer\BMPxxxxxxxxxxxxx
JDEdwardsE910\SolutionExplorer\JDExxxxxx
JDEdwardsE910\system
JDEdwardsE910\system\bin32
JDEdwardsE910\system\bin32\debug
JDEdwardsE910\system\Classes
JDEdwardsE910\system\Classes\buildDeployBSSV

```

JDEdwardsE910\system\Classes\ConsumerWEBXML  
JDEdwardsE910\system\Classes\endorsed  
JDEdwardsE910\system\Classes\lib  
JDEdwardsE910\system\Classes\Orchestration  
JDEdwardsE910\system\Classes\samples  
JDEdwardsE910\system\Generator  
JDEdwardsE910\system\IDA  
JDEdwardsE910\system\include  
JDEdwardsE910\system\include\connector  
JDEdwardsE910\system\include\database  
JDEdwardsE910\system\include\jdesaw  
JDEdwardsE910\system\include\Metadata  
JDEdwardsE910\system\include\netmessaging  
JDEdwardsE910\system\include\perfmon  
JDEdwardsE910\system\include\workflow  
JDEdwardsE910\system\include\xml  
JDEdwardsE910\system\includev  
JDEdwardsE910\system\includev\unicode  
JDEdwardsE910\system\JDK  
JDEdwardsE910\system\JRE  
JDEdwardsE910\system\lib32  
JDEdwardsE910\system\libv32  
JDEdwardsE910\system\Locale  
JDEdwardsE910\system\Locale\Iconv  
JDEdwardsE910\system\Locale\Uconvtab  
JDEdwardsE910\system\Locale\xml  
JDEdwardsE910\system\Locale\xml\hpux  
JDEdwardsE910\system\Locale\xml\NT  
JDEdwardsE910\system\Locale\xml\Solaris  
JDEdwardsE910\system\Mobile  
JDEdwardsE910\system\Mobile\Authentication  
JDEdwardsE910\system\Mobile\JrnlSQLCode  
JDEdwardsE910\system\Mobile\WebLogic  
JDEdwardsE910\system\OC4J  
JDEdwardsE910\system\OC4J\ant  
JDEdwardsE910\system\OC4J\ant\bin  
JDEdwardsE910\system\OC4J\ant\etc  
JDEdwardsE910\system\OC4J\ant\etc\checkstyle  
JDEdwardsE910\system\OC4J\ant\lib  
JDEdwardsE910\system\OC4J\bin  
JDEdwardsE910\system\OC4J\diagnostics  
JDEdwardsE910\system\OC4J\diagnostics\config  
JDEdwardsE910\system\OC4J\diagnostics\lib  
JDEdwardsE910\system\OC4J\j2ee  
JDEdwardsE910\system\OC4J\j2ee\home  
JDEdwardsE910\system\OC4J\j2ee\utilities  
JDEdwardsE910\system\OC4J\javacache  
JDEdwardsE910\system\OC4J\javacache\lib  
JDEdwardsE910\system\OC4J\javavm  
JDEdwardsE910\system\OC4J\javavm\lib  
JDEdwardsE910\system\OC4J\jdbc  
JDEdwardsE910\system\OC4J\jdbc\lib  
JDEdwardsE910\system\OC4J\jlib  
JDEdwardsE910\system\OC4J\lib  
JDEdwardsE910\system\OC4J\opmn  
JDEdwardsE910\system\OC4J\opmn\lib  
JDEdwardsE910\system\OC4J\rdbms  
JDEdwardsE910\system\OC4J\rdbms\jlib  
JDEdwardsE910\system\OC4J\sqlj  
JDEdwardsE910\system\OC4J\sqlj\jlib

```
JDEdwardsE910\system\OC4J\toplink
JDEdwardsE910\system\OC4J\toplink\jlib
JDEdwardsE910\system\OC4J\webservices
JDEdwardsE910\system\OC4J\webservices\lib
JDEdwardsE910\system\OC4J\xqs
JDEdwardsE910\system\OC4J\xqs\lib
JDEdwardsE910\system\OC4J\xqs\tools
JDEdwardsE910\system\resource
JDEdwardsE910\system\resource\cmap
JDEdwardsE910\system\resource\truetype
JDEdwardsE910\systemcomp
JDEdwardsE910\ThirdParty
JDEdwardsE910\ThirdParty\BPMBroker
```

## 23.2 Language Directory Structure

The following table outlines the Release 9.1 software directory structure for the Release 9.1 language installation image. You must understand this directory structure to help you verify that the language was installed correctly.

| Directory Name                 | Definition                                                           |
|--------------------------------|----------------------------------------------------------------------|
| \LANGUAGE                      | Name of language for JD Edwards EnterpriseOne language installation. |
| \Helps                         | Language help files.                                                 |
| \SolutionExplorer              | Solution Explorer language files.                                    |
| \SolutionExplorer\PLANNER      | Planner path code.                                                   |
| \SolutionExplorer\PLANNER\DATA | Language database.                                                   |

## 23.3 IBM i Libraries

After you transfer Release 9.1 software to the Enterprise Server and run Installation Workbench, you should have the following Enterprise Server libraries, where xxxx is the release to which you are installing, such as E910.

| Library Type     | Library Name | IFS                                                                                                                                     | Definition                          |
|------------------|--------------|-----------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------|
| Install          | JDEOW        |                                                                                                                                         | Menus and executable programs       |
| Host Application | E900SYS      | E900SYS<br>classes<br>include<br>includea<br>includev<br>locale<br>resource<br>INI<br>output<br>queue<br>printqueue<br>OneWorld\Package | JD Edwards EnterpriseOne Foundation |

| Library Type        | Library Name | IFS            | Definition                                |
|---------------------|--------------|----------------|-------------------------------------------|
| Host Application    | E900SYS      | Packages       | Package source, include, and spec files   |
| Shared              | DD910        |                | Data Dictionary tables                    |
|                     | OL910        |                | Object Librarian tables                   |
|                     | SVM910       |                | Server Map tables                         |
|                     | SY910        |                | System tables                             |
|                     | OWJRNL       |                | Journaling                                |
|                     |              | JDE910         | EnterpriseOne log files                   |
| Environment         |              |                |                                           |
| DV910 (Development) | TESTCTL      |                | Control Tables and Data Dictionary tables |
|                     | TESTDTA      |                | Business Data tables                      |
|                     | CODV910      |                | Central Objects and Versions tables       |
|                     | DV910        |                | Pathcode service programs                 |
|                     | DV910        |                | Parent package service programs           |
|                     |              | DV910\specfile | Pathcode specifications                   |
| PS910 (Pristine)    | PS910CTL     |                | Control Tables and Data Dictionary tables |
|                     | PS910DTA     |                | Business Data tables                      |
|                     | COPS910      |                | Central Objects and Versions tables       |
|                     | PS910        |                | Pathcode service programs                 |
|                     | PS910        |                | Parent package service programs           |
|                     |              | PS910\specfile | Pathcode specifications                   |
| PD910 (Production)  | PRODCTL      |                | Control Tables and Data Dictionary tables |
|                     | PRODDTA      |                | Business Data tables                      |
|                     | COPD910      |                | Central Objects and Versions tables       |
|                     | PD910        |                | Pathcode service programs                 |
|                     | PD910FA      |                | Parent package service programs           |
|                     |              | PD910\specfile | Pathcode specifications                   |
| PY910 (Prototype)   | CRPCTL       |                | Control Tables and Data Dictionary tables |
|                     | CRPDTA       |                | Business Data tables                      |
|                     | COPY910      |                | Central Objects and Versions tables       |
|                     | PY910        |                | Pathcode service programs                 |
|                     | PY910FA      |                | Parent package service programs           |
|                     |              | PY910\specfile | Pathcode specifications                   |

## 23.4 Workstation General Directory Structure

After you install Release 9.1 installation on a Workstation, you should have the following local directory structure:

```
\E910
\E910\Log
\E910\output
\E910\packages
\E910\PD910
\E910\PrintQueue
\E910\queues
\E910\system
\E910\PD910\bin32
\E910\PD910\spec
\E910\PD910\spec\JDE
\E910\queues\control
\E910\queues\outqueue
\E910\system\bin32
\E910\system\Classes
\E910\system\include
\E910\system\includev
\E910\system\lib32
\E910\system\libv32
\E910\system\locale
\E910\system\resource
\E910\system\Classes\samples
\E910\system\includev\unicode
\E910\system\locale\iconv
\E910\system\locale\uconvtab
\E910\system\locale\xml
\E910\system\resource\cidfont
\E910\system\resource\cmap
\E910\system\resource\encoding
\E910\system\resource\font
\E910\system\resource\iccprofile
\E910\system\resource\truetype
\E910\system\resource\font\pfm
```

## Major Technical Tables

This chapter lists the major technical tables in the Release 9.1 data sources. This chapter does not list any Release 9.1 application tables. All technical media storage objects (GTxxx) are listed at the end of this chart. Many tables exist in multiple data sources. Some tables exist in data sources not noted here.

---

---

**Note:** The Local - pathcode data source refers only to local databases that are path code specific. In the chart below, Local - pathcode could represent more than one data source, depending on the number of path codes you use. Pathcode is one or more of the following path codes:

- PY910
  - DV910
  - PS910
  - PD910
  - DEP910
- 
- 

---

---

**Note:** The Local data source refers only to the local database on the Deployment Server, which is used by the planner environment.

---

---

\* Specific tables in the list below reflect language information, and contain a language preference code that is translated by JD Edwards EnterpriseOne.

| Table   | Data Source                                                                                                                  | Description              | Purpose                                                                                                                                                  |
|---------|------------------------------------------------------------------------------------------------------------------------------|--------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------|
| F0004D* | Control Tables                                                                                                               | UDC - Alternate Language | Contains the User Defined Code (UDC) key, language key, and text for headers in the F0004 table. Provides UDC type descriptions for alternate languages. |
| F0005D* | Control Tables                                                                                                               | UDC - Alternate Language | Contains UDC key, language key, and text for detail in the F0005 table. Provides UDC value descriptions for alternate languages.                         |
| F00165* | Business Data - Data Dictionary - 910Object Librarian - 910 Business Data Local Data Dictionary Local Object Librarian Local | Media Objects storage    | Stores text OLE references and image references. Stores glossary text and media objects for all languages.                                               |

| <b>Table</b> | <b>Data Source</b>                            | <b>Description</b>               | <b>Purpose</b>                                                                                                                                                    |
|--------------|-----------------------------------------------|----------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| F0092        | System - 910<br>Planner - 910<br>System Local | Library List - User              | Contains one record per user with initial menu, initial program, and whether to enable fast path.                                                                 |
| F00921*      | System - 910<br>Planner - 910<br>System Local | User Display Preferences         | Contains one record per user with date format, date separator, DW prefix, and language preference.                                                                |
| F00922       | System - 910<br>Planner - 910<br>System Local | User Display Preferences Tagfile | Contains one record per user with workstation configuration name. This table is used with the F00050 table.                                                       |
| F00924       | System - 910<br>Planner - 910<br>System Local | User Install Packages            | Contains one record per user for each authorized package.                                                                                                         |
| F0093        | System - 910<br>Planner - 910<br>System Local | Library List Control             | Contains a list, by user, of authorized environments.                                                                                                             |
| F0094        | System - 910<br>Planner - 910<br>System Local | Library List Master file         | Contains master file information for an environment.                                                                                                              |
| F00941       | System - 910<br>Planner - 910<br>System Local | Environment Detail - EO          | Contains one record per environment, with release and path code.                                                                                                  |
| F00942       | System - 910<br>Planner - 910<br>System Local | Object Path Master file          | Contains one record per path code with the data source for the specification files and the server path for the other development objects (.DLL, source, headers). |
| F00945       | System - 910<br>Planner - 910<br>System Local | Release Master                   | Contains one record per release, with the data source for system tables and the environments server path.                                                         |
| F00946       | System - 910<br>Planner - 910<br>System Local | Release Compatibility Map        | Contains information used to map major release levels to determine forward and backward compatibility.                                                            |
| F00948       | System - 910<br>Planner - 910<br>System Local | Release Data Source Map          | Contains information used to map a specific type of data source to a release level, such as Object Librarian, data dictionary, or versions list data sources.     |
| F00950       | System - 910<br>System Local                  | Security Workbench table         | Stores security attributes (one record for each user or group).                                                                                                   |
| F00960       | System - 910<br>System Local                  | Machine/Group Identification     | Stores a list of all workstations that installed Release 8.9 to scheduled packages.                                                                               |
| F83100*      | System - 910<br>System Local                  | Data Title                       | Series of definitions of data titles. Each row is the definition or specification of the data title. Provides soft coded RDA text.                                |



| <b>Table</b> | <b>Data Source</b>           | <b>Description</b>                              | <b>Purpose</b>                                                                                                                                                                     |
|--------------|------------------------------|-------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| F83110*      | System - 910<br>System Local | Column Headings                                 | Gives each period number an associated description. Provides soft coded RDA text.                                                                                                  |
| F9100        | Control Table                | Task Master                                     | Lists Release 8.9 tasks (Solution Explorer only).                                                                                                                                  |
| F9101        | Control Table                | Task Relationships                              | Groups tasks listed in the F9100 table in logical (parent/child) tree order (ActivEra only).                                                                                       |
| F9102        | Control Table                | Task Descriptions                               | Provides descriptions of tasks listed in the F9100 table (ActivEra only).                                                                                                          |
| F9105        | Control Table                | Variant Description                             | Describes the attributes of variants listed in this table. A variant performs a series of designated tasks (nodes) within a tree order defined in the F9101 table (ActivEra only). |
| F9105D       | Control Table                | Alternate Variant Descriptions                  | Provides translated text for descriptions listed in the F9105 table (ActivEra only).                                                                                               |
| F9106        | Control Table                | Variant Detail                                  | Defines which nodes (tasks) are run within a variant and the names of any tasks dynamically renamed within a variant (ActivEra only).                                              |
| F9106D       | Control Table                | Alternate Variant Detail Descriptions           | Provides translated text for descriptions listed in the F9106 table (ActivEra only).                                                                                               |
| F9010        | Control Table                | Environment Setup Answers                       |                                                                                                                                                                                    |
| F9020        | Control Table                | ActivEra Qualifier Rules Header                 | Defines rule names used by ActivEra. Rules are applied to conditionally execute an individual task or task relationship (tree order).                                              |
| F9022        | Control Table                | ActivEra Qualifier Rules Detail                 | Lists conditional statements within rules listed in the F9020 table (ActivEra only).                                                                                               |
| F9030        | Control Table                | Documentation Cross-reference                   | Stores indexes of HTML documents associated with specific tasks (ActivEra only).                                                                                                   |
| F9050        | Control Table                | Rough-cut Answer Dependency                     | Defines the hierarchical means of eliminating system codes and subsequent applications which do not apply within a specified system configuration (ActivEra only).                 |
| F91100       | System - 910                 | Favorites - Relationship Properties             | Categorizes business views on a parent/child format.                                                                                                                               |
| F91100D*     | System - 910                 | Favorites - All Descriptions                    | Stores alternate descriptions for different languages.                                                                                                                             |
| F91300       | System - 910                 | Scheduled Job Master                            |                                                                                                                                                                                    |
| F91310       | System - 910                 | Scheduled Job Parameters                        |                                                                                                                                                                                    |
| F91320       | System - 910                 | Job Schedule                                    |                                                                                                                                                                                    |
| F91330       | System - 910                 | Scheduled Job Override Printer Info             |                                                                                                                                                                                    |
| F91400       | System - 910                 | Report Director Templates                       | Contains the design templates for reports that users can create.                                                                                                                   |
| F91410       | System - 910                 | Report Director Templates Sequence Items        | Helps users manipulate data sequencing.                                                                                                                                            |
| F91420       | System - 910                 | Report Director Template Smart Field Activation | Creates a list showing all data items belonging to a smart field template.                                                                                                         |

| Table  | Data Source                                    | Description                           | Purpose                                                                                                                                                                                                                                                                                                                                                                    |
|--------|------------------------------------------------|---------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| F91430 | System - 910                                   | Smart Field Template Criteria         | Stores a subset of selection criteria.                                                                                                                                                                                                                                                                                                                                     |
| F91500 | System - 910                                   | Application Header for Tip of the Day | Contains application names or tools names where tips reside.                                                                                                                                                                                                                                                                                                               |
| F91510 | System - 910                                   | Tip Details for Tip of the Day        | Stores tip texts and a key to modify the sequence.                                                                                                                                                                                                                                                                                                                         |
| F9200  | Data Dictionary<br>Data Dictionary Local       | Data Item Master                      | Contains the relational breakdown of data dictionary.                                                                                                                                                                                                                                                                                                                      |
| F9202* | Data Dictionary<br>Data Dictionary Local       | Data Field Display Text               | <p>Contains display text for each data field for language, data item, and product code reporting. Used when data items descriptions requested. Data dictionary row and column text for all languages* *</p> <p>The language preference code for data dictionary applies to text only. Text includes row and column headings, a compressed description, and glossaries.</p> |
| F9203* | Data Dictionary<br>Data Dictionary Local       | Data Item Alpha Descriptions          | Contains alpha descriptions and compressed descriptions of data items. Used when data items descriptions requested. Similar to the F9202 table. Contains data dictionary alpha descriptions for all languages.                                                                                                                                                             |
| F9207  | Data Dictionary<br>Data Dictionary Local       | DD Error Message Information          | Contains one record per error message.                                                                                                                                                                                                                                                                                                                                     |
| F9210  | Data Dictionary<br>Data Dictionary Local       | Data Field Specifications             | Contains detailed information (specifications) for each data item. This table is accessed whenever a data item needs to be identified.                                                                                                                                                                                                                                     |
| F9211  | Data Dictionary<br>Data Dictionary Local       | Data Dictionary - Smart Fields        | Contains information for Smart Fields.                                                                                                                                                                                                                                                                                                                                     |
| F9212  | Data Dictionary - 910<br>Data Dictionary Local | Smart Field Criteria - Setup Rules    |                                                                                                                                                                                                                                                                                                                                                                            |
| F96021 | System - 910                                   | Software Package Build Header         | Stores the detail information from the definition process of package build.                                                                                                                                                                                                                                                                                                |
| F9603  | System - 910                                   | Software Package Build Header         | Stores information from the assembly process of package build.                                                                                                                                                                                                                                                                                                             |
| F96210 | System - 910<br>System Local                   | Package Build Validation Tables       |                                                                                                                                                                                                                                                                                                                                                                            |
| F96211 | System - 910<br>System Local                   | Package Build Validation Detail       |                                                                                                                                                                                                                                                                                                                                                                            |
| F96215 | System - 910<br>Planner - 910<br>System Local  | Software Package Build Header History | Contains the history record of the F96021 record. It stores statuses of the package each time it is built.                                                                                                                                                                                                                                                                 |
| F9622  | System - 910<br>Planner - 910<br>System Local  | Software Package Build Detail         | Stores the option information from the definition process of package build. Each record is either the name of the specification file, the name of a .DLL file, the name of the compression directory, or the name of an object.                                                                                                                                            |

| <b>Table</b> | <b>Data Source</b>                            | <b>Description</b>                    | <b>Purpose</b>                                                                                                                                                  |
|--------------|-----------------------------------------------|---------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------|
| F96225       | System - 910<br>Planner - 910<br>System Local | Software Package Build Detail History | Contains the history record of the software build program (P9622). Stores the status of the build on the operation of that record when the package is finished. |
| F9631        | System - 910<br>Planner - 910<br>System Local | Software Package Detail               | Stores the detail information for the assembly process of package build. Stores the object names, foundation name, data name, or helps name.                    |
| F9650        | System - 910<br>Planner - 910<br>System Local | Machine Master                        | Holds the default information regarding all machines used by JD Edwards EnterpriseOne.                                                                          |
| F9651        | System - 910<br>Planner - 910<br>System Local | Machine Detail                        | Holds specific information about each machine defined in the machine master table by record type.                                                               |
| F9652        | System - 910<br>Planner - 910<br>System Local | Deployment Group Header               | Specifies groups that can be used by the Release 9.1 administrator for deploying packages.                                                                      |
| F9653        | System - 910<br>Planner - 910<br>System Local | Deployment Group Detail Definitions   | Stores the users that belong to one or more groups that were defined in the deployment header file. In addition, groups of groups can be defined here.          |
| F9654        | System - 910<br>Planner - 910<br>System Local | Deployment Location Definitions       | Enables definition of one or more locations for deployment. This table is used primarily in multitier deployment.                                               |
| F9660        | System - 910<br>Planner - 910<br>System Local | Task Breaks                           |                                                                                                                                                                 |
| F96600       | System - 910<br>Planner - 910<br>System Local | Deployment Features                   |                                                                                                                                                                 |
| F96601       | System - 910<br>Planner - 910<br>System Local | Deployment Registry                   |                                                                                                                                                                 |
| F96602       | System - 910<br>Planner - 910<br>System Local | Deployment Shortcut                   |                                                                                                                                                                 |
| F96603       | System - 910<br>Planner - 910<br>System Local | Deployment Execute                    |                                                                                                                                                                 |
| F96604       | System - 910<br>Planner - 910<br>System Local | Deployment Third Party                |                                                                                                                                                                 |

| Table    | Data Source                                   | Description                                      | Purpose                                                                                      |
|----------|-----------------------------------------------|--------------------------------------------------|----------------------------------------------------------------------------------------------|
| F96605   | System - 910<br>Planner - 910<br>System Local | Deployment Initialization                        |                                                                                              |
| F96605T  | System - 910<br>Planner - 910<br>System Local | Deployment Initialization                        |                                                                                              |
| F96606   | System - 910<br>Planner - 910<br>System Local | Deployment File Set                              |                                                                                              |
| F966071  | System - 910<br>Planner - 910<br>System Local | Deployment ODBC Data Source                      |                                                                                              |
| F966072  | System - 910<br>Planner - 910<br>System Local | Deployment ODBC Data Source Attributes           |                                                                                              |
| F9670    | System - 910<br>Planner - 910<br>System Local | Software Update Master Table                     |                                                                                              |
| F9671    | System - 910<br>Planner - 910<br>System Local | Software Update Detail Table                     |                                                                                              |
| F96710   | System - 910<br>Planner - 910<br>System Local | Impact Analysis Results                          |                                                                                              |
| F9672    | System - 910<br>Planner - 910<br>System Local | Software Update Pathcode Information             |                                                                                              |
| F96761   | System - 910<br>Planner - 910<br>System Local | Software Update Object Detail                    |                                                                                              |
| F967611  | System - 910<br>Planner - 910<br>System Local | Software Update Language Table                   |                                                                                              |
| F9691100 | System Local                                  | Change Table - Favorites                         | Stores adds, changes, and deletes to favorites tables between releases.                      |
| F9691400 | System Local                                  | Change Table - Report Director Template Header   | Stores adds/changes/deletes to the Report Director template header table between releases.   |
| F9691410 | System Local                                  | Change Table - Report Director Template Sequence | Stores adds/changes/deletes to the Report Director Template Sequence table between releases. |
| F9691420 | System Local                                  | Change Table - Smart Field Activity              | Stores adds/changes/deletes to the Smart Field Activity table between releases.              |

| Table    | Data Source                                    | Description                                    | Purpose                                                                                                                                                                                            |
|----------|------------------------------------------------|------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| F9691430 | System Local                                   | Change Table - Smart Field Criteria            | Stores adds/changes/deletes to the Smart Field Criteria table between releases.                                                                                                                    |
| F9746    | System Local                                   | UDC Merge table                                | Contains the UDC records changed or added from release to release. This table is used by the UDC merge program (R98741).                                                                           |
| F960004  | Control Tables - xxx<br>Control Tables Local   | UDC Type                                       |                                                                                                                                                                                                    |
| F960005  | Control Tables - xxx<br>Control Tables Local   | UDC Codes                                      |                                                                                                                                                                                                    |
| F9755    | Data Dictionary - 910<br>Data Dictionary Local | Data Item Master Changes by Release            | Contains the data dictionary items changed or added from release to release. This table is used by the Data Dictionary merge program (R989200P).                                                   |
| F9757    | Data Dictionary - 910<br>Data Dictionary Local | Data Item Alpha Description Changes by Release | Lists changes made to alpha descriptions of data items (F9203) between releases. This table is used in the data dictionary merge process.                                                          |
| F9759    | Data Dictionary - 910<br>Data Dictionary Local | Error Message Pgm Call Changes By Release      | Lists changes made to error messages (F9207) between releases. This table is used in the data dictionary merge process.                                                                            |
| F9760    | Data Dictionary - 910<br>Data Dictionary Local | Data Field Specification Changes By Release    | Lists changes made to field specifications (F9210) between releases. This table is used in the data dictionary merges.                                                                             |
| F980011  | Central Objects - xxx<br>Versions Local        | Cross ' Reference Relationships                | Lists cross-reference relationships for business views, event rules, and controls.                                                                                                                 |
| F980021  | Central Objects - xxx<br>Versions Local        | Cross ' Reference Field Relationships          | Lists cross-reference relationships for fields in an application.                                                                                                                                  |
| F98101   | System - 910<br>System Local                   | Imaging Constants                              | Determines whether you are doing third-party imaging.                                                                                                                                              |
| F983051  | Versions - xxx Versions<br>Local               | Versions List                                  | Contains one record per version (batch or interactive). For interactive, it stores processing option values. For batch, this table holds data selection, sequencing, and other template overrides. |
| F982xx   | System - 910<br>System Local<br>Planner - 910  | Series (OMW)                                   |                                                                                                                                                                                                    |
| F98306*  | Central Objects - xxx<br>Versions Local        | Processing Option Text                         | Provides processing option text for all languages.                                                                                                                                                 |
| F9840    | Version - 910<br>Planner - 910                 | Installation Plan Master table                 | Contains general information for the installation plan with one record per plan name (description and status).                                                                                     |
| F98401   | Version - 910<br>Planner - 910                 | Data Source Plan Detail table                  | Lists data sources for each plan, and one record per plan record per data source associated with that plan.                                                                                        |
| F98402   | Version - 910<br>Planner - 910                 | Host Plan Detail table                         | Lists the Enterprise Server and hosts for each plan (one record per plan, per server).                                                                                                             |
| F984021  | Version - 910<br>Planner - 910                 | Location Plan Detail table                     | Contains the last location for a plan.                                                                                                                                                             |

| <b>Table</b> | <b>Data Source</b>                                          | <b>Description</b>                         | <b>Purpose</b>                                                                                                                                                                                                                                                      |
|--------------|-------------------------------------------------------------|--------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| F984022      | Version - 910<br>Planner - 910                              | Replication Plan Detail table              | Stores replicated plan for remote locations, publisher, and subscriber tables.                                                                                                                                                                                      |
| F98403       | Version - 910<br>Planner - 910                              | Environment Plan Detail table              | Lists environments for each plan. Holds flags for production data, demo data, and table conversions for an upgrade.                                                                                                                                                 |
| F984031*     | Version - 910<br>Planner - 910                              | Language and Environment Plan Detail table | Lists language and the selected environments for each plan.                                                                                                                                                                                                         |
| F98404       | Version - 910<br>Planner - 910                              | Package Plan Detail table                  | Lists packages and package definitions for each environment.                                                                                                                                                                                                        |
| F98405       | Version - 910<br>Planner - 910                              | Table Conversion Scheduler                 | Lists table conversion information merged in Table Conversion Scheduler from Environment Planner and Table Conversion Planner. This table is similar to the F9843 table.                                                                                            |
| F984052      | Version - 910<br>Planner - 910                              | Table Conversion - History Log             | Stores the logs for table conversions, control table merges, and specification merges.                                                                                                                                                                              |
| F9843        | System - 910                                                | Table Conversion - JDE Scheduler           | Contains table conversions, control table merges, and specification merges for upgrades, updates, and coexistent installations.                                                                                                                                     |
| F9843T       | System - 910                                                |                                            |                                                                                                                                                                                                                                                                     |
| F98511       | System - 910<br>Planner - 910                               | REP Data Sources by Environment            | Lists default data sources by environment. This table is used during installation.                                                                                                                                                                                  |
| F9860        | Object Librarian<br>Object Librarian Local                  | Object Librarian Master table              | Contains one record per object with description and object type.                                                                                                                                                                                                    |
| F9861        | Object Librarian<br>Object Librarian Local                  | Object Librarian - Status Detail           | Contains one record per object, per location, per path code. Each object has a server location plus locations for each person who checks it out to his machine.                                                                                                     |
| F986101      | System - 910<br>Server Map<br>Planner - 910<br>System Local | Object Configuration Master                | Contains all data sources for tables, batch applications, and business functions that run on the server. The only data sources not controlled through this file are the system data source in Release Master and the Development data source in object path master. |
| F98611       | System - 910<br>Server Map<br>Planner - 910<br>System Local | Data Source Master                         | Holds data source definitions. One record per data source with type, database, machine name, and foundation .DLL.                                                                                                                                                   |
| F986110      | System - 910<br>Server Map<br>Planner - 910<br>System Local |                                            | Contains one record for each job on the server with status information.                                                                                                                                                                                             |
| F986111      | System - 910<br>Server Map<br>Planner - 910<br>System Local | Job Number Master                          | Contains the next numbers table for server jobs.                                                                                                                                                                                                                    |

| <b>Table</b> | <b>Data Source</b>                                          | <b>Description</b>                    | <b>Purpose</b>                                                                                                                                            |
|--------------|-------------------------------------------------------------|---------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------|
| F986113      | System - 910<br>Server Map<br>Planner - 910<br>System Local | Subsystem Job Master                  | Contains server job records, including status, location, and version.                                                                                     |
| F986115      | System - 910<br>Server Map<br>Planner - 910<br>System Local | Table and Data Source<br>Sizing table | Holds storage, sizing, and location parameters for Oracle, with some general information for all data sources.                                            |
| F986116      | System - 910<br>Server Map<br>Planner - 910<br>System Local | MVS table and Data<br>Source Sizing   | Holds storage, sizing, and location parameters for MVS. Similar to the F986115 table.                                                                     |
| F98613       | System - 910<br>Server Map<br>Planner - 910<br>System Local | Business View<br>Environmental Server | Lists cached tables.                                                                                                                                      |
| F986150      | System - 910<br>System Local                                | Server Transfer Package<br>Contents   | Lists objects belonging to each server package. This table is used by the server package installation process (P986150).                                  |
| F986151      | System - 910<br>System Local                                | Server Package Transfer               | Lists the servers and path codes to which a given server package will be transferred. This table is used by the server package install process (P986150). |
| F986152      | System - 910<br>System Local                                | Server Package Master                 | Contains the master list of all service packages. This table is used by the server package install process (P986150).                                     |
| F98616       | System - 910<br>System Local                                | Printer                               | Lists the printer definitions, including logical name, physical name, and conversion program, one record per printer.                                     |
| F986161      | System - 910<br>System Local                                | Default Printer table                 | Lists default printer settings by user and environment.                                                                                                   |
| F986162      | System - 910<br>System Local                                | Paper Definition                      | Lists paper sizes defined for each printer, one record per printer.                                                                                       |
| F986163      | System - 910<br>System Local                                | Printer Capability                    | Lists printer capabilities (paper orientation and size, type and location of printer) for each printer, one record per printer.                           |
| F986164      | System - 910<br>System Local                                | Output Conversions                    | Lists printer output conversions defined for each printer, one record per printer.                                                                        |
| F986165      | System Shared                                               | New Default Printer Table             | Stores the default printer information including the user, environment, host name, printer name, and the status.                                          |
| F986167      | System - 910<br>System Local                                | Printer Security                      | Reserved for future use.                                                                                                                                  |
| F9862        | Object Librarian<br>Object Librarian Local                  | Object Librarian -<br>Function Detail | Lists one record for each function contained in the source file.                                                                                          |

| Table   | Data Source                                   | Description                             | Purpose                                                                                                            |
|---------|-----------------------------------------------|-----------------------------------------|--------------------------------------------------------------------------------------------------------------------|
| F9863   | Object Librarian<br>Object Librarian Local    | Object Librarian - Object Relationships | Contains one record per business function per related object. This table is used when building business functions. |
| F9865   | Object Librarian<br>Object Librarian Local    | Form Information                        | Contains one record per interactive form, including online help information.                                       |
| F98710  | Central Objects Specifications                | Table Header                            | Holds table-specific information for tables created in TDA (BOBSPEC).                                              |
| F98711  | Central Objects Specifications                | Table Columns                           | Holds all column information for the table in TDA (DDCLMN).                                                        |
| F98712  | Central Objects Specifications                | Primary Index Header                    | TDA - Information pertaining to the primary index.                                                                 |
| F98713  | Central Objects Specifications                | Primary Index Detail                    | TDA - All fields that make up the primary index.                                                                   |
| F98720  | Central Objects Specifications                | Business View Specifications            | Holds all business-view specific information from BDA.                                                             |
| F98740  | Central Objects Specifications                | Event Rules - Link                      | Stores header file for event rules.                                                                                |
| F98741  | Central Objects Specifications                | Event Rules - Specification             | Contains actual event rules detail for a form.                                                                     |
| F98743  | Central Objects Specifications                | Data Structure Templates                | Contains one record for each template, for example, Data Structure for Business Function.                          |
| F98744  | Central Objects Specifications                | Media Object                            | Contains media object text for tools.                                                                              |
| F98745  | Central Objects Specifications                | Smart Field Named Mappings              | Contains smart field named mappings.                                                                               |
| F98750* | Central Objects Specifications                | FDA Text Information                    | Contains form design text for all languages for any generated application.                                         |
| F98751  | Central Objects Specifications                | FDA Specification Information           | Contains specifications for an application.                                                                        |
| F98752  | Central Objects Specifications                | FDA/SVR Header Information              | Contains summary information about each application.                                                               |
| F98753  | Central Objects Specifications                | FDA/SVR Detail Information              | Contains summary information about each form for each application.                                                 |
| F98760* | Central Objects Specifications                | RDA Text Information                    | Holds records that contain the report design aid text for all languages.                                           |
| F98761  | Central Objects Specifications                | RDA Specification Info                  | Holds records that contain report design aid setup information.                                                    |
| F98762  | Central Objects Specifications                | JDEBLC - Behavior Information           | Contains business function specifications.                                                                         |
| F9882   | System - 910<br>Planner - 910<br>System Local | Checkout Log table                      | Logs all transactions that take place to objects.                                                                  |
| F98825  | System - 910                                  | Package Deployment Scheduling           | Contains information for deploying client packages, such as group user ID and package assignment.                  |
| F9883   | System - 910                                  | Release 9.1 Network Locations table     | Contains information for deploying server packages, such as package assignments.                                   |



| <b>Table</b> | <b>Data Source</b>                               | <b>Description</b>                        | <b>Purpose</b>                                                                                                                                           |
|--------------|--------------------------------------------------|-------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------|
| F9885        | System - 910<br>System Local                     | Install Package Header                    | Contains one record per package.                                                                                                                         |
| F9886        | System - 910<br>System Local                     | Install Package Detail                    | Contains one record per package per product code or object to be included in the package.                                                                |
| F9887        | System - 910<br>System Local                     | Install Package Build History             | Lists each time the package is built.                                                                                                                    |
| F9888        | System - 910<br>Planner - 910<br>System Local    | Merge Log                                 | Contains temporary message logging for merges.                                                                                                           |
| F98800D*     | Control Tables                                   | Process Master - Alternative Description  | Contains multiple language information for the F98800 table.                                                                                             |
| F98800T      | Control Tables                                   | Process Master Supplemental Information   | Categorizes Composer processes.                                                                                                                          |
| F98810D*     | Control Tables                                   | Activity Master - Alternative Description | Contains multiple language information for the F98810 table.                                                                                             |
| F98810       | Control Tables                                   | Activity Master                           | Contains workflow activity information.                                                                                                                  |
| F98811       | Control Tables                                   | Activity Specifications                   | Contains workflow activity specifications stored as event rules.                                                                                         |
| F98830       | Control Tables                                   | Process Activity Associations             | Contains workflow activity relationships.                                                                                                                |
| F98840       | Control Tables                                   | Organizational Structure Master           | Contains the defining data for organizational models.                                                                                                    |
| F98845       | Control Tables                                   | Organizational Structure Rule             | Contains the data that ties workflows to organizational models.                                                                                          |
| F98860       | Control Tables                                   | Process Instance                          | Contains the instances of workflow processes.                                                                                                            |
| F98865       | Control Tables                                   | Activity Instance                         | Contains the instances of workflow activities within processes.                                                                                          |
| F98881       | System - 910<br>System - Local                   | Specification Merge Logging               | Contains logging information generated from the Specification Merge for upgrade, update, and the Specification Merge and Object Librarian Merge reports. |
| F9889        | System - 910<br>System - Local                   | Deployment Location Master                | Lists records for each tier with system and help information. This table is used only for multitier deployment.                                          |
| F98891       | System - 910<br>System - Local                   | Deployment Location Path Code             | Lists records with packages and help information. This table is used only for multitier deployment.                                                      |
| F98892       | System - 910<br>System - Local                   | Package Deployment Scheduling             | Lists scheduling information for a multitier environment.                                                                                                |
| F98950       | Central Objects Specifications<br>System - Local | User Overrides table                      | Contains application version information: application, version, and user who entered it.                                                                 |
| F98980       | System - 910<br>System - Local                   | Font Override by Language                 | Lists languages with information on corresponding display fonts.                                                                                         |
| F98BLOB      | System - 910                                     | DB2 BLOB Support                          |                                                                                                                                                          |

| Table    | Data Source                                    | Description                                   | Purpose                                                                                                                                           |
|----------|------------------------------------------------|-----------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------|
| F98CONST | System - 910<br>System - Local                 | Table of Constants                            | Lists constants for report design aid and form design aid.                                                                                        |
| F98DRENV | System - 910<br>System - Planner               | Data Replication Environment Mapping table    | Determines which path codes to update for data dictionary replication.                                                                            |
| F98DRLOG | System - 910<br>Server Map<br>System - Planner | Data Replication Change Log                   | Contains one record for each replicated change. The table information is stored as a BLOB.                                                        |
| F98DRPCN | System - 910<br>Server Map<br>System - Planner | Data Replication Pending Change Notifications | Contains one record for each replicated change for each subscriber. Records are deleted as subscribers are notified.                              |
| F98DRPUB | System - 910<br>System - Planner               | Data Replication Publisher                    | Lists definitions of published objects.                                                                                                           |
| F98DRSUB | System - 910<br>System - Planner               | Data Replication Subscribers                  | Defines each subscriber.                                                                                                                          |
| F98EVDTL | System - 910<br>System - Local                 | Event Detail file                             | Filters events displayed in Form Design Aid (FDA) or Universal Batch Engine (UBE) design.                                                         |
| F98EVHDR | System - 910<br>System - Local                 | Event Header file                             | Stores event description and event ID. This table is used for all event rules.                                                                    |
| F98MOQUE | System - 910<br>System - Local                 | Media Object Queues                           | Contains path codes to locations of multimedia objects.                                                                                           |
| F98OWSEC | System - 910<br>System - Local                 | Release 9.1 Security                          | Contains the security tables that store the Release 9.1 user name and password for obtaining database user and password for certain data sources. |
| F98TMPL  | System - 910<br>System - Local                 | Templates                                     |                                                                                                                                                   |
| F98VAR   | System - 910<br>System - Local                 | Table of Variables                            | Contains commonly used event rule variables.                                                                                                      |
| GT92002  | Data Dictionary                                | Data Dictionary - Glossary Information        | Contains column in data dictionary with descriptions of data dictionary items.                                                                    |
| GT9860A  | Object Librarian                               | Object Librarian Generic Text Structure       | Contains notes for objects in the Object Librarian.                                                                                               |
| GT9862A  | Object Librarian                               | Business Function Notes                       | Contains notes for business functions.                                                                                                            |
| GT98DSA  | Object Librarian                               | Data Structure Notes - Structure and Item     | Contains notes for data structures.                                                                                                               |
| GT98DSB  | Object Librarian                               | Data Structure Notes - Structure and Item     | Contains notes for data structures.                                                                                                               |
| GT98TMPL | Object Librarian                               | Media Object Templates                        | Contains templates that can be used for any attachment.                                                                                           |

---

## Working with Reports

During the installation, upgrade, and cumulative update processes, JD Edwards EnterpriseOne creates reports that show detailed information about the plan and summarize the status of the environment builds. During upgrades and cumulative updates, additional reports summarize the status of tables merges.

This chapter discusses:

- [Section 25.1, "Installation Planner Validation Report \(R9840B\)"](#)  
This report is for installation, upgrade, and cumulative update customers.
- [Section 25.2, "Table and Index Creation \(R98407\)"](#)  
This report is for upgrade and cumulative update customers.
- [Section 25.3, "Environment Database Creation Report \(R98403\)"](#)  
This report is for installation, upgrade and cumulative update customers.
- [Section 25.4, "Data Dictionary Specification Merge Report and Data Dictionary Text Merge Report \(R98722C and R98722T\)"](#)  
This report is for upgrade and cumulative update customers only.
- [Section 25.5, "Object Librarian Modifications Report \(R9840D\)"](#)  
This report is for upgrade and cumulative update customers only.
- [Section 25.6, "Async Launch \(R98405A\)"](#)  
This report is for upgrade and cumulative update customers only.
- [Section 25.7, "Report on Table Conversions \(R984052\)"](#)  
This report is for upgrade and cumulative update customers only.
- [Section 25.8, "Object Specification Merge Report \(R98700\)"](#)  
This report is for upgrade and cumulative update customers only.
- [Section 25.9, "Index Recreation \(R9698713\)"](#)  
This report is for installation, upgrade and cumulative update customers.
- [Section 25.10, "Pathcode Copy \(R9800942\)"](#)  
This report is for installation, upgrade and cumulative update customers.

## 25.1 Installation Planner Validation Report (R9840B)

---

**Note:** This report is used by installation, upgrade, and cumulative update customers.

---

All processes use version XJDE0001 of this report.

The Installation Planner Validation report summarizes the status of the installation plan and verifies that the plan information is correct before you run the Installation Workbench

### 25.1.1 Setting Processing Options

The Extra Info tab contains these options:

| Option                                  | Value                                                                                                                                                                                               |
|-----------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Additional data source information flag | Enter Y to include additional information.                                                                                                                                                          |
| OCM Information Flag                    | Enter Y to see all Object Configuration Manager (OCM) information for the current data selection.<br>Enter D to select all default records.<br>Enter N to prevent OCM records from being displayed. |
| OCM Differences Flag                    | Enter Y to see OCM differences between the new environment and the previous environment.                                                                                                            |
| Path Code Information Flag              | Enter Y to display all path code information for the plan(s) in the data selection                                                                                                                  |
| Update the Plan Status (10 – 60)        | Enter 30                                                                                                                                                                                            |

### 25.1.2 How to Read the Report

Use the Installation Planner Validation report summary section to review basic information about the installation, upgrade, or cumulative update; the number of records validated; and the types of processes run.

Review the main body of the report to verify that each data source, machine, and package build in the plan was created successfully. To verify, each detail line should have the value *Record Validated* in the far right column.

The report includes the status of the following record types:

- Location
- Data sources (listed by database type)
- Environments
- Path codes
- Object Configuration Manager (OCM)
- Machines
- Table conversions
- Control table merges
- Specification table merges
- Packages

A summary should appear at the end of the report verifying that all records were validated and the plan status was updated to 30.

## 25.2 Table and Index Creation (R98407)

JD Edwards EnterpriseOne creates a report for each environment that is being upgraded. It creates new tables and indexes and recreates changed tables and indexes based on the F9698710 and F9698712 tables. It also reads the F9843 table to regenerate additional tables that do not have spec changes or to prevent regeneration of tables or indexes that will be converted in table conversion workbench or in post-workbench conversions.

The R98407 program creates a log of the actions it will perform against the database. The log table is the F984072 table. When the R98407 program is rerun it creates any items that are not at successful status and prints all items on the report.

## 25.3 Environment Database Creation Report (R98403)

Release 9.1 creates an Environment Database Creation report for each environment that is part of your plan. For each environment, you can choose to load either production or demonstration data.

Users performing installations and upgrades should run version XJDE0001.

Users performing cumulative updates should run version XJDE0004.

Upgrade users should run XJDE0005 because the update process updates only generic text. When running against pristine data, these users should run version XJDE0024.

The environment database creation copies the System data source (previous release) to the System - 910 data source. The System data source is release specific. The report is read and errors are processed in the same way as they are for the regular Environment Database Creation.

### 25.3.1 Setting Processing Options

These processing options are the typical processing options for each version of the Environment Database Creation report.

#### 25.3.1.1 Version XJDE0001 for Installations and Upgrades

The Environment Tab contains these options:

| Option                                                               | Values                                                                                                          |
|----------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------|
| Enter the Environment for the database to be created.                | Leave this field blank.                                                                                         |
| Enter the Data Source for the database to be created.                | Leave this field blank.                                                                                         |
| Enter a 1 to load Production Data or a 2 to load Demonstration Data. | Enter 2. The default is 1.<br>If this report is called from another process, the system passes in this flag.    |
| Enter the source Data Source for Loading of Data.                    | Enter <i>OneWorld Local</i> .<br>If this report is called from another process, the system passes in this flag. |
| Enter the Source Environment for the database to be copied from.     | Leave this field blank.<br>If this report is called from another process, the system passes in this flag.       |

The Update Tab contains the following options:

| Option                                                                                     | Value                                                                                                  |
|--------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------|
| Enter a 1 for Proof Mode or a 2 to create the Environment Database.                        | Enter 2.<br>The default is Proof Mode.                                                                 |
| Enter a A to recreate existing tables in data sources that allow automatic table creation. | Leave this field blank.<br>The default is not to recreate tables.                                      |
| Enter a 1 to only copy tables that exist in the source data source.                        | Leave this field blank.                                                                                |
| Enter a Y to add records without clearing the target table.                                | Leave this field blank.<br>This is used for language tables. The default is to clear the target table. |

The Print Tab contains these options:

| Option                              | Value                                                         |
|-------------------------------------|---------------------------------------------------------------|
| Enter a 1 to only print exceptions. | Leave this field blank.<br>The default is to print all lines. |

The Licensing Tab contains these options:

| Option                                                                             | Value                                                           |
|------------------------------------------------------------------------------------|-----------------------------------------------------------------|
| Enter a Y to create all tables or a N to create licensed tables only.              | Leave this field blank.<br>The default is to create all tables. |
| Enter a Y to print all tables in the report or an N to print licensed tables only. | Leave this field blank.<br>The default is to print all tables.  |

### 25.3.1.2 Version XJDE0004 for Updates

The Environment Tab contains these options:

| Option                                                              | Value                                                                                                                              |
|---------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------|
| Enter the Environment for the database to be created.               | Leave this field blank.                                                                                                            |
| Enter the Data Source for the database to be created.               | Leave this field blank.                                                                                                            |
| Enter a 1 to load Production Data or a 2 to load Demonstration Data | Enter 1.<br>The default is to load production data. If this report is called from another process, the system passes in this flag. |
| Enter the source Data Source for Loading of Data.                   | Leave this field blank.<br>If this report is called from another process, the system passes in the data source.                    |
| Enter the Source Environment for the database to be copied from.    | Leave this field blank.<br>If this report is called from another process, the system passed in the Source Environment.             |

The Update Tab contains these options:

| Option                                                                                    | Value                                                                                                                                                                            |
|-------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Enter a 1 for Proof Mode or a 2 to create the Environment Database.                       | Enter <b>2</b> .<br>The default is Proof Mode.                                                                                                                                   |
| Enter a A to recreate existing tables in data sources that allow automatic table creation | Leave this field blank.<br>The default is not to recreate tables.                                                                                                                |
| Enter a 1 to only copy tables that exist in the source data source                        | Leave this field blank.<br>The default is to copy all tables.                                                                                                                    |
| Enter a Y to add records without clearing the target table.                               | Enter <b>N</b> .<br>to indicate you do not want to add records without clearing the target table.<br>This is used for language tables. The default is to clear the target table. |

The Print Tab contains this option:

| Option                              | Value                                                         |
|-------------------------------------|---------------------------------------------------------------|
| Enter a 1 to only print exceptions. | Leave this field blank.<br>The default is to print all lines. |

The Licensing Tab contains these options:

| Option                                                                             | Value                                                           |
|------------------------------------------------------------------------------------|-----------------------------------------------------------------|
| Enter a Y to create all tables or an N to create licensed tables only.             | Leave this field blank.<br>The default is to create all tables. |
| Enter a Y to print all tables in the report or an N to print licensed tables only. | Leave this field blank.<br>The default is to print all tables.  |

### 25.3.1.3 Version XJDE0024 for Running Pristine Data

The Environment Tab contains these options:

| Option                                                               | Value                                                                                                                                      |
|----------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------|
| Enter the Environment for the database to be created.                | Leave this field blank.                                                                                                                    |
| Enter the Data Source for the database to be created.                | Leave this field blank.                                                                                                                    |
| Enter a 1 to load Production Data or a 2 to load Demonstration Data. | Enter <b>2</b> .<br>The default is to load production data. If this report is called from another process, the system passes in this flag. |
| Enter the source Data Source for Loading of Data.                    | Enter <i>OneWorld Local</i> .<br>If this report is called from another process, the system passes in the data source.                      |
| Enter the Source Environment for the database to be copied from.     | Leave this field blank.<br>If this report is called from another process, the system passes in the Source Environment .                    |

The Update Tab contains these options:

| Option                                                                                     | Value                                                                                                  |
|--------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------|
| Enter a 1 for Proof Mode or a 2 to create the Environment Database.                        | Enter 2.<br>The default is Proof Mode.                                                                 |
| Enter a A to recreate existing tables in data sources that allow automatic table creation. | Enter A.<br>The default is not to recreate tables.                                                     |
| Enter a 1 to only copy tables that exist in the source data source.                        | Leave this field blank.<br>The default is to copy all tables.                                          |
| Enter a Y to add records without clearing the target table.                                | Leave this field blank.<br>This is used for language tables. The default is to clear the target table. |

The Print Tab contains these options:

| Option                              | Value                                                         |
|-------------------------------------|---------------------------------------------------------------|
| Enter a 1 to only print exceptions. | Leave this field blank.<br>The default is to print all lines. |

The Licensing Tab contains the following options:

| Option                                                                            | Value                                                           |
|-----------------------------------------------------------------------------------|-----------------------------------------------------------------|
| Enter a Y to create all tables or a N to create licensed tables only.             | Leave this field blank.<br>The default is to create all tables. |
| Enter a Y to print all tables in the report or a N to print licensed tables only. | Leave this field blank.<br>The default is to print all tables.  |

#### 25.3.1.4 How to Read the Report

Review the reports to make sure the environments were created and configured successfully. The report includes a status for each table:

- Tables that have been created correctly have a status of Success.
- Tables that had errors have a status of Failure.
- Tables can have a status of No Action.

The Environment Database Creation report does not have a cover page. The reports list the following properties of each table (object) created:

| Object headings    | Description                                                                                                            |
|--------------------|------------------------------------------------------------------------------------------------------------------------|
| Syst Code          | System Code. Shows the JD Edwards EnterpriseOne product code for the database listed in the Member Description column. |
| Object Name        | Displays the alphanumeric name of the database.                                                                        |
| Member Description | Displays the full name of the database being created.                                                                  |
| Data Source        | Displays the data source toward which this member points.                                                              |
| Crt Tbl            | Create Table. Shows whether tables are being created for this database.                                                |
| Copy Data          | Shows whether the table was copied with data.                                                                          |



| Object headings         | Description                                                                                    |
|-------------------------|------------------------------------------------------------------------------------------------|
| Rec Insrt               | Record Insert. Displays the number of records inserted.                                        |
| Rec Fail                | Record Failure. Displays the number of records that failed.                                    |
| Copied from Data Source | Displays whether the table was copied with data and the data source from which it was copied.  |
| Status                  | Displays one of the following statuses for the table creation: Success, Failure, or No Action. |
| Source DS Warnings      | Displays any errors or warnings associated with the source data source.                        |
| Target DS Warnings      | Displays any errors or warnings associated with the target data source.                        |

### 25.3.1.5 Errors and How to Resolve Them

A report occasionally lists a status of Failure for tables that are created successfully. These failures are generally due to problems creating indices and are not critical for the successful installation of the software.

During an upgrade or cumulative update, you could receive failures for some tables. To confirm successful table creation, verify that the following tables were created successfully:

- F0007Z1
- F00092
- F0086
- F03B11
- F03B14
- F03B112
- F060116
- F06106
- F08042
- F08330
- F0911
- F1501B
- F1721
- F1731
- F17111
- F30006Z1
- F3002Z1
- F3003Z1
- F3460Z1
- F39062
- F4077
- F4106
- F4111

- F41508
- F4600
- F4812H
- F5215
- F7302
- F986113

Reports frequently list a status of No Action for tables the system created successfully. This status is accompanied by source and target data source warnings for these tables to explain why no action was taken. These warnings are normal and you can ignore them. The most common reasons for the warnings are because the source and target data sources are the same or the table was created by a previously installed environment.

When the source and target are the same, the report lists the following warnings:

| Source data source warning | Target data source warning |
|----------------------------|----------------------------|
| Source Same as Target      | Existing table             |

This commonly occurs when the "copied from" data source is the same as the "target" data source (where the table is mapped), and often occurs for the following tables:

| UDC tables      | Menu tables                     |
|-----------------|---------------------------------|
| F0004 and F0005 | F0082, F00821, F0083, and F0084 |

If you load multiple environments that share the same mappings (for example, DV910 and TS910), the first environment loaded (DV910 in this case) lists the tables with a Success status. The second environment (TS910) lists any tables already created during the first environment load with a status of No Action and a target data source warning of Existing Table.

The No Action status and Existing Table warning for the second (TS910) environment are normal. You can verify that any table with a target data source warning of Existing Table has been created successfully by verifying it was created while loading a previous environment.

## 25.4 Data Dictionary Specification Merge Report and Data Dictionary Text Merge Report (R98722C and R98722T)

---

---

**Note:** These reports are only for customers installing Release 9.1 on the IBM i. The reports are not for upgrade or cumulative update customers.

- PY910
  - DV910
  - PS910
  - PD910
  - DEP910
- 
-

The Control Table Workbench creates these reports:

- Data Dictionary Specification Merge report (R98722C)
- Data Dictionary Text Merge report (R98722T)

Run version ZJDE0001 for both of these reports.

The data dictionary merge reports show the results of merging modified data dictionary information into the Release 9.1 data dictionary.

### 25.4.1 Processing Options

The processing options for both reports are the same.

The Merge Option tab contains the option to select update mode.

### 25.4.2 Errors and How to Resolve Them

Most failures on these reports result from attempting to merge data items that do not exist in the target data dictionary into JD Edwards EnterpriseOne. These failures are normal and can be ignored. If every item on the report lists a merge status of "failed," then the source data dictionary could not be found to perform the merge. Verify your source data dictionary and run the merge again.

## 25.5 Object Librarian Modifications Report (R9840D)

---

**Note:** This report is used only by upgrade and cumulative update customers.

---

The Object Librarian Modifications report is created when running the Installation Workbench program before you merge any objects. It shows which objects from the previous release are flagged to be merged into the new release as well as which components of that object have been changed or added.

This report does not have processing options.

If you have made custom modifications to your business data, you can use the Customization Object Analyzer to identify customizations in order to determine the impact and level of effort to retro-fit the customizations into the newer release of JD Edwards EnterpriseOne. The Customization Object Analyzer is a summary and detail report that reads the custom modifications that have been made to your system. The reports are:

- Object Customization Summary Report
- Object Customization Detail Report

#### See Also

The section entitled *Customization Object Analyzer* in the *JD Edwards EnterpriseOne Tools Software Updates Guide*.

## 25.6 Async Launch (R98405A)

Table conversion workbench launches the R98405A program for every conversion when running them asynchronously, regardless of whether they will be run on the Deployment Server or Enterprise Server. The R98405A program launches the

conversion. When all conversions complete, you can review their status by running the R984052 report, which is described in [Report on Table Conversions \(R984052\)](#).

## 25.7 Report on Table Conversions (R984052)

Report on Table Conversions is created by Table Conversion Workbench when conversions are run asynchronously. The report shows the results for each table conversion and merge. Review this report to verify that each table conversion or merge completed normally.

### 25.7.1 How to Read the Report

The following column headings appear in this report:

| Object headings      | Description                                                                                   |
|----------------------|-----------------------------------------------------------------------------------------------|
| Environment          | The new environment being converted or merged to.                                             |
| Previous Environment | The environment being converted or merged from.                                               |
| Obj Name             | Object Name. The name of the table being converted or merged.                                 |
| Program Name         | The identification number of the table conversion or merge program.                           |
| Version              | The version of the table conversion or merge.                                                 |
| Status               | The status of the table creation. A successful completion is indicated by Completed Normally. |

## 25.8 Object Specification Merge Report (R98700)

---

---

**Note:** This report is used only by upgrade and cumulative update customers.

---

---

The Object Specification Merge report is closely related to the Object Librarian Modification report. This report is created during the Specification Table Merge Workbench. It shows the results of the merge for each modification and summarizes the activity shown on each Specification Merge Multithread Driver Report (R987001). Review this report to verify that all modifications were successfully merged.

### 25.8.1 Processing Options

This report has processing options for each of the following versions:

| Version number | Version Title               |
|----------------|-----------------------------|
| ZJDE0001       | UPGRADE – normal processing |
| ZJDE0002       | UPDATE – normal processing  |
| ZJDE0003       | UPGRADE – restart           |
| ZJDE0004       | UPDATE – restart            |
| ZJDE0005       | UPGRADE – reprint           |
| ZJDE0006       | UPDATE – reprint            |
| ZJDE0007       | Internet Code Change Merge  |

## 25.8.2 How to Read the Report

This report is designed to help you review the objects that will be merged. If the report shows any objects that you do not want to be merged, you can change the modification flag and the merge option so that the modification will not be merged into the new release. Similarly, you can verify that all modifications you want to be merged into the new release are flagged appropriately.

Two sets of headings appear on this report: one for the modified object, and a subheading for the modified components of that object.

| Object headings    | Description                                                                      |
|--------------------|----------------------------------------------------------------------------------|
| Obj Type           | Type of object. For example, APPL for application or BSFN for business function. |
| Object Name        | Alphanumeric identifier for the object.                                          |
| Member Description | Brief description of the object.                                                 |
| Syst Code          | Product code the object belongs to.                                              |
| Location           | The machine the object is on, which is typically the Deployment Server.          |
| Path Code          | Path code in the previous release that the object belongs to.                    |
| Mod Flag           | Whether the object has been changed (C).                                         |
| Mrg Opt            | Whether the object will be merged (1 is yes, 0 is no).                           |
| Date Modified      | Last date the object was changed.                                                |

| Component headings | Description                                                                                                                                                                        |
|--------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Object Component   | Part of the object that was changed or added (for example, forms and event rules).                                                                                                 |
| Status             | Successfully read components will have a status of changed or added. If the status is "failed," the batch application could not read the modified component.                       |
| Description        | Brief description of the change. If the status is "failed," the description will be a brief explanation of the error. These errors usually result from a failure to read the file. |

The report includes the status of the following record types:

- Package names
- Source environments
- Target environments
- Advanced options

The report is broken into four sections:

- The first section is a cover page which summarizes the processing options used to generate the report.
- The second section is a list of the completion statuses of these objects as described in this table:

| Object           | Status               | Description                                                                                                                                                                                                                                                                                                 |
|------------------|----------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Object Librarian | Success              | Indicates the number of objects successfully added or updated.                                                                                                                                                                                                                                              |
|                  | System 88 Warning    | Indicates the system detected custom modifications for an object in a JD Edwards EnterpriseOne product code that does not exist in the new Object Librarian. Object Librarian objects were obsoleted by JD Edwards EnterpriseOne, so you, as the customer, need to decide how this affects your procedures. |
|                  | Errors: Setup issues | Indicates setup issues. To verify that your setup is correct you should: <ul style="list-style-type: none"> <li>■ Verify access authority to the source and target Object Librarian.</li> <li>■ Check the JDE.LOG for insert or delete errors on the F986* tables.</li> </ul>                               |
| Versions List    | Success              | Indicates the number of copies successfully added or updated. Specification Merge totals indicate the number of added, replaced, and merged objects.                                                                                                                                                        |
|                  | PO Change Warning    | Indicates the processing options format for a ZJDE version has changed. Review and update options on these versions.                                                                                                                                                                                        |
|                  | Errors               | Indicates the number of errors that occurred during the merge. Check the JDE.LOG for more complete messages dealing with F983051 or F98306.                                                                                                                                                                 |
| Central Objects  | No Action Taken      | This category is applicable for ZJDE versions. It shows that the version data was transferred but that no specification merges occurred.                                                                                                                                                                    |
|                  | Warnings and Errors  | Indicates that details for warnings and errors occurred. You can locate these in the detailed fourth section of the report.                                                                                                                                                                                 |
|                  | Not Processed        | Indicates that the merge did not finish. Evaluate the errors and rerun the merge using a Restart version number.                                                                                                                                                                                            |
|                  | In Process           | Indicates a fatal error occurred in the merge business function before completing the object. Evaluate and fix the error conditions before restarting the merge.                                                                                                                                            |

- The third section summarizes the merge statuses of each object in one line per object with these column headings:

| Object headings        | Description                                                                  |
|------------------------|------------------------------------------------------------------------------|
| Obj Type               | Object type, such as BSFN is a business function and TBLE is a table.        |
| Object Name            | Alphanumeric identifier for the object.                                      |
| Version                | The report version number run for this object.                               |
| Syst Code              | Product code.                                                                |
| Merge Action           | Indicates the object on source was added, replaced, or merged on the target. |
| Object Librarian Merge | Completion status for Object Librarian updates for this object.              |
| Versions List Merge    | Completion status for Versions List updates for this object.                 |

| Object headings | Description                                                |
|-----------------|------------------------------------------------------------|
| Merge Status    | Completion status for Specification merge for this object. |
| Date Completed  | Date the object was merged.                                |
| Time Updated    | Time the object was updated.                               |

- The fourth section contains detail information for each merged object and includes these common errors:
  - Insert errors.
  - Header and source files that fail to copy.
  - Invalid dictionary items for tables or views.
  - Invalid files name or column in business views.

This table explains the column headings in the section:

| Object headings | Description                                                                                                                                            |
|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------|
| Object Name     | Alphanumeric identifier for the object.                                                                                                                |
| Version         | The report version number run for this object. "+" indicates a template for a report.                                                                  |
| Obj Type        | Object type. For example, BSFN is a business function and TBLE is a table.                                                                             |
| Syst Code       | Product code.                                                                                                                                          |
| Merge Action    | Indicates the object on target source was added, replaced, or merged.                                                                                  |
| Merge Status    | Success means that the object and all modified components were merged successfully. Warning means that one or more components did not merge correctly. |
| Mod Flag        | Modification flag.                                                                                                                                     |
| Date Completed  | Last date the object was modified.                                                                                                                     |
| Time Updated    | Last time the object was updated.                                                                                                                      |

This table describes the column subheadings:

| Object headings | Description                                                                                                                                                                                     |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Description     | Type of object component, such as a template, a field or an event rule.                                                                                                                         |
| Status          | Status of the merge for that particular component. Success is denoted by a status of Added or Changed. Unsuccessful merges are noted with Failed or Error.                                      |
| Description     | This can be a brief description of the component or, in the case of a failure, an error message describing the failure. Disable and Append indicates event rules which require developer fixes. |

### 25.8.3 Errors and How to Resolve Them

If an error occurs which stops the merge process there are two ways to recover, RESTART or RERUN. If the process stops during the Object Librarian merge or the Versions List merge, no recovery of specifications is necessary. Just rerun the merge after fixing the problem that initially caused the error. If the Merge Status column indicates that some items have merged or started merging, you must do a RESTART.

A RESTART merges items which are at a merge status of "Not Processed". All other statuses are skipped. Whether original specifications must be restored for objects with a status of "Error," "Warning," or "In Process," the status must be evaluated based on the merge action type.

| Merge ActionRestore Target Specifications | Merge Status  |
|-------------------------------------------|---------------|
| ADDNO                                     | Any           |
| REPLACENO                                 | Any           |
| CHANGENO                                  | NOT PROCESSED |
| CHANGENO                                  | SUCCESS       |
| CHANGEYES                                 | ERROR         |
| CHANGEYES                                 | IN PROCESS    |
| CHANGEYES                                 | WARNING       |

To restore specifications for a single object, use Object Transfer to copy the object from the new pristine environment to the target environment.

#### 25.8.3.1 Modifying the Merge Status of an Object

This release contains a new application (P98700) for an interactive view of the progress during merges. F98810 is a new table used to control and track the merge process. Each record is time stamped as processing occurs. Before a RESTART operation it is possible to change the merge status to Not Processed, following the rules above, to repeat a merge for a specific object.

*See Also*

#### [Restarting the Specification Merge](#)

*Release 9.1 on a Cluster* section in the *JD Edwards EnterpriseOne Tools Server and Workstation Administration Guide*.

The summary report shows the status of the completed Object Librarian, Versions List, and Specifications Merges.

### 25.8.4 Compare Tables and Indexes Against Central Objects or TAM Specifications (R9698711)

You can run the R9698711 program from Batch Versions after an install or upgrade. The report compares database tables and indexes against Release 9.1 Central Objects or TAM specifications. Use this report to verify the format of Release 9.1 tables in your database.

### 25.8.5 UDC Merge Report, Data Dictionary Merge Report, and Menu Merge Report

---

**Note:** These reports are used only by upgrade and cumulative update customers.

---

The UDC Merge, Data Dictionary Merge, and Menu Merge programs produce these reports:



- UDC Merge and Exception report (R987241)
- Data Dictionary Merge and Exception report (R989200)
- Menu Merge report (R989751B)

These three merge reports are created when you run Control Table Workbench during *Running Installation Workbench* in the JD Edwards EnterpriseOne Upgrade Guide. These reports show the status of the UDCs, data dictionary items, and menus that were merged.

### 25.8.5.1 Setting Processing Options

The processing options are the same for all of these merge reports.

#### 25.8.5.1.1 UDC Merge and Exception Report and Data Dictionary Merge and Exception Report

The Release Info tab contains these options:

| Option                               | Value                                                   |
|--------------------------------------|---------------------------------------------------------|
| Update Mode                          | Enter 2.<br>Default is Update Mode.                     |
| Environment Name for the Old Release | Enter a valid environment name. For example, PRODB7334. |
| Old Release Name                     | Enter the name of the old release. For example, B7334.  |
| New Release Name                     | Enter the name of the new release. For example, E910.   |
| Merge Language Codes                 | Enter N if language codes do not need to be merged.     |

#### 25.8.5.1.2 Menu Merge and Exception Report

The Merge tab contains these options:

| Option                               | Value                                                                  |
|--------------------------------------|------------------------------------------------------------------------|
| Update Mode                          | Enter 2.<br>The default is update mode.                                |
| Environment Name for the Old Release | Enter the name of the old release environment. For example, PRODB7334. |
| Old Release Name                     | Enter the name of the old release. For example, E910.                  |
| New Release Name                     | Enter the name of the new release. For example, E910.                  |

### 25.8.5.2 How to Read the Report

Each report has a cover page that contains a summary of and basic information about your upgrade, release information, source mappings, mappings from replication, additional table mappings, and the mode in which the report was run.

The main text of the report indicates the status of Environment and Release Information, Source UDC Table Mappings, UDC Table Mappings from Replication, Additional Table Mappings, and Mode.

If the entire merge is successful, a message appears at the end of each report:

- For the UDC Merge and Exception report: "UDC Merge process completed successfully with no errors and warnings."
- For the Data Dictionary Merge report: "Data dictionary merge process completed successfully with no errors and warnings."

- For the Menu Merge report: "Menu merge process completed successfully with no errors and warnings."

---

**Note: Tools Release 9.1 Update 2.**

If you have made custom modifications to your business data, you can use the Application Configuration Analyzer to verify that your changes were carried forward to the new release. The Application Configuration Analyzer is a set of reports which identify differences for processing options, data dictionary (DD) items, and user defined codes (UDCs) between releases or environments. These reports are:

- Versions Compare
- User Defined Codes Compare
- Data Dictionary Compare

**See Also**

- The section entitled: *Application Configuration Analyzer* in the *JD Edwards EnterpriseOne Tools Software Updates Guide*.
- 

**25.8.5.3 Errors and How to Resolve Them**

If warnings appear in the report, the merge finished. Check the warning log printed at the end of the report to diagnose any problems that may have occurred.

Errors appear only when the problem is severe enough to stop processing. If the report contains error messages, the merge process was not completed. Information regarding any errors is also printed in the log at the end of the report.

This following error message appears if change tables do not have records associated with the From Release and To Release settings: "DD Merge process terminated: Check Error Log."

## 25.9 Index Recreation (R9698713)

The R9698713 program is run from Batch Versions after an install or upgrade. It compares database indexes versus Release 9.1 index specifications in F98712 and F98713. If you run the program in Update mode, it recreates incorrect indexes.

## 25.10 Pathcode Copy (R9800942)

Environment Workbench runs the R9800942 program for each custom environment whose path code is to be copied from an existing path code. It copies the directory structure of the existing path code on the Deployment Server. It also copies `package.inf` and records in the package definition tables F9603, F9631, F96021 and F96215, replacing the path code names in those items.

## Understanding Data Source Charts

This chapter discusses these data sources:

- [Section 26.1, "Business Data"](#)
- [Section 26.2, "Central Objects"](#)
- [Section 26.3, "Control Tables"](#)
- [Section 26.4, "Data Dictionary"](#)
- [Section 26.8, "Local"](#)
- [Section 26.5, "Logic"](#)
- [Section 26.6, "Object Librarian"](#)
- [Section 26.7, "Language"](#)
- [Section 26.8, "Local"](#)
- [Section 26.9, "OWJRNL"](#)
- [Section 26.10, "Server Map"](#)
- [Section 26.11, "System"](#)
- [Section 26.12, "Versions"](#)

### 26.1 Business Data

This chart lists the characteristics of the Business Data data source.

| Field                                             | Valid Value for Client Access                                                                |
|---------------------------------------------------|----------------------------------------------------------------------------------------------|
| Data Source Name (list includes possible sources) | Business Data - PROD<br>Business Data - CRP<br>Business Data - TEST<br>Business Data - PS910 |
| Data Source Use                                   | DB                                                                                           |
| Data Source Type                                  | I                                                                                            |
| Object Owner ID                                   | Blank                                                                                        |
| Library Name (list includes possible libraries)   | PRODDTA<br>TESTDTA<br>CRPDTA<br>PS910DTA                                                     |

| Field                                            | Valid Value for Client Access                                                                   |
|--------------------------------------------------|-------------------------------------------------------------------------------------------------|
| Library List Name                                | RDB name of the IBM i<br><b>Note:</b> To find the IBM i RDB name, use the WRKRDBDIRE command.   |
| Database Name (list includes possible databases) | Business Data - PROD<br>Business Data - TEST<br>Business Data - CRPDTA<br>Business Data - PS910 |
| Server Name                                      | Name of the machine where your database resides                                                 |
| Platform                                         | IBM i                                                                                           |
| Use Table Owner                                  | Blank                                                                                           |
| Use Julian Dates                                 | Selected                                                                                        |
| Use Decimal Shift                                | Selected                                                                                        |
| Support for Updates                              | Selected                                                                                        |
| OCM Data Source                                  | Blank                                                                                           |
| LOB Data Source                                  | Selected                                                                                        |
| IBM i BLOB Support                               | Blank                                                                                           |

## 26.2 Central Objects

This chart lists the characteristics of the Central Objects data source.

| Field                                             | Client Access                                                                                                                                       |
|---------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------|
| Data Source Name (list includes possible sources) | Central Objects - PY910 (for CRP)<br>Central Objects - PS910 (for Prist)<br>Central Objects - PD910 (for Prod)<br>Central Objects - DV910 (for Dev) |
| Data Source Use                                   | DB                                                                                                                                                  |
| Data Source Type                                  | I                                                                                                                                                   |
| Object Owner ID                                   | Blank                                                                                                                                               |
| Library Name (list includes possible libraries)   | COPD910 (for Prod)<br>COPY910 (for CRP)<br>COPS910 (for Prist)<br>CODV910 (for Dev)                                                                 |
| Library List Name                                 | RDB name of the IBM i<br><b>Note:</b> To find the IBM i RDB name, use the WRKRDBDIRE command.                                                       |
| Database Name (list includes possible databases)  | Central Objects - PY910<br>Central Objects - PS910<br>Central Objects - PD910<br>Central Objects - DV910                                            |

| Field               | Client Access                                   |
|---------------------|-------------------------------------------------|
| Server Name         | Name of the machine where your database resides |
| Platform            | IBM i                                           |
| Use Table Owner     | Blank                                           |
| Use Julian Dates    | Selected                                        |
| Use Decimal Shift   | Selected                                        |
| Support for Updates | Selected                                        |
| OCM Data Source     | Blank                                           |
| LOB Data Source     | Selected                                        |
| IBM i BLOB Support  | Blank                                           |

## 26.3 Control Tables

This chart lists the characteristics of the Control Tables data source.

| Field                                             | Client Access                                                                                    |
|---------------------------------------------------|--------------------------------------------------------------------------------------------------|
| Data Source Name (list includes possible sources) | Control Tables - Prod<br>Control Tables - CRP<br>Control Tables - PS910<br>Control Tables - Test |
| Data Source Use                                   | DB                                                                                               |
| Data Source Type                                  | I                                                                                                |
| Object Owner ID                                   | Blank                                                                                            |
| Library Name (list includes possible libraries)   | PRODCTL<br>CRPCTL<br>PS910CTL<br>TESTCTL                                                         |
| Library List Name                                 | RDB name of the IBM i<br><b>Note:</b> To find the IBM i RDB name, use the WRKRDBDIRE command.    |
| Database Name (list includes possible databases)  | Control Tables - Prod<br>Control Tables - CRP<br>Control Tables - PS910<br>Control Tables - Test |
| Server Name                                       | Name of the machine where your database resides                                                  |
| Platform                                          | IBM i                                                                                            |
| Use Table Owner                                   | Blank                                                                                            |
| Use Julian Dates                                  | Selected                                                                                         |
| Use Decimal Shift                                 | Selected                                                                                         |
| Support for Updates                               | Selected                                                                                         |

| Field              | Client Access |
|--------------------|---------------|
| OCM Data Source    | Blank         |
| LOB Data Source    | Selected      |
| IBM i BLOB Support | Blank         |

## 26.4 Data Dictionary

This chart lists the characteristics of the Data Dictionary data source.

| Field               | Client Access                                                                                 |
|---------------------|-----------------------------------------------------------------------------------------------|
| Data Source Name    | Data Dictionary - 910                                                                         |
| Data Source Use     | DB                                                                                            |
| Data Source Type    | I                                                                                             |
| Object Owner ID     | Blank                                                                                         |
| Library Name        | DD910                                                                                         |
| Library List Name   | RDB name of the IBM i<br><b>Note:</b> To find the IBM i RDB name, use the WRKRDBDIRE command. |
| Database Name       | Data Dictionary - 910                                                                         |
| Server Name         | Name of the machine where your database resides                                               |
| Platform            | IBM i                                                                                         |
| Use Table Owner     | Blank                                                                                         |
| Use Julian Dates    | Selected                                                                                      |
| Use Decimal Shift   | Selected                                                                                      |
| Support for Updates | Selected                                                                                      |
| OCM Data Source     | Blank                                                                                         |
| LOB Data Source     | Selected                                                                                      |
| IBM i BLOB Support  | Blank                                                                                         |

## 26.5 Logic

This chart lists the characteristics of the Logic data source.

| Field            | Client Access                                                          |
|------------------|------------------------------------------------------------------------|
| Data Source Name | Name of the machine where your database resides                        |
| Data Source Use  | SVR                                                                    |
| Data Source Type | I                                                                      |
| Object Owner ID  | Blank                                                                  |
| Library Name     | xMAP (where x is the release to which you are installing, such as 910) |

| Field               | Client Access                                                                                                                              |
|---------------------|--------------------------------------------------------------------------------------------------------------------------------------------|
| Library List Name   | RDB name of the IBM i<br><b>Note:</b> Ensure the system value for QCCSID is 37.<br>To find the IBM i RDB name, use the WRKRDBDIRE command. |
| Database Name       | <i>machinename</i> - 910 Server Map                                                                                                        |
| Server Name         | Name of the machine where your database resides                                                                                            |
| Platform            | IBM i                                                                                                                                      |
| Use Table Owner     | Blank                                                                                                                                      |
| Use Julian Dates    | Selected                                                                                                                                   |
| Use Decimal Shift   | Selected                                                                                                                                   |
| Support for Updates | Selected                                                                                                                                   |
| OCM Data Source     | Blank                                                                                                                                      |
| IBM i BLOB Support  | Selected                                                                                                                                   |

## 26.6 Object Librarian

This chart lists the characteristics of the Object Librarian data source.

| Field               | Valid Value for Client Access                                                                 |
|---------------------|-----------------------------------------------------------------------------------------------|
| Data Source Name    | Object Librarian - 910                                                                        |
| Data Source Use     | DB                                                                                            |
| Data Source Type    | I                                                                                             |
| Object Owner ID     | Blank                                                                                         |
| Library Name        | OL910                                                                                         |
| Library List Name   | RDB name of the IBM i<br><b>Note:</b> To find the IBM i RDB name, use the WRKRDBDIRE command. |
| Database Name       | Object Librarian - 910                                                                        |
| Server Name         | Name of the machine where your database resides                                               |
| Platform            | IBM i                                                                                         |
| Use Table Owner     | Blank                                                                                         |
| Use Julian Dates    | Selected                                                                                      |
| Use Decimal Shift   | Selected                                                                                      |
| Support for Updates | Selected                                                                                      |
| OCM Data Source     | Blank                                                                                         |
| IBM i BLOB Support  | Blank                                                                                         |
| LOB Data Source     | Selected                                                                                      |

## 26.7 Language

This chart lists the characteristics of the Language data source, which applies to the Oracle tablespace on the Deployment Server.

| Field                                              | Valid Value for Oracle                                   |
|----------------------------------------------------|----------------------------------------------------------|
| Data Source Name (list includes possible sources)  | Language<br>Language – 910<br>For example, French – 910. |
| Data Source Use                                    | DB                                                       |
| Data Source Type                                   | N                                                        |
| Object Owner ID (list includes possible owner IDs) | Blank                                                    |
| Library Name                                       | Blank                                                    |
| Library List Name                                  | Blank                                                    |
| Database Name (list includes possible databases)   | Language<br>JDELanguage_F910                             |
| Server Name                                        | Local                                                    |
| Platform                                           | LOCAL                                                    |
| Use Table Owner                                    | Blank                                                    |
| Use Julian Dates                                   | Blank                                                    |
| Use Decimal Shift                                  | Blank                                                    |
| Support for Updates                                | Blank                                                    |
| OCM Data Source                                    | Blank                                                    |
| IBM i BLOB Support                                 | Blank                                                    |

## 26.8 Local

This chart lists the characteristics of the Local data source, which applies to the Oracle tablespace on the Deployment Server.

| Field                                              | Valid Value for Oracle                                                                |
|----------------------------------------------------|---------------------------------------------------------------------------------------|
| Data Source Name (list includes possible sources)  | Local<br>JDELocal - DV910<br>JDELocal - PS910<br>JDELocal - PD910<br>JDELocal - PY910 |
| Data Source Use                                    | DB                                                                                    |
| Data Source Type                                   | N                                                                                     |
| Object Owner ID (list includes possible owner IDs) | dbo                                                                                   |
| Library Name                                       | Blank                                                                                 |
| Library List Name                                  | Blank                                                                                 |



| Field                                            | Valid Value for Oracle                                                                            |
|--------------------------------------------------|---------------------------------------------------------------------------------------------------|
| Database Name (list includes possible databases) | JDELocal<br>JDEPlan910<br>JDECTL910<br>JDEDD910<br>JDESY910<br>JDEVL910<br>JDEOL910<br>JDEData910 |
| Server Name                                      | Local                                                                                             |
| Platform                                         | LOCAL                                                                                             |
| Use Table Owner                                  | Selected                                                                                          |
| Use Julian Dates                                 | Selected                                                                                          |
| Use Decimal Shift                                | Selected                                                                                          |
| Support for Updates                              | Selected                                                                                          |
| OCM Data Source                                  | Blank                                                                                             |
| LOB Data Source                                  | Blank                                                                                             |

## 26.9 OWJRNL

This chart lists the characteristics of the Journal data source.

| Field                                             | Valid Value for Client Access                                                                 |
|---------------------------------------------------|-----------------------------------------------------------------------------------------------|
| Data Source Name (list includes possible sources) | OWJRNL                                                                                        |
| Data Source Use                                   | DB                                                                                            |
| Data Source Type                                  | I                                                                                             |
| Object Owner ID                                   | Blank                                                                                         |
| Library Name                                      | OWJRNL                                                                                        |
| Library List Name                                 | RDB name of the IBM i<br><b>Note:</b> To find the IBM i RDB name, use the WRKRDBDIRE command. |
| Database Name                                     | OWJRNL                                                                                        |
| Server Name                                       | Name of the machine where your database resides                                               |
| Platform                                          | IBM i                                                                                         |
| Use Table Owner                                   | Blank                                                                                         |
| Use Julian Dates                                  | Selected                                                                                      |
| Use Decimal Shift                                 | Selected                                                                                      |
| Support for Updates                               | Selected                                                                                      |
| OCM Data Source                                   | Blank                                                                                         |
| IBM i BLOB Support                                | Blank                                                                                         |

## 26.10 Server Map

This chart lists the characteristics of the Server Map data source.

| Field               | Valid Value for Client Access                                                                 |
|---------------------|-----------------------------------------------------------------------------------------------|
| Data Source Name    | <i>machinename</i> - 910 Server Map                                                           |
| Data Source Use     | DB                                                                                            |
| Data Source Type    | I                                                                                             |
| Object Owner ID     | Blank                                                                                         |
| Library Name        | SVM910                                                                                        |
| Library List Name   | RDB name of the IBM i<br><b>Note:</b> To find the IBM i RDB name, use the WRKRDBDIRE command. |
| Database Name       | <i>machinename</i> - 910 Server Map                                                           |
| Server Name         | Name of the machine where your database resides                                               |
| Platform            | IBM i                                                                                         |
| Use Table Owner     | Blank                                                                                         |
| Use Julian Dates    | Selected                                                                                      |
| Use Decimal Shift   | Selected                                                                                      |
| Support for Updates | Selected                                                                                      |
| OCM Data Source     | Selected                                                                                      |
| IBM i BLOB Support  | Blank                                                                                         |
| LOB Data Source     | Selected                                                                                      |

## 26.11 System

This chart lists the characteristics of the System data source.

| Field                                             | Valid Value for Client Access                                                                 |
|---------------------------------------------------|-----------------------------------------------------------------------------------------------|
| Data Source Name (list includes possible sources) | System - 910                                                                                  |
| Data Source Use                                   | DB                                                                                            |
| Data Source Type                                  | I                                                                                             |
| Object Owner ID                                   | Blank                                                                                         |
| Library Name                                      | SY910                                                                                         |
| Library List Name                                 | RDB name of the IBM i<br><b>Note:</b> To find the IBM i RDB name, use the WRKRDBDIRE command. |
| DLL Name                                          | Blank                                                                                         |
| Database Name (list includes possible databases)  | System - 910                                                                                  |
| Server Name                                       | Name of the machine where your database resides                                               |

| Field               | Valid Value for Client Access |
|---------------------|-------------------------------|
| Platform            | IBM i                         |
| Use Table Owner     | Blank                         |
| Use Julian Dates    | Selected                      |
| Use Decimal Shift   | Selected                      |
| Support for Updates | Selected                      |
| OCM Data Source     | Selected                      |
| IBM i BLOB Support  | Blank                         |
| LOB Data Source     | Selected                      |

## 26.12 Versions

This chart lists the characteristics of the Versions data source.

| Field                                             | Valid Value for Client Access                                                                 |
|---------------------------------------------------|-----------------------------------------------------------------------------------------------|
| Data Source Name (list includes possible sources) | Versions - PD910<br>Versions - PY910<br>Versions - DV910<br>Versions - PS910                  |
| Data Source Use                                   | DB                                                                                            |
| Data Source Type                                  | I                                                                                             |
| Object Owner ID                                   | Blank                                                                                         |
| Library Name (list includes possible libraries)   | COPD910<br>COPY910<br>CODV910<br>COPS910                                                      |
| Library List Name                                 | RDB name of the IBM i<br><b>Note:</b> To find the IBM i RDB name, use the WRKRDBDIRE command. |
| DLL Name                                          | Blank                                                                                         |
| Database Name (list includes possible databases)  | Versions - PD910<br>Versions - PY910<br>Versions - DV910<br>Versions - PS910                  |
| Server Name                                       | Name of the machine where your database resides                                               |
| Platform                                          | IBM i                                                                                         |
| Use Table Owner                                   | Blank                                                                                         |
| Use Julian Dates                                  | Selected                                                                                      |
| Use Decimal Shift                                 | Selected                                                                                      |
| Support for Updates                               | Selected                                                                                      |
| OCM Data Source                                   | Blank                                                                                         |

| Field              | Valid Value for Client Access |
|--------------------|-------------------------------|
| IBM i BLOB Support | Blank                         |
| LOB Data Source    | Selected                      |

---

## Deinstalling the Software

This chapter includes these tasks:

- [Section 27.1, "Understanding the Deinstallation"](#)
- [Section 27.2, "Deinstalling the Software from the Workstations"](#)
- [Section 27.3, "Deinstalling the Local OEE from the Deployment Server"](#)
- [Section 27.4, "Manual Cleanup of a Deinstalled Oracle Database on the Deployment Server"](#)
- [Section 27.5, "Using the OUI Installer to Deinstall JD Edwards EnterpriseOne from the Deployment Server"](#)
- [Section 27.6, "Dropping DB2\400 Libraries"](#)
- [Section 27.7, "Deinstalling the Platform Pack"](#)

### 27.1 Understanding the Deinstallation

The installation and upgrade processes do not automatically remove any JD Edwards EnterpriseOne databases. You should have a database administrator (DBA) for your relational database management system (RDMS) manually remove any unused databases according to the list of databases and associated components, which are provided in this document.

The deinstallation program restricts you from deinstalling a mandatory component without also removing all associated optional components that were previously installed. The relationship between the mandatory and optional components is shown in this table:

| Server            | Mandatory Component                 | Optional Components                                                                                |
|-------------------|-------------------------------------|----------------------------------------------------------------------------------------------------|
| Deployment Server | JD Edwards EnterpriseOne Files      | Production Environment<br>Prototype Environment<br>Development Environment<br>Pristine Environment |
| Enterprise Server | JD Edwards EnterpriseOne Foundation | ES Production<br>ES Prototype<br>ES Development<br>ES Pristine                                     |

## 27.2 Deinstalling the Software from the Workstations

You can remove previous JD Edwards EnterpriseOne installations from workstations by running the deinstallation program as described in the *JD Edwards EnterpriseOne Development Client Installation Guide*.

## 27.3 Deinstalling the Local OEE from the Deployment Server

---

---

**Note:** Oracle products use the term "deinstall" to refer to removing an Oracle product.

---

---

To deinstall the local Oracle database:

1. Either export the local database tablespaces or deinstall JD Edwards EnterpriseOne using Start > Programs > Oracle - <Home\_Name> > Oracle Installation Products > Universal Installer where <Home\_Name> is the name that you gave the installation of EnterpriseOne on the Deployment Server.
2. Locate this file:  
`<Oracle_Home>\deinstall\deinstall.bat`
3. Right click on the file that you located in Step 2 and select **Run as administrator**, where <Oracle\_Home> is the directory where you installed the local Oracle database. For example, your directory might be:  
`c:\Oracle\E1Local`
4. At the end of the deinstallation, verify that the Oracle\_Home directory has been deleted (for example, `c:\Oracle\E1local`). If it still exists, you should attempt to manually delete it.

---

---

**Caution:** Prior to any reinstall an Oracle local database on this same machine, the Oracle\_Home directory (for example, `c:\Oracle\E1local`) must not exist. If you attempt to reinstall the local Oracle database and this directory still exists, it is likely that the new installation will fail.

---

---

**Tip:** You may not be able to delete the Oracle\_Home directory (for example, `c:\Oracle\E1local`) if a process has it locked. In that case, to determine which process(es) has it locked, run the steps in the section of this guide entitled: [Section 3.11.5.4, "Process Explorer"](#).

## 27.4 Manual Cleanup of a Deinstalled Oracle Database on the Deployment Server

If the deinstallation of the OEE database fails for some reason, you need to perform the manual steps in this procedure to completely remove the old installation before reinstalling the database.

1. Deinstall the Deployment Server.

Be sure the Deployment Server is deinstalled before attempting to deinstall the database. This should ensure that no EnterpriseOne tablespaces are imported (attached) to the EnterpriseOne database.

**2. Delete the following registry keys:**

```

\HKEY_LOCAL_MACHINE\SOFTWARE\ORACLE\KEY_E1Local
\HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\ORACLE\KEY_E1Local
\HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\services\ (see Keys below)

```

**Keys.** Delete any keys with names that start with "Oracle" and contain "E1Local".

**3. Delete this directory:**

```
c:\Oracle\E1Local
```

If you cannot delete the E1Local subdirectory because a file in that directory is locked, follow these steps:

- a. Determine which file is locked and which process has the lock on the file. A freeware program called Process Explorer can be helpful in determining this information. You can obtain a free copy of Process Explorer from this web site:

<http://technet.microsoft.com/en-us/sysinternals>

- b. Either kill the locking process with Process Explorer or Microsoft Windows Task Manager or, if the process was started as a Microsoft Windows service, change the Startup Type to Manual and reboot the computer again.

- c. Try again to delete the E1Local subdirectory.

**4. Remove the 64-bit Oracle inventory entries.**

- a. With a text editor (such as Notepad), edit this file:

```
c:\Program Files\Oracle\inventory\ContentsXML\inventory.xml
```

- b. Delete any lines that start with:

```
<HOME NAME="E1Local"
```

- c. Save the file.

**5. Remove the entry from the Windows PATH.**

- a. Navigate to Control Panel > System.
- b. Click **Advanced** system settings on the left.
- c. Click **Environment Variables...** near the bottom.
- d. In the System variables box near the bottom, highlight Path and click the **Edit...** button.
- e. In the Variable value field, delete this value:

```
c:\Oracle\E1Local\bin
```

Be sure to remove the semicolon as well.

- f. Click OK.

**6. Remove the ORACLE\_HOME Windows environment variable.**

- a. Navigate to Control Panel > System.
- b. Click **Advanced** system settings on the left.
- c. Click **Environment Variables...** near the bottom.
- d. In the System variables box near the bottom, highlight **ORACLE\_HOME** and click Delete.

- e. Click OK.

## 27.5 Using the OUI Installer to Deinstall JD Edwards EnterpriseOne from the Deployment Server

You can use the OUI installer to deinstall JD Edwards EnterpriseOne from the Deployment Server. To deinstall the local database, depending on your local database type, refer to the preceding sections of this guide entitled: [Section 27.3, "Deinstalling the Local OEE from the Deployment Server"](#).

To use the OUI installer to deinstall JD Edwards EnterpriseOne from the Deployment Server:

1. Log on to the Deployment Server as a user with Administrator rights.

---

---

**Caution:** Ensure that the Administrator account name that you use does not contain any special characters.

---

---

2. If JD Edwards EnterpriseOne is running on the Deployment Server, stop it.


Use Task Manager to verify these processes are stopped:

- `activConsole.exe`
- `jdenet_n.exe`
- `java.exe`


If any of these processes are running, either wait for them to finish or kill them via Task Manager.

3. Go to Start > All Programs > Oracle - JDE\_DEP910\_Home > Oracle Installation Products > Universal Installer.





4. On Oracle Universal Installer: Welcome, select the **Deinstall Products ...** button.




5. On Inventory, with the Contents tab select, put a check mark next to the Oracle Homes for the Deployment Server Home.


For example, if you followed recommendation in this guide the Oracle Home for your Deployment Server is:

**JDE\_DEP910\_HOME**


6. Select the **Remove** button.




7. On Confirmation, verify that you want to deinstall the listed components and their dependent components and if so, select the **Yes** button.



The Remove dialog indicates the progress of the deinstall action.



8. When the deinstallation process completes, the Inventory is shown again. The products you selected for deinstallation should no longer be displayed in the inventory.
9. Select the **Close** button.



You are returned to the Oracle Universal Installer: Welcome screen.

10. On Oracle Universal Installer: Welcome, select the **Cancel** button to exit the Oracle Universal Installer.

## 27.6 Dropping DB2\400 Libraries

This section lists the DB2\400 libraries that must be manually dropped by a DBA. This is the list of libraries that were created by the JD Edwards EnterpriseOne 9.0 Installation of the Platform Pack on your Enterprise or Database Server for your JD Edwards EnterpriseOne installation, or from a previous JD Edwards EnterpriseOne installation.

By design, these libraries are not automatically removed by the JD Edwards EnterpriseOne deinstallation program. You should have a DBA for your RDBMS manually remove any unused libraries listed in the table below.

| JD Edwards EnterpriseOne Component | DB2\400 Library Name |
|------------------------------------|----------------------|
| Foundation                         | SY910                |
|                                    | OL910                |
|                                    | DD910                |
|                                    | SVM910               |
|                                    | OWJRNL               |
| Production                         | COPD910              |
|                                    | PRODDTA              |
|                                    | PRODCTL              |
| Pristine                           | COPS910              |
|                                    | PS910DTA             |
|                                    | PS910CTL             |
| Development                        | CODV910              |
|                                    | TESTDTA              |
|                                    | TESTCTL              |
| Prototype                          | COPY910              |
|                                    | CRPDTA               |
|                                    | CRPCTL               |

## 27.7 Deinstalling the Platform Pack

You should always use the JD Edwards EnterpriseOne OUI-based installation program to remove JD Edwards EnterpriseOne. If you manually remove the software, the deinstallation cannot be guaranteed to be complete and, as a result, subsequent reinstallation of JD Edwards EnterpriseOne may be hindered.


To run the JD Edwards EnterpriseOne Platform Pack Installer for the IBM i Enterprise Server:

1. Log on to the same Microsoft Windows machine where you initially ran the Platform Pack installer for IBM i. If you followed the recommendation, this will be the JD Edwards EnterpriseOne Deployment Server.
2. Locate the directory where you extracted the install images. If you followed the recommendation, the directory is:

c:\IBMPPack




3. In the extracted structure, locate the setup.exe file under the \install subdirectory, right-click on it, and select Run as Administrator.



4. On Oracle Universal Installer, Welcome, click the **Deinstall Products...** button.






5. Turn on the check box next to the Oracle Home for the Platform Pack and expand the node to show all installed components. For example, the Oracle Home might be named **JDE\_PPack910\_Home**.

---


**Note:** At this step, you should select only the Oracle Home that is associated with this particular OUI. That is, the Oracle Home name that you select on this screen should match the Oracle Home name that you selected from Start > Programs.

---


6. Click the **Remove...** button.




7. On Confirmation, verify that you want to deinstall the listed components and their dependent components and if so, select the **Yes** button.




8. On User Input, you must enter the password for the account you used to run the install. For example, enter the password for QSECOFR. Then click on OK
9. Click the OK button.



The Remove dialog indicates the progress of the deinstall action.



10. When the deinstallation process complete, the Inventory is shown again. The products you selected for deinstallation should no longer be displayed in the inventory.
11. Select the **Close** button.





You are returned to the Oracle Universal Installer: Welcome screen.

12. On Oracle Universal Installer: Welcome, select the **Cancel** button to exit the Oracle Universal Installer.
13. Verify that the installation directory (Oracle Home) has been deleted. If it still exists, you can delete it.



# Understanding IBM i Databases

This appendix presents a diagram of the JD Edwards EnterpriseOne relationships with the IBM i databases.

